

Oracle® Database

Oracle Clusterware and Oracle Real Application Clusters
Installation Guide

10g Release 2 (10.2) for AIX

B14201-01

August 2005

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Installation Guide, 10g Release 2 (10.2) for AIX

B14201-01

Copyright © 2004, 2005, Oracle. All rights reserved.

Primary Authors: David Austin, Mark Bauer, Kevin Flood, Emily Murphy, Lyju Vadassery, Douglas Williams

Contributing Authors: Jonathan Creighton, Pat Huey, Raj Kumar

Contributors: Chris Allison, Karin Brandauer, Sudip Datta, Rajiv Jayaraman, Roland Knapp, Diana Lorentz, Barb Lundhild, Vijay Lunawat, Sundar Matpadi, John Patrick McHugh, Randy Neville, Philip Newlan, Michael Polaski, Dipak Saggi, Sudheendra Sampath, Janelle Simmons, Clive Simpkins, Khethavath P. Singh, Nitin Vengurlekar, Gary Young

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software—Restricted Rights (June 1987). Oracle Corporation, 500 Oracle Parkway, Redwood City, CA 94065

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Retek are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

Send Us Your Comments	ix
Preface	xi
Intended Audience.....	xi
Documentation Accessibility	xi
Structure	xii
Related Documents	xiv
Conventions	xv
What's New in Oracle Database 10g Oracle Real Application Clusters Installation and Configuration?	xix
Oracle Database 10g Release 2 (10.2) New Features for RAC Installation and Configuration	xix
Part I Oracle Clusterware and Oracle Real Application Clusters Installation Planning and Requirements	
1 Introduction to Installing and Configuring Oracle Clusterware and Oracle Real Application Clusters	
Oracle Clusterware and Oracle Real Application Clusters Documentation Overview	1-1
Oracle Real Application Clusters Administration and Deployment Guide.....	1-2
General System Installation Requirements	1-2
Overview of Cluster Verification Utility	1-2
Overview of Oracle Universal Installer	1-3
Overview of Upgrading and Multiple-release Systems	1-3
Hardware Requirements for Oracle Clusterware and Oracle Real Application Clusters.....	1-3
Software Requirements for Oracle Clusterware and Oracle Real Application Clusters	1-4
Configuration Tasks for Oracle Clusterware and Oracle Real Application Clusters	1-5
Pre-Installation, Installation, and Post-Installation Overview	1-6
Pre-Installation Overview for Oracle Database 10g Real Application Clusters	1-6
Installation Overview for Oracle Database 10g Real Application Clusters.....	1-6
Post-Installation Overview for Oracle Database 10g Real Application Clusters	1-7
Oracle Universal Installer and Real Application Clusters	1-7
Storage Considerations for Installing Oracle Database 10g Real Application Clusters	1-8
Overview of Automatic Storage Management	1-8
Shared Storage for Database Recovery Area.....	1-10

Additional Considerations for Using Oracle Database 10g Features in RAC	1-11
Oracle Database 10g and Real Application Clusters Components	1-11
Oracle Clusterware	1-11
The Installed Real Application Clusters Components.....	1-12
Oracle Database 10g Real Application Clusters Release Compatibility	1-12
Required Operating System Groups	1-13
Cloning Oracle Clusterware and RAC in Grid Environments	1-14
Cloning Oracle Clusterware Homes	1-14
Cloning RAC Homes	1-15

Part II Oracle Clusterware and Oracle Real Application Clusters Pre-Installation Procedures

2 Pre-Installation Tasks

Understanding and Using Cluster Verification Utility	2-1
Entering Cluster Verification Utility Commands.....	2-2
Using CVU to Determine if Installation Prerequisites are Complete	2-2
Using the Cluster Verification Utility Help.....	2-2
Using Cluster Verification Utility with Oracle 10g Release 1	2-3
Verbose Mode and "Unknown" Output	2-3
Logging In to the System as root	2-3
Creating Required Operating System Groups and User	2-4
Creating the Oracle Inventory Group	2-6
Creating the OSDBA Group	2-7
Creating an OSOPER Group (Optional)	2-7
Creating a HAGSUSER Group (Optional)	2-7
Creating the Oracle Software Owner User	2-7
Verifying That the User nobody Exists	2-9
Creating Identical Users and Groups on Other Cluster Nodes.....	2-9
Configuring SSH on All Cluster Nodes	2-11
Configuring SSH on Cluster Member Nodes	2-11
Enabling SSH User Equivalency on Cluster Member Nodes.....	2-13
Preventing Oracle Clusterware Installation Errors Caused by stty Commands.....	2-14
Configuring Shell Limits, System Configuration, and Network Tuning Parameters	2-15
Configure Shell Limits.....	2-15
Configure System Configuration Parameters	2-16
Configure Network Tuning Parameters	2-16
Configuring the oracle User's Environment	2-18
Checking the Hardware Requirements	2-19
Checking the Network Requirements	2-21
Checking the Network Setup with CVU	2-23
Checking the Software Requirements	2-23
Running the rootpre.sh Script	2-28
Checking the Hardware and Operating System Setup with CVU	2-28
Checking the Operating System Requirements Setup with CVU	2-29
Identifying Required Software Directories	2-29
Identifying or Creating an Oracle Base Directory	2-31

Creating the Oracle Clusterware Home Directory.....	2-33
Stopping Existing Oracle Processes for Upgrades or Co-existing Databases	2-35

3 Configuring Oracle Clusterware and Oracle Database Storage

Reviewing Storage Options for Oracle Clusterware, Database, and Recovery Files.....	3-1
Overview of Storage Options	3-1
Overview of Oracle Clusterware Storage Options.....	3-1
Overview of Oracle Database and Recovery File Options.....	3-1
General Storage Considerations	3-2
After You Have Selected Disk Storage Options	3-3
Checking for Available Shared Storage with CVU	3-4
Configuring Storage for Oracle Clusterware Files on a Supported Shared File System	3-4
Requirements for Using a File System for Oracle Clusterware Files.....	3-4
Creating Required Directories for Oracle Clusterware Files on Shared File Systems	3-5
Configuring Storage for Oracle Clusterware Files on Raw Devices	3-7
Identifying Required Raw Partitions for Clusterware Files	3-7
Configuring Raw Disk Devices for Oracle Clusterware Without HACMP or GPFS.....	3-8
Configuring Raw Logical Volumes for Oracle Clusterware.....	3-10
Creating a Volume Group for Oracle Clusterware	3-11
Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group	3-13
Importing the Volume Group on the Other Cluster Nodes.....	3-14
Activating the Volume Group in Concurrent Mode on All Cluster Nodes	3-15
Choosing a Storage Option for Oracle Database Files.....	3-15
Configuring Disks for Automatic Storage Management	3-15
Identifying Storage Requirements for ASM.....	3-16
Using an Existing ASM Disk Group.....	3-18
Configuring Database File Storage for ASM and Raw Devices	3-19
Configuring Database File Storage on Raw Devices	3-22
Identifying Required Raw Partitions for Database Files	3-23
Configuring Raw Disk Devices for Database File Storage Without HACMP or GPFS	3-24
Configuring Raw Logical Volumes for Database File Storage	3-28
Creating a Volume Group for Database Files	3-28
Creating Database File Raw Logical Volumes in the New Volume Group.....	3-31
Importing the Database File Volume Group on the Other Cluster Nodes.....	3-33
Activating the Database File Volume Group in Concurrent Mode on All Cluster Nodes...	3-34
Creating the Database Configuration Assistant Raw Device Mapping File	3-34

Part III Installing Oracle Clusterware and Oracle Database 10g with Oracle Real Application Clusters, Creating Oracle Real Application Clusters Databases, and Performing Post-Installation Tasks

4 Installing Oracle Clusterware

Verifying Oracle Clusterware Requirements with CVU	4-1
Troubleshooting Oracle Clusterware Setup	4-2
Preparing to Install Oracle Clusterware with OUI.....	4-3
Installing Oracle Clusterware with OUI	4-7

Running OUI to Install Oracle Clusterware.....	4-7
Troubleshooting Oracle Clusterware Installation Verification	4-7
Oracle Clusterware Background Processes	4-9

5 Installing Oracle Database 10g with Real Application Clusters

Verifying System Readiness for installing Oracle Database with CVU	5-1
Troubleshooting Installation Setup for AIX.....	5-2
Selecting a Configuration Option	5-3
Automatic Storage Management Configuration	5-4
Database Configuration Type Descriptions	5-4
General Purpose, Transaction Processing, and Data Warehouse Configuration Types ..	5-4
Using the Advanced Configuration Type	5-5
Behavior of OUI, DBCA, and Other Assistants During Installation	5-5
Installation of Oracle Database 10g with RAC Using the Oracle Universal Installer	5-5
De-Installing Real Application Clusters Software	5-7
De-Installing Oracle Database 10g RAC Software and ASM.....	5-7
De-Installing Oracle Clusterware	5-9

6 Creating Real Application Clusters Databases with Database Configuration Assistant

Using Database Configuration Assistant in Real Application Clusters	6-1
Benefits of Using Database Configuration Assistant	6-2
Oracle Real Application Clusters High Availability Services	6-2
Service Configuration and Instance Preferences	6-2
Transparent Application Failover Policies	6-2
Automatic Listener Migration from Release 10.1 to 10.2	6-3
Verifying Requirements for DBCA	6-3
Creating an Oracle Real Application Clusters Database with DBCA	6-4
Deleting a Real Application Clusters Database with DBCA	6-6

7 Oracle Real Application Clusters Post-Installation Procedures

Required Post-Installation Tasks	7-1
Back Up the Voting Disk After Installation.....	7-1
Download and Install Patches.....	7-1
Configure Oracle Products	7-2
Verify Required Post-Installation is Completed.....	7-2
Recommended Post-Installation Tasks	7-2
Verifying Enterprise Manager Operations	7-3
Recommended Post-Installation Tasks	7-3
Back Up the root.sh Script	7-3
Set Up Users Accounts	7-3
Set the ORACLE_HOME and ORACLE_SID Environments	7-3

Part IV Oracle Real Application Clusters Environment Configuration

8 Configuring the Server Parameter File in Oracle Real Application Clusters Environments

Parameter Files and Real Application Clusters.....	8-1
Using Server Parameter Files in Real Application Clusters	8-1
Location of The Server Parameter File	8-2
Parameter File Search Order in Real Application Clusters.....	8-2
Migrating to the Server Parameter File in Real Application Clusters Environments	8-3
Server Parameter File Placement in Real Application Clusters	8-3
Procedures for Migrating to the Server Parameter File	8-3
Server Parameter File Errors in Real Application Clusters.....	8-4

9 Understanding the Oracle Real Application Clusters Installed Configuration

Understanding the Configured Environment in Real Application Clusters.....	9-1
Oracle Cluster Registry in Oracle Real Application Clusters	9-1
Oratab Configurations for Oracle Real Application Clusters	9-2
Database Components Created Using Database Configuration Assistant.....	9-2
Tablespaces and Data files	9-2
Control Files	9-3
Redo Log Files	9-3
Managing Undo Tablespaces in Real Application Clusters	9-3
Initialization Parameter Files.....	9-4
Configuring Service Registration-Related Parameters in Real Application Clusters	9-4
Configuring the Listener File (listener.ora).....	9-5
Local Listeners	9-5
Multiple Listeners	9-5
How Oracle Database Uses the Listener (listener.ora File).....	9-5
Listener Registration and PMON Discovery	9-6
Directory Server Access (ldap.ora File)	9-6
Net Service Names (tnsnames.ora File).....	9-7
Net Services Profile (sqlnet.ora File).....	9-11

Part V Oracle Clusterware and Oracle Real Application Clusters Installation and Configuration Reference Information

A Troubleshooting the Oracle Clusterware and Oracle Real Application Clusters Installation Process

Troubleshooting the Oracle Real Application Clusters Installation.....	A-1
General Installation Issues	A-1
Real Application Clusters Installation Error Messages	A-2
Performing Cluster Diagnostics During Real Application Clusters Installations	A-2

B Using Scripts to Create Oracle Real Application Clusters Databases

Creating a Database Using Scripts.....	B-1
--	-----

C Configuring Raw Devices for Oracle Real Application Clusters

Raw Devices Required by DBCA for Non-Cluster Environments.....	C-1
Planning Your Raw Device Creation Strategy.....	C-1

D Converting to Oracle Real Application Clusters from Single-Instance Oracle Databases

Single-Instance to Cluster-Enabled Conversion Administrative Issues.....	D-1
Converting with DBCA.....	D-2
Single Instance on a Non-Cluster Computer to Oracle Database 10g with RAC.....	D-2
Back Up the Original Single-Instance Database.....	D-2
Perform the Pre-Installation Steps.....	D-3
Set Up the Cluster.....	D-3
Validate the Cluster.....	D-3
Copy the Preconfigured Database Image.....	D-3
Install Oracle Database 10g Software with Real Application Clusters.....	D-3
Single Instance on a Cluster to Oracle Database 10g RAC.....	D-4
Single Instance on a Cluster Running from a Cluster-Enabled Oracle Home.....	D-4
Single Instance on a Cluster Running from a RAC-Disabled Oracle Home.....	D-7
Single Instance on a Cluster Running from a Single-Instance Installed Oracle Home....	D-7
Converting with rconfig and Oracle Enterprise Manager.....	D-7
Prerequisites for Converting to RAC Databases.....	D-8
Single-Instance to RAC Conversion Scenarios.....	D-8
Converting Single-Instance Databases to RAC Using rconfig.....	D-9
Example of an rconfig XML Input File.....	D-10
Converting Single-Instance Databases to RAC Using Oracle Enterprise Manager.....	D-11
Converting Single-Instance ASM to Cluster ASM.....	D-12
Post-Conversion Steps.....	D-13

E Directory Structure for Oracle Database 10g Oracle Real Application Clusters Environments

Understanding the Real Application Clusters Directory Structure.....	E-1
Directory Structures for Real Application Clusters.....	E-1

F How to Stop Processes in an Existing Oracle Real Application Clusters Database

Back Up the Oracle Real Application Clusters Database.....	F-1
Shut Down Oracle Real Application Clusters Databases.....	F-1
Stop All Oracle Processes.....	F-1
Stopping Oracle Clusterware or Cluster Ready Services Processes.....	F-2
Stopping Oracle Database 10g Processes Before Adding Products or Upgrading.....	F-2

Index

Send Us Your Comments

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Installation Guide 10g Release 2 (10.2) for AIX

B14201-01

Oracle welcomes your comments and suggestions on the quality and usefulness of this publication. Your input is an important part of the information used for revision.

- Did you find any errors?
- Is the information clearly presented?
- Do you need more information? If so, where?
- Are the examples correct? Do you need more examples?
- What features did you like most about this manual?

If you find any errors or have any other suggestions for improvement, please indicate the title and part number of the documentation and the chapter, section, and page number (if available). You can send comments to us in the following ways:

- Electronic mail: infodev_us@oracle.com
- FAX: (650) 506-7227. Attn: Server Technologies Documentation Manager
- Postal service:

Oracle Corporation
Server Technologies Documentation Manager
500 Oracle Parkway, Mailstop 4op11
Redwood Shores, CA 94065
USA

If you would like a reply, please give your name, address, telephone number, and electronic mail address (optional).

If you have problems with the software, please contact your local Oracle Support Services.

Preface

Oracle Database Oracle Clusterware Oracle Real Application Clusters Installation and Configuration Guide explains how to install and configure Oracle Clusterware and Oracle Real Application Clusters (RAC). This preface contains the following topics:

- [Intended Audience](#)
- [Documentation Accessibility](#)
- [Structure](#)
- [Related Documents](#)
- [Conventions](#)

Intended Audience

Oracle Database Oracle Clusterware Oracle Real Application Clusters Installation and Configuration Guide provides configuration information for network and system administrators, and database installation information for database administrators (DBAs) who install and configure RAC.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, seven days a week. For TTY support, call 800.446.2398.

Structure

This document is divided into five parts. It contains the following chapters:

Part I: "Oracle Clusterware and Oracle Real Application Clusters Installation Planning and Requirements"

Part I introduces the Oracle Clusterware and RAC installation process.

Chapter 1, "Introduction to Installing and Configuring Oracle Clusterware and Oracle Real Application Clusters"

This chapter describes the RAC installation process and provides Oracle Clusterware and RAC installation planning information.

Part II: Oracle Clusterware and Oracle Real Application Clusters Pre-Installation Procedures

Part II describes the platform-specific pre-installation procedures for installing Oracle Clusterware and RAC.

Chapter 2, "Pre-Installation Tasks"

This chapter describes the server pre-installation procedures for installing Oracle Clusterware and RAC.

Chapter 3, "Configuring Oracle Clusterware and Oracle Database Storage"

This chapter describes pre-installation procedures for configuring storage for Oracle Clusterware and Oracle Real Application Clusters.

Part III: "Installing Oracle Clusterware and Oracle Database 10g with Oracle Real Application Clusters, Creating Oracle Real Application Clusters Databases, and Performing Post-Installation Tasks"

Part III describes how to install Oracle Clusterware and Oracle Database 10g with Real Application Clusters for AIX.

Chapter 4, "Installing Oracle Clusterware"

This chapter describes how to install Oracle Clusterware for AIX.

Chapter 5, "Installing Oracle Database 10g with Real Application Clusters"

This chapter describes how to install Oracle Database 10g with Oracle Real Application Clusters on all operating systems.

Chapter 6, "Creating Real Application Clusters Databases with Database Configuration Assistant"

This chapter explains how to use Database Configuration Assistant to create RAC databases.

Chapter 7, "Oracle Real Application Clusters Post-Installation Procedures"

This chapter describes the post-installation tasks for RAC.

Part IV: Oracle Real Application Clusters Environment Configuration

Part IV provides Oracle Database 10g Real Application Clusters environment configuration information.

Chapter 8, "Configuring the Server Parameter File in Oracle Real Application Clusters Environments"

This chapter describes the use of the server parameter file (SPFILE) in Oracle Real Application Clusters.

Chapter 9, "Understanding the Oracle Real Application Clusters Installed Configuration"

This chapter describes the Oracle Database 10g Real Application Clusters installed configuration.

Part V: Oracle Clusterware and Oracle Real Application Clusters Installation and Configuration Reference Information

Part V provides reference information for the installation and configuration of RAC.

Appendix A, "Troubleshooting the Oracle Clusterware and Oracle Real Application Clusters Installation Process"

This appendix provides RAC installation and configuration troubleshooting information.

Appendix B, "Using Scripts to Create Oracle Real Application Clusters Databases"

This appendix explains how to use scripts in RAC.

Appendix C, "Configuring Raw Devices for Oracle Real Application Clusters"

This appendix explains how to configure shared disk subsystems using raw devices in RAC environments.

Appendix D, "Converting to Oracle Real Application Clusters from Single-Instance Oracle Databases"

This appendix describes how to convert to Oracle Database 10g RAC from single-instance Oracle databases.

Appendix E, "Directory Structure for Oracle Database 10g Oracle Real Application Clusters Environments"

This appendix describes the directory structure for the installed RAC software.

Appendix F, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"

This appendix describes how to shut down processes running in an existing RAC database in preparing to install patch updates or making other changes.

Related Documents

For more information, refer to the following Oracle resources:

Oracle Real Application Clusters Documentation

- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*

Error messages are available only online, or by using Tahiti, the Oracle documentation search tool.

Installation Guides

- *Oracle Diagnostics Pack Installation*

Operating System-Specific Administrative Guides

- *Oracle Database Administrator's Reference, 10g Release 2 (10.2) for UNIX Systems*
- *Oracle Database Platform Guide for Microsoft Windows (32-Bit)*
- *Oracle Database System Administration Guide 10g Release 2 (10.2) for IBM z/OS (OS/390)*

Oracle Database 10g Real Application Clusters Management

- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*
- *Oracle Database 2 Day DBA*
- *Getting Started with the Oracle Diagnostics Pack*

Generic Documentation

- *Oracle Database New Features*
- *Oracle Database Net Services Administrator's Guide*
- *Oracle Database Concepts*
- *Oracle Database Reference*

Printed documentation is available for sale in the Oracle Store at the following Web site:

<http://oraclestore.oracle.com/>

To download free release notes, installation documentation, white papers, or other collateral, please visit the Oracle Technology Network (OTN). You must register online before using OTN; registration is free and can be done at the following Web site:

<http://otn.oracle.com/membership/>

If you already have a username and password for OTN, then you can go directly to the documentation section of the OTN Web site at the following Web site:

<http://otn.oracle.com/documentation/>

Oracle error message documentation is available only in HTML. You can browse the error messages by range in the Documentation directory of the installation media. When you find a range, use your browser's "find in page" feature to locate a specific

message. When connected to the Internet, you can search for a specific error message using the error message search feature of the Oracle online documentation.

Printed documentation is available for sale in the Oracle Store at the following Web site:

<http://oraclestore.oracle.com/>

To download free release notes, installation documentation, white papers, or other collateral, please visit the Oracle Technology Network (OTN). You must register online before using OTN; registration is free. Register for OTN at the following Web site:

<http://otn.oracle.com/membership/>

If you already have a username and password for OTN, then you can go directly to the documentation section of the OTN Web Site:

<http://otn.oracle.com/documentation/>

Conventions

This section describes the conventions used in the text and code examples of this documentation set. It describes:

- [Conventions in Text](#)
- [Conventions in Code Examples](#)

Conventions in Text

We use various conventions in text to help you more quickly identify special terms. The following table describes those conventions and provides examples of their use.

Convention	Meaning	Example
Bold	Bold typeface indicates terms that are defined in the text or terms that appear in a glossary, or both.	When you specify this clause, you create an index-organized table .
<i>Italics</i>	Italic typeface indicates book titles or emphasis.	<i>Oracle Database Concepts</i> Ensure that the recovery catalog and target database do <i>not</i> reside on the same disk.
UPPERCASE monospace (fixed-width) font	Uppercase monospace typeface indicates elements supplied by the system. Such elements include parameters, privileges, datatypes, RMAN keywords, SQL keywords, SQL*Plus or utility commands, packages and methods, as well as system-supplied column names, database objects and structures, usernames, and roles.	You can specify this clause only for a NUMBER column. You can back up the database by using the BACKUP command. Query the TABLE_NAME column in the USER_TABLES data dictionary view. Use the DBMS_STATS.GENERATE_STATS procedure.

Convention	Meaning	Example
lowercase monospace (fixed-width) font	Lowercase monospace typeface indicates executables, filenames, directory names, and sample user-supplied elements. Such elements include computer and database names, net service names, and connect identifiers, as well as user-supplied database objects and structures, column names, packages and classes, usernames and roles, program units, and parameter values. Note: Some programmatic elements use a mixture of UPPERCASE and lowercase. Enter these elements as shown.	Enter <code>sqlplus</code> to start SQL*Plus. The password is specified in the <code>orapwd</code> file. Back up the data files and control files in the <code>/disk1/oracle/dbs</code> directory. The <code>department_id</code> , <code>department_name</code> , and <code>location_id</code> columns are in the <code>hr.departments</code> table. Set the <code>QUERY_REWRITE_ENABLED</code> initialization parameter to <code>true</code> . Connect as <code>oe</code> user. The <code>JRepUtil</code> class implements these methods.
lowercase italic monospace (fixed-width) font	Lowercase italic monospace font represents placeholders or variables.	You can specify the <i>parallel_clause</i> . Run <i>old_release.SQL</i> where <i>old_release</i> refers to the release you installed prior to upgrading.

Conventions in Code Examples

Code examples illustrate SQL, PL/SQL, SQL*Plus, or other command-line statements. They are displayed in a monospace (fixed-width) font and separated from normal text as shown in this example:

```
SELECT username FROM dba_users WHERE username = 'MIGRATE';
```

The following table describes typographic conventions used in code examples and provides examples of their use.

Convention	Meaning	Example
[]	Brackets enclose one or more optional items. Do not enter the brackets.	DECIMAL (<i>digits</i> [, <i>precision</i>])
{ }	Braces enclose two or more items, one of which is required. Do not enter the braces, and do not enter more than one option.	{ENABLE DISABLE}
	A vertical bar represents a choice of two or more options within brackets or braces. Enter one of the options. Do not enter the vertical bar.	{ENABLE DISABLE} [COMPRESS NOCOMPRESS]
...	Horizontal ellipsis points indicate either: <ul style="list-style-type: none"> That we have omitted parts of the code that are not directly related to the example That you can repeat a portion of the code 	CREATE TABLE ... AS <i>subquery</i> ; SELECT <i>col1</i> , <i>col2</i> , ... , <i>coln</i> FROM employees;

Convention	Meaning	Example
.	Vertical ellipsis points indicate that we have omitted several lines of code not directly related to the example.	<pre>SQL> SELECT NAME FROM V\$DATAFILE; NAME ----- /fs1/dbs/tbs_01.dbf /fs1/dbs/tbs_02.dbf . . . /fs1/dbs/tbs_09.dbf 9 rows selected.</pre>
Other notation	You must enter symbols other than brackets, braces, vertical bars, and ellipsis points as shown.	<pre>acctbal NUMBER(11,2); acct CONSTANT NUMBER(4) := 3;</pre>
<i>Italics</i>	Italicized text indicates placeholders or variables for which you must supply particular values.	<pre>CONNECT SYSTEM/<i>system_password</i> DB_NAME = <i>database_name</i></pre>
UPPERCASE	Uppercase typeface indicates elements supplied by the system. We show these terms in uppercase in order to distinguish them from terms you define. Unless terms appear in brackets, enter them in the order and with the spelling shown. However, because these terms are not case sensitive, you can enter them in lowercase.	<pre>SELECT last_name, employee_id FROM employees; SELECT * FROM USER_TABLES; DROP TABLE hr.employees;</pre>
lowercase	Lowercase typeface indicates programmatic elements that you supply. For example, lowercase indicates names of tables, columns, or files. Note: Some programmatic elements use a mixture of UPPERCASE and lowercase. Enter these elements as shown.	<pre>SELECT last_name, employee_id FROM employees; sqlplus hr/hr CREATE USER mjones IDENTIFIED BY ty3MU9;</pre>

What's New in Oracle Database 10g Oracle Real Application Clusters Installation and Configuration?

This section describes Oracle Database 10g Release 2 (10.2) features as they pertain to the installation and configuration of Oracle Real Application Clusters (RAC). The topic in this section is:

- [Oracle Database 10g Release 2 \(10.2\) New Features for RAC Installation and Configuration](#)

Note: Updates from the preceding 10.x releases are preceded by the release number, in parentheses. For example: (10.1). Where there are lists of updates to a feature that contain multiple releases, these releases are preceded by the release number in parentheses as follows where *feature* is the description of the feature:

- (10.1) *feature*
 - (10.2) *feature*
-
-

Oracle Database 10g Release 2 (10.2) New Features for RAC Installation and Configuration

- Oracle Database 10g Release 2 (10.2) is provided with Cluster Verification Utility. Cluster Verification Utility (CVU) is a validation tool that you can use to check whether or not your cluster is properly configured, to avoid installation and database creation failures. It provides the following cluster setup checks:
 - The cluster configuration meets the requirements for installing Oracle Clusterware
 - The cluster configuration meets the requirements for Real Application Clusters installation
 - The cluster configuration meets the requirements for creating a database with Oracle Real Application Clusters, or meets the requirements for a change in database configuration

You can use the CVU command-line interface:

- To validate cluster components individually, including node connectivity, and proper configuration of administrative privileges, Oracle Cluster Registry

(OCR), Oracle Clusterware, and other required components for Real Application Clusters

- To validate a pre-defined set of requirements, including the proper setup for node connectivity, shared storage accessibility, integrity of the Oracle Clusterware stack, and other requirements that a system must meet for a specific stage of Oracle Clusterware or RAC database installation or configuration.

CVU is available on the Oracle 10g Release 2 (10.2) installation media. You can either run CVU from the installation media, or run it from your local system after installation to perform configuration checks before installing Oracle software. CVU commands to perform installation checks are provided in this installation guide.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for detailed information about CVU

- With Oracle Database 10g Release 2 (10.2), you can now create duplicates of cluster nodes (or *clone* a node) using an image file. In addition, cloning is now the preferred method for adding nodes. The process for cloning, as well as details about using non-interactive (silent) installation scripts, is described in *Oracle Universal Installer and OPatch User's Guide*.

Both Oracle Clusterware and Oracle Real Application Clusters can be cloned. You can also use Oracle Enterprise Manager Database Control and Grid Control to perform cloning.

- With Oracle Database 10g Release 2 (10.2), Cluster Ready Services, or CRS, is now called Oracle Clusterware.
- Oracle Database 10g Release 2 (10.2) enables rolling upgrades from Oracle Database 10g Release 1 (10.1) Cluster Ready Services to Oracle Database 10g Release 2 (10.2) Oracle Clusterware.

During Oracle Clusterware installation, if Oracle Universal Installer (OUI) detects a 10g Release 1 (10.1) Cluster Ready Services installation, then OUI provides the option to install Oracle Clusterware across all nodes in the cluster, or across a subset of nodes in the cluster. During Oracle Clusterware installation, Oracle Database 10g Release 1 (10.1) Cluster Ready Services remains available on nodes that are not being upgraded.

- Starting with Oracle Database 10g Release 2 (10.2), Oracle Clusterware should be installed in a separate Oracle Clusterware home directory. This is a change to the Optimal Flexible Architecture (OFA) rules. You should not install Oracle Clusterware in a release-specific Oracle home mount point, typically `/u01/app/oracle/product/10.2.0`, as succeeding versions of Oracle Clusterware will overwrite the Oracle Clusterware installation in the same path. Also, if Oracle Clusterware 10g Release 2 (10.2) detects an existing Oracle Cluster Ready Services installation, then it overwrites the existing installation in the same path.
- Oracle Database 10g Release 2 (10.2) Oracle Clusterware installation provides the option to use a Cluster Configuration File. The Cluster Configuration File simplifies Oracle Clusterware installation in situations such as installing in test environments, or installing Oracle Clusterware on a large number of nodes.

- With Oracle Database 10g Release 2 (10.2), Database Configuration Assistant (DBCA) provides a simplified procedure for creating an Automatic Storage Management (ASM) instance and for configuring disk groups.
- With Oracle Database 10g Release 2 (10.2), Automatic Storage Management should be installed in a separate ASM home directory. This is a change to the Optimal Flexible Architecture (OFA) rules. To install ASM in its own home directory, you must run the database OUI twice. The first time you run the database OUI, install the ASM home. The second time you run the database OUI, install the database with RAC home.
- With Oracle Database 10g Release 2 (10.2), a single ASM instance for each node is now able to serve disk groups to all the database instances in the cluster, whether or not database instances are configured with the RAC parameter turned on in the database parameter file. This change simplifies managing the cluster, because you do not need to distribute disks across multiple ASM instances statically. Instead, you can manage all disks with a single cluster of ASM instances.
- (10.1) Oracle Database 10g with RAC is available in both Standard Edition and Enterprise Edition.
- (10.1) Oracle Database 10g installation requires you to perform a two-phase process in which you run Oracle Universal Installer (OUI) twice. The first phase installs Oracle Clusterware 10g Release 2 (10.2) and the second phase installs the Oracle Database 10g software with RAC. The installation also enables you to create and configure services for your RAC environment.

(10.1) If you have a previous Oracle Database version with RAC or Oracle Parallel Server, then OUI activates Database Upgrade Assistant (DBUA) to automatically upgrade your previous release Oracle Database. DBUA can upgrade the following to Oracle Database 10g Release 2 (10.2): Oracle8i (8.1.7.4) Oracle Parallel Server databases; Oracle9i (9.0.1.4 and higher) and Oracle 9i (9.2.0.4 and higher) RAC databases; and can upgrade 10.1.0.2 and higher RAC databases, including those using ASM. It can also upgrade ASM 10.1 to ASM 10.2.

See Also: *Oracle Database Upgrade Guide* for information about how to plan for upgrading an existing database

- Oracle Database 10g Release 2 (10.2) Oracle Clusterware contains the cluster management software required to support Oracle Database 10g RAC databases. Oracle Clusterware also provides high availability components that provide many system management features, including determining node availability, cluster group membership, and locking services for Oracle Database processes. The components of Oracle Clusterware interact with third-party vendor clusterware, if present, to coordinate cluster membership information.

In addition, while continuing to be required for RAC databases, Oracle Clusterware is also available for use with single-instance databases and applications that you deploy on clusters. The API libraries required for use with single-instance databases are provided with the Oracle Client installation media.

With this release, the following updates have been made to Oracle Clusterware:

- The Oracle Database cluster manager on database releases previous to 10g Release 1 was referred to as "Cluster Manager." In Oracle Database 10g releases, the cluster manager role is performed by Cluster Synchronization Services (CSS), a component of Oracle Clusterware, on all platforms. The Cluster Synchronization Service Daemon (CSSD) performs this function.

- With Oracle Database 10g Release 2 (10.2) with RAC, Oracle Clusterware provides for the creation of a mirrored Oracle Cluster Registry (OCR) file, enhancing cluster reliability.
- With Oracle Database 10g Release 2 (10.2) with RAC, CSS has been modified to allow you to configure CSS with multiple voting disks. In 10g Release 1 (10.1), you could configure only one voting disk. By enabling multiple voting disk configuration, the redundant voting disks allow you to configure a RAC database with multiple voting disks on independent shared physical disks.

Note: To obtain the benefits of multiple voting disks, you must configure at least three voting disks.

- (10.1) There are new and changed pages and dialog boxes for Oracle Universal Installer (OUI), Database Configuration Assistant (DBCA), and Database Upgrade Assistant (DBUA). The Virtual Internet Protocol Configuration Assistant (VIPCA) is a new tool for the 10.x releases. These enhancements are described in the following:
 - (10.1) Database Creation Page: This page lets you select the type of starter database to create, and enables you to configure a database using DBCA after the software installation is complete.
 - (10.1) Database Backup and Recovery Page
 - (10.1) Database Security Page: You can now set the password for the ASM instance `SYS` user as well as the other database administration and monitoring accounts during installation.
 - (10.1) Database Management Page: This page provides the option to use Oracle Enterprise Manager Grid Control or Database Control to monitor the database.
 - (10.1) Create Disk Group Page: This page lets you create one disk group for ASM database data file management for backup and recovery.
 - (10.1) Existing ASM Disk Groups Page: This page provides assistance with placing disk groups in cases where you already have an ASM instance on your system.
 - (10.1) OUI Cluster Installation Mode Page: This page lets you select whether to perform a cluster or a single-instance Oracle Database 10g installation.
 - (10.1) `SYS` and `SYSTEM` Passwords Page: This page has fields for entering and confirming the `SYS` and `SYSTEM` user passwords. This includes `SYSMAN` and `DBSNMP` if you use Oracle Enterprise Manager Database Control.
 - (10.1) Storage Options Page: This page has storage options for selecting the storage type for the database files such as control files, data files, and redo logs.
 - (10.1) DBCA Services Page: This page lets you create and configure services for your RAC environment.
 - (10.1) DBCA Initialization Parameters Page: This page has two dialog boxes to display both Basic and Advanced parameter settings.
 - (10.1) VIPCA: The pages for this assistant lets you configure virtual Internet protocol addresses for your RAC database.

- (10.1) A new auxiliary, system-managed tablespace called `SYSAUX` contains performance data and combines content that was stored in different tablespaces (some of which are no longer required) in earlier releases. This is a required tablespace for which you must plan disk space.
- (10.1) The `gsdctl` commands should be used only with Oracle9i databases. The Oracle Clusterware installation process stops any existing Global Service Daemon (GSD) processes. To start or stop the GSD processed manually, use `srvctl start nodeapps` or `srvctl stop nodeapps` respectively.
- (10.1) On some platforms, versions of the cluster manager previous to Oracle Database 10g were referred to as Cluster Manager. On all platforms in Oracle Database 10g, this function is performed by an Oracle Clusterware component known as Cluster Synchronization Services (CSS). Cluster Synchronization Service Daemon (CSSD) performs this function.
- (10.1) Oracle Database 10g provides cluster file system support for Linux and Windows-based platforms.

See Also: For more information about Oracle Cluster File System on Linux, refer to the Linux Technology Center on OTN, which is located at the following URL:

<http://www.oracle.com/technology/tech/linux/index.html>

- (10.1) RAC and Database Configuration Assistant (DBCA) support Automatic Storage Management (ASM) and Oracle Managed Files (OMF).

See Also:

- *Oracle Database Administrator's Guide* for information about Automatic Storage Management, a new database file management feature
- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about administering services and storage in RAC
- *Oracle Database Upgrade Guide* for information about using DBUA
- (10.2) The Oracle Database 10g version of the `srvConfig.loc` file is the `ocr.loc` file. The Oracle9i version of `srvConfig.loc` still exists for backward compatibility.

Note: If OUI detects the Oracle9i `svrconfig.loc` file, then the Oracle9i `srvConfig.loc` file is modified to point to `/dev/null`. Changing the `srvConfig.loc` file prevents Oracle9i clients such as GSD and `srvconfig` from overwriting contents of the device used for Oracle Cluster Registry in Oracle 10g Release 2 (10.2).

Part I

Oracle Clusterware and Oracle Real Application Clusters Installation Planning and Requirements

Part I describes how to plan your Oracle Clusterware and Oracle Real Application Clusters (RAC) installations, and describes Oracle Clusterware and RAC installation requirements. Part I contains the following topics:

[Chapter 1, "Introduction to Installing and Configuring Oracle Clusterware and Oracle Real Application Clusters"](#)

Introduction to Installing and Configuring Oracle Clusterware and Oracle Real Application Clusters

This chapter provides an overview of Oracle Clusterware and Oracle Real Application Clusters (RAC) installation and configuration procedures. It includes the following topics:

- [Oracle Clusterware and Oracle Real Application Clusters Documentation Overview](#)
- [General System Installation Requirements](#)
- [Configuration Tasks for Oracle Clusterware and Oracle Real Application Clusters](#)
- [Pre-Installation, Installation, and Post-Installation Overview](#)
- [Oracle Universal Installer and Real Application Clusters](#)
- [Storage Considerations for Installing Oracle Database 10g Real Application Clusters](#)
- [Additional Considerations for Using Oracle Database 10g Features in RAC](#)
- [Oracle Database 10g and Real Application Clusters Components](#)
- [Oracle Database 10g Real Application Clusters Release Compatibility](#)
- [Required Operating System Groups](#)
- [Cloning Oracle Clusterware and RAC in Grid Environments](#)

Oracle Clusterware and Oracle Real Application Clusters Documentation Overview

This section describes the Oracle Clusterware and RAC documentation set.

This book contains the pre-installation, installation, and post-installation information for AIX. Additional information for this release may be available in the Oracle Database 10g README or Release Notes. The platform-specific Oracle Database 10g installation media contains a copy of this book in both HTML and PDF formats.

The Server Documentation directory on the installation media contains *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* as well as additional Oracle Database 10g documentation.

Oracle Real Application Clusters Administration and Deployment Guide

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide describes how to administer Oracle Clusterware components such as the voting disks and Oracle Cluster Registry (OCR) devices. This book also explains how to administer storage, how to use RAC scalability features to add and delete instances and nodes, how to use Recovery Manager (RMAN), and how to perform backup and recovery in RAC.

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide describes RAC deployment topics such as services, high availability, and workload management. The book describes how the Automatic Workload Repository (AWR) tracks and reports service levels, and how you can use service level thresholds and alerts to improve high availability in your RAC environment. The book also describes how to make your applications highly available using Oracle Clusterware.

Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide also provides information about how to monitor and tune performance in RAC environments by using Oracle Enterprise Manager, and by using information in AWR and Oracle Database performance views. The book also provides some application-specific deployment techniques for online transaction processing and data warehousing environments.

General System Installation Requirements

Each node that you want to make part of your Oracle Clusterware or Oracle Clusterware and RAC installation must meet the hardware and software requirements specified in [Part II](#) of this book. You can use the new Cluster Verification Utility to assist you with verification of requirements.

If you are uncertain about concepts related to setting up and configuring a RAC database, then read *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* to inform yourself about concepts such as services, setting up storage, and other information relevant to configuring your cluster.

Overview of Cluster Verification Utility

Cluster Verification Utility (CVU) is provided with Oracle Clusterware and Oracle Database 10g Release 2 (10.2) with Real Application Clusters. The purpose of CVU is to enable you or your hardware vendors to verify that all components required for a successful installation of Oracle Clusterware or Oracle Clusterware and a RAC database are installed and configured correctly during setup and configuration. CVU also provides you with ongoing assistance any time you need to make changes to your RAC cluster. This guide provides CVU commands that you can use to verify the completion of tasks.

There are two types of CVU commands:

- **Stage Commands** are CVU commands used to test system setup and readiness for successful software installation, database creation, or configuration change steps. These commands are also used to validate successful completion of specific cluster configuration steps.
- **Component Commands** are CVU commands used to check individual cluster components, and determine their state.

This guide provides stage and component CVU commands where appropriate to assist you with cluster verification.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for detailed information about Cluster Verification Utility.

Overview of Oracle Universal Installer

Oracle Universal Installer (OUI) is a graphical user interface (GUI) tool that assists you with installing and configuring Oracle Database. It can be run using different command options to perform installation pre-checks, specialized installation processes, and other tasks. To see an overview of OUI options, navigate to the directory path `oui/bin` in the Oracle home directory, and type the following command:

```
$ ./runInstaller -help
```

See Also: *Oracle Universal Installer and OPatch User's Guide* for more detailed information about OUI options

Overview of Upgrading and Multiple-release Systems

The path that you must take to upgrade to the new Oracle Database 10g release depends on the release number of your current database. It may not be possible to upgrade directly from your current release of Oracle Database to the latest release. Depending on your current release, you may need to upgrade through one or more intermediate releases to upgrade to the new Oracle Database 10g release.

For example, if the current database is running release 8.1.6, then first upgrade to release 8.1.7 using the instructions in *Oracle8i Migration for release 8.1.7*. The release 8.1.7 database can then be upgraded to the new Oracle Database 10g release.

Oracle9i database can coexist with Oracle Database 10g Release 2 (10.2). However, if you want separate releases of the database to coexist, then you must install Oracle Database 10g with Oracle9i already installed. You should not install Oracle9i after installing Oracle10g.

See Also: *Oracle Database Upgrade Guide* for more information about upgrading

Hardware Requirements for Oracle Clusterware and Oracle Real Application Clusters

Each node in a cluster requires the following hardware:

- External shared disks for storing the Oracle Clusterware (Oracle Cluster Registry and voting disk) files, and database files.

[Chapter 3](#) describes the storage disk configuration options that are available.

Review these options before you decide which storage option to use in your RAC environment. However, note that when Database Configuration Assistant (DBCA) configures automatic disk backup, it uses a database recovery area that must be shared.

Note: Oracle Clusterware software can be installed on General Parallel File System (GPFS).

- One private internet protocol (IP) address for each node to serve as the private interconnect. The following must be true for each private IP address:

- It must be separate from the public network
- It must be accessible on the same network interface on each node
- It must have a unique address on each node

The private interconnect is used for internode communication by both Oracle Clusterware and RAC. The private IP address must be available in each node's `/etc/hosts` file.

During Oracle Clusterware installation, the information you enter as the private IP address determines which private interconnects are used by Oracle Clusterware for its own communication. They must all be available, and capable of responding to a `ping` command.

Oracle recommends that you use a logical Internet Protocol (IP) address that is available across all private networks, and that you take advantage of any available operating system-based failover mechanism by configuring it according to your third-party vendor's instructions for using their product to support failover.

- One public IP address for each node, to be used as the Virtual IP address for client connections and for connection failover.

During installation this public virtual IP address (VIP) is associated with the same interface name on every node that is part of your cluster. The IP addresses that you use for all of the nodes that are part of a cluster must be from the same subnet. If you have a domain name server (DNS), then register the host names for the VIP with the DNS. The VIP should not be in use at the time of the installation, because this is a VIP that Oracle Clusterware manages. The network interface name should be identical across all of the nodes.

- One public fixed host name address for each node, typically assigned by the system administrator during operating system installation. If you have a domain name server (DNS), then you can register both the fixed IP and the VIP address with the DNS. If you do not have a DNS, then you must make sure that both public IP addresses are in the node `/etc/host` file (for all cluster nodes), and any client system's `/etc/host` file that requires access to the database.

Note: In addition to these requirements, Oracle recommends the following:

- While installing and using Real Application Clusters software, you should attempt to keep the system clocks on all cluster nodes as close as possible to the same time. Oracle strongly recommends using the Network Time Protocol feature of most operating systems for this purpose, with all nodes using the same reference Network Time Protocol server.
 - Use redundant switches as a standard configuration for all cluster sizes.
-

Software Requirements for Oracle Clusterware and Oracle Real Application Clusters

Each node in a cluster requires a supported interconnect software protocol to support Cache Fusion, and to support Oracle Clusterware polling. Your interconnect *must* be certified by Oracle for your platform. You should also have a Web browser, both to enable Oracle Enterprise Manager, and to view online documentation.

For Oracle Database 10g requirements, Oracle Clusterware provides the same functions as third-party vendor clusterware. Using Oracle Clusterware also reduces

installation and support complications. However, you may require third-party vendor clusterware if you use a non-ethernet interconnect, or if you have deployed clusterware-dependent applications on the same cluster where you deploy RAC.

Configuration Tasks for Oracle Clusterware and Oracle Real Application Clusters

Before installing RAC, perform the following procedures:

1. Ensure that you have a certified combination of the operating system and an Oracle Database software release by referring to the Oracle *MetaLink* certification information, which is located at the following Web site:

<http://metalink.oracle.com>

Click **Certify & Availability**, and select **1.View Certifications by Product**.

Note: The layout of the Oracle *MetaLink* site and the site's certification policies are subject to change.

2. Configure a high-speed interconnect that uses a private network. Some platforms support automatic failover to an additional interconnect.
3. Determine the storage option for your system and configure the shared disk. Oracle recommends that you use Automatic Storage Management (ASM) and Oracle Managed Files (OMF), or a cluster file system. If you use ASM or a cluster file system, then you can also take advantage of OMF and other Oracle Database 10g storage features. If you use RAC on Oracle Database 10g Standard Edition, then you must use ASM.

When you start Oracle Universal Installer (OUI) to install Oracle Clusterware, you are asked to provide the paths for voting disks, and for the Oracle Cluster Registry (OCR).

For voting disks: Configure one disk, if you have existing redundancy support for the voting disk. If you intend to use multiple voting disks managed by Oracle Clusterware, then you must have at least three disks to provide sufficient redundancy, and you must ensure that each voting disk is located on physically independent storage.

In addition, if you select multiple voting disks managed by Oracle Clusterware, then you should ensure that all voting disks are located on a secure network protected from external security threats, and you should ensure that all voting disks are on regularly maintained systems. If a voting disk fails, then you need to fix the physical hardware and bring it back online. The Cluster Synchronization Services (CSS) component of Oracle Clusterware continues to use the other voting disks, and automatically makes use of the restored drive when it is brought online again.

For OCR: Configure one disk if you have existing redundancy support. If you intend to use OCR mirroring managed by Oracle Clusterware, then you must have two OCR locations, and you must ensure that each OCR is located on physically independent storage.

In addition, if you select mirrored OCRs managed by Oracle Clusterware, then you should ensure that all OCRs are located on a secure network protected from external security threats, and you should ensure that all OCRs are on regularly

maintained systems. If an OCR copy fails or becomes inaccessible, then you can use the `ocrconfig` tool to replace the OCR.

4. Install the operating system patch updates that are listed in the pre-installation chapter in this book in [Part II](#).
5. Use the Cluster Verification Utility (CVU) to help you to verify that your system meets requirements for installing Oracle Database with RAC.

Pre-Installation, Installation, and Post-Installation Overview

The following describes the installation procedures that are covered in [Part II](#) and [Part III](#) of this book.

Pre-Installation Overview for Oracle Database 10g Real Application Clusters

The pre-installation procedures in [Part II](#) explain how to verify user equivalence, perform network connectivity tests, how to set directory and file permissions, and other required pre-installation tasks. Complete all pre-installation tasks and verify that your system meets all pre-installation requirements before proceeding to the install phase.

Installation Overview for Oracle Database 10g Real Application Clusters

Oracle Database 10g Real Application Clusters installation is a two-phase installation. In phase one, use Oracle Universal Installer (OUI) to install Oracle Clusterware as described in [Chapter 4, "Installing Oracle Clusterware"](#). Note that the Oracle home in phase one is a home for the Oracle Clusterware software, which *must be different* from the Oracle home that you use in phase two for the installation of the Oracle database software with RAC components. The Oracle Clusterware installation starts the Oracle Clusterware processes in preparation for installing Oracle Database 10g with RAC, as described in [Chapter 5, "Installing Oracle Database 10g with Real Application Clusters"](#). Use OUI in this phase to install the RAC software.

You must install Oracle Clusterware and Oracle Database in a separate home directories. If you will use multiple Oracle Database homes with ASM, then you should install a separate Oracle Database home for ASM. You should create the listener in the Oracle database Oracle home.

If OUI detects a previous release of Oracle Clusterware (previously known as Oracle Cluster Ready Services), then you are prompted to select either a rolling upgrade, or a full upgrade.

If OUI detects a previous release of the Oracle database, then OUI provides you with the option to start Database Upgrade Assistant (DBUA) to upgrade your database to Oracle Database 10g Release 2 (10.2). In addition, DBUA displays a Service Configuration page for configuring services in your RAC database.

See Also: *Oracle Database Upgrade Guide* for additional information about preparing for upgrades

After the installation completes, OUI starts the Oracle Database assistants, such as Database Configuration Assistant (DBCA), to configure your environment and create your RAC database. You can later use the DBCA Instance Management feature to add or modify services and instances as described in [Chapter 6, "Creating Real Application Clusters Databases with Database Configuration Assistant"](#).

Post-Installation Overview for Oracle Database 10g Real Application Clusters

After you create your database, download and install the most recent patch set for your Oracle Database 10g release, as described in [Chapter 7, "Oracle Real Application Clusters Post-Installation Procedures"](#). If you are using other Oracle products with your RAC database, then you must also configure them.

You must also perform several post-installation configuration tasks to use certain Oracle Database 10g features.

On the installation media, you can select additional Oracle Database 10g software that may improve performance or extend database capabilities. Examples: Oracle JAccelerator, Oracle *interMedia*, and Oracle Text.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*, and *Oracle Universal Installer and OPatch User's Guide* for more information about using the RAC scalability features of adding and deleting nodes and instances from RAC databases

Oracle Universal Installer and Real Application Clusters

Oracle Universal Installer (OUI) facilitates the installation of Oracle Clusterware and Oracle Database 10g software. In most cases, you use the graphical user interface (GUI) provided by OUI to install the software. However, you can also use OUI to complete non-interactive (or *silent*) installations, without using the GUI. Refer to [Appendix B](#) for information about non-interactive installations.

The Oracle Inventory maintains records of Oracle software releases and patches. Each installation has a central inventory where the Oracle home is registered. Oracle software installations have a local inventory directory, whose path location is recorded in the central inventory Oracle home. The local inventory directory for each Oracle software installation contains a list of components and applied interim patches associated with that software. Because your Oracle software installation can be corrupted by faulty inventory information, OUI must perform all read and write operations on Oracle inventories.

When you install Oracle Clusterware or RAC, OUI copies this Oracle software onto the node from which you are running it. If your Oracle home is not on a shared file system, then OUI propagates the software onto the other nodes that you have selected to be part of your OUI installation session. The Oracle Inventory maintains a list of each node that is a member of the RAC database, and lists the paths to each node's Oracle home. This is used to maintain software patches and updates for each member node of the RAC database.

If you create your RAC database using OUI, or if you create it later using DBCA, then Oracle Enterprise Manager Database Control is configured for your RAC database. Database Control can manage your RAC database, all its instances, and the hosts where instances are configured.

You can also configure Enterprise Manager Grid Control to manage multiple databases and application servers from a single console. To manage RAC databases in Grid Control, you must install a Grid Control agent on each of the nodes of your cluster. The Agent installation is designed to recognize a cluster environment and install across all cluster nodes; you need to perform the installation on only one of the cluster nodes to install Grid Control agent on all cluster nodes.

When OUI installs the Oracle Clusterware or Oracle Database software, Oracle recommends that you select a preconfigured database, or use Database Configuration

Assistant (DBCA) interactively to create your RAC database. You can also manually create your database as described in procedures posted on the Oracle Technical Network, which is at the following URL:

<http://www.oracle.com/technology/index.html>

Oracle recommends that you use Automatic Storage Management (ASM). If you are not using ASM, or if you are not using a cluster file system, then configure shared raw devices before you create your database.

See Also:

- *Oracle Universal Installer and OPatch User's Guide* for more details about OUI
- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for information about using Oracle Enterprise Manager to administer RAC environments
- The Grid Technology Center on the Oracle Technology Network (OTN), which is available at the following URL:

<http://www.oracle.com/technology/tech/index.html>

Storage Considerations for Installing Oracle Database 10g Real Application Clusters

This section discusses storage configuration options that you should consider before installing Oracle Database 10g Release 2 (10.2) with Real Application Clusters.

Overview of Automatic Storage Management

Oracle recommends using Automatic Storage Management (ASM) or a cluster file system with Oracle Managed Files (OMF) for database storage. This section provides an overview of ASM.

Note that RAC installations using Oracle Database Standard Edition must use ASM for database file storage.

You can use ASM to simplify the administration of Oracle database files. Instead of having to manage potentially thousands of database files, using ASM, you need to manage only a small number of disk groups. A **disk group** is a set of disk devices that ASM manages as a single logical unit. You can define a particular disk group as the default disk group for a database, and Oracle Database will automatically allocate storage for, create, or delete, the files associated with the appropriate database object. When administering the database, you need to refer to database objects only by name, rather than by file name.

When using ASM with a single Oracle home for database instances on a node, the ASM instance can run from that same home. If you are using ASM with Oracle Database instances from multiple database homes on the same node, then Oracle recommends that you run the ASM instance from an Oracle home that is distinct from the database homes. In addition, the ASM home should be installed on every cluster node. Following this recommendation prevents the accidental removal of ASM instances that are in use by databases from other homes during the de-installation of a database's Oracle home.

Benefits of Automatic Storage Management

ASM provides many of the same benefits as storage technologies such as a redundant array of independent disks (RAID) or a logical volume manager (LVM). Like these technologies, ASM lets you create a single disk group from a collection of individual disk devices. It balances input and output (I/O) loads to the disk group across all of the devices in the disk group. It also implements striping and mirroring to improve I/O performance and data reliability.

However, unlike RAID or LVMs, ASM implements striping and mirroring at the file level. This implementation lets you specify different storage attributes for individual files in the same disk group.

Disk Groups and Failure Groups

A disk group can contain between 1 to 10000 disk devices. Each disk device can be an individual physical disk, a multiple disk device such as a RAID storage array or logical volume, or even a partition on a physical disk. However, in most cases, disk groups consist of one or more individual physical disks. To enable ASM to balance I/O and storage appropriately within the disk group, all devices in the disk group should have similar, if not identical, storage capacity and performance.

Note: Do not put more than one partition of a single disk into the same disk group. You can put separate partitions of a single disk into separate disk groups.

Although you can specify a logical volume as a device in an ASM disk group, Oracle does not recommend their use. Because logical volume managers can hide the physical disk architecture, ASM may not operate effectively when logical volumes are specified as disk group devices.

When you add a device to a disk group, you can specify a failure group for that device. Failure groups define ASM disks that share a common potential failure mechanism. An example of a failure group is a set of SCSI disks sharing the same SCSI controller. Failure groups are used to determine which ASM disks to use for storing redundant copies of data. For example, if two-way mirroring is specified for a file, then ASM automatically stores redundant copies of file extents in separate failure groups. Failure groups apply only to normal and high redundancy disk groups. You define the failure groups in a disk group when you create or alter the disk group.

Redundancy Levels

ASM provides three levels of mirroring, called redundancy levels, that you can specify when creating a disk group. The redundancy levels are:

- External redundancy
 - In disk groups created with external redundancy, the contents of the disk group are not mirrored by ASM. Choose this redundancy level when:
 - The disk group contains devices, such as RAID devices, that provide their own data protection
 - Your use of the database does not require uninterrupted access to data. For example: a development environment where you have a suitable backup strategy
- Normal redundancy

In disk groups created with normal redundancy, the contents of the disk group are two-way mirrored by default. However, you can choose to create certain files that are three-way mirrored, or that are not mirrored. To create a disk group with normal redundancy, you must specify at least two failure groups (a minimum of two devices).

The effective disk space of a disk group that uses normal redundancy is half the total disk space of all of its devices.

- **High redundancy**

In disk groups created with high redundancy, the contents of the disk group are three-way mirrored by default. To create a disk group with high redundancy, you must specify at least three failure groups (a minimum of three devices).

The effective disk space of a disk group that uses high redundancy is one-third of the total disk space of all of its devices.

See Also: *Oracle Database Administrator's Guide* for additional information about ASM and redundancy

ASM and Installation Types

The type and number of disk groups that you can create when installing Oracle Database software depends on the type of database you choose to create during the installation, as follows:

- **Preconfigured database**

If you choose to create the default preconfigured database that uses ASM, then OUI prompts you to specify one or more disk device names and redundancy. By default, OUI creates a disk group named DATA, with normal redundancy.

- **Advanced database**

If you choose to create an advanced database that uses ASM, then you can create one or more disk groups. These disk groups can use one or more devices. For each disk group, you can specify the redundancy level that suits your requirements.

- **Configure Automatic Storage Management**

If you choose to create an ASM instance only, then OUI prompts you to create Disk Group. If OUI finds a Grid Control service is found on the system, then OUI prompts you to indicate if the ASM instance shall be managed by Grid Control. The Management Service box lists the available Oracle Management Services.

Shared Storage for Database Recovery Area

When you configure a database recovery area in a RAC environment, the database recovery area must be on shared storage. When Database Configuration Assistant (DBCA) configures automatic disk backup, it uses a database recovery area that must be shared.

If the database files are stored on a cluster file system, then the recovery area can also be shared through the cluster file system.

If the database files are stored on an Automatic Storage Management (ASM) disk group, then the recovery area can also be shared through ASM.

Note: ASM disk groups are always valid recovery areas, as are cluster file systems. Recovery area files do not have to be in the same location where data files are stored. For instance, you can store data files on raw devices, but use ASM for the recovery area.

Additional Considerations for Using Oracle Database 10g Features in RAC

Oracle recommends that you use the following Oracle Database 10g features to simplify RAC database management:

- Oracle Enterprise Manager—Use Enterprise Manager to administer your *entire* processing environment, not just the RAC database. Enterprise Manager lets you manage a RAC database with its instance targets, listener targets, host targets, and a cluster target, as well as ASM targets if you are using ASM storage for your database.
- Automatic undo management—This feature automatically manages undo processing.
- Automatic segment-space management—This feature automatically manages segment freelists and freelist groups.
- Locally managed tablespaces—This feature enhances space management performance.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about these features in RAC environments

Oracle Database 10g and Real Application Clusters Components

Oracle Database 10g provides single-instance database software and the additional components to operate RAC databases. Some of the RAC-specific components include the following:

- Oracle Clusterware
- A RAC-enabled Oracle home

Oracle Clusterware

OUI installs Oracle Clusterware on each node of the cluster. If third-party vendor clusterware is not present, then you must use OUI to enter the nodes on which you want Oracle Clusterware to be installed. The Oracle Clusterware home can either be shared by all nodes, or private to each node, depending on your responses when you run OUI. The home that you select for Oracle Clusterware *must* be different from the RAC-enabled Oracle home.

When third-party vendor clusterware is present, Oracle Clusterware may interact with the third-party vendor clusterware.

Note: The Oracle Database cluster manager in database releases previous to 10g Release 1 was referred to as "Cluster Manager." In Oracle Database 10g, the cluster manager role is performed by Cluster Synchronization Services (CSS), a component of Oracle Clusterware, on all platforms. The Cluster Synchronization Service Daemon (CSSD) performs this function.

The Installed Real Application Clusters Components

All instances in RAC environments share the control file, server parameter file, redo log files, and all data files. These files reside on a shared cluster file system or on shared disks. Either of these types of file configurations are accessed by all the cluster database instances. Each instance also has its own set of redo log files. During failures, shared access to redo log files enables surviving instances to perform recovery.

Oracle Database 10g Real Application Clusters Release Compatibility

You can install and operate different releases of Oracle Database software on the same computer:

- With Oracle Database 10g Release 2 (10.2) if you have an existing Oracle home, then you must install the database into the existing Oracle home. You should install Oracle Clusterware in a separate Oracle Clusterware home. Each node can have only one Oracle Clusterware home.

During installation, Oracle Universal Installer (OUI) prompts you to install additional Oracle Database 10g components if you have not already installed all of them.

- OUI lets you de-install and re-install Oracle Database 10g Real Application Clusters if needed.
- If you want to install Oracle9i and Oracle Database 10g Release 2 (10.2) on the same system, then you must install Oracle9i first. You cannot install Oracle9i on a system with Oracle Database 10g.
- If OUI detects an earlier database release, then OUI asks you about your upgrade preferences. You have the option to upgrade one of the previous release databases with DBUA or to create a new database using DBCA. The information collected during this dialog is passed to DBUA or DBCA after the software is installed.

Note: Do not move Oracle binaries from the Oracle home to another location. Doing so can cause dynamic link failures.

- You can run different releases of Oracle Database and Automatic Storage Management (ASM). If the Oracle Database release and the ASM release are the same release, then they can both run out of the same Oracle home. If they are different releases, then the Oracle Database release and the ASM release must be in their separate release homes. For example, you can install an ASM release 10g Release 2 (10.2) instance and use it with Oracle Database 10g Release 1 (10.1) database, or you can install an Oracle 10g Release 2 (10.2) database and use it with an ASM 10g Release 1 (10.1) instance.

Note: When using different release ASM and Oracle Database releases, the functionality of each is dependent on the functionality of the earlier software release. For example, an Oracle Database 10g release 10.1.0.2 using an ASM 10.1.0.3 instance will not be able to use new features available for ASM in the 10.1.0.3 release, but instead only ASM 10.1.0.2 features. Conversely, an Oracle Database 10g release 10.1.0.3 using an ASM instance release 10.1.0.2 will function like a release 10.1.0.2 database.

Required Operating System Groups

Depending on whether this is the first time that you are installing Oracle server software on your system, you may need to create several groups and a user account to own Oracle software, as described later in the pre-installation procedures. The required groups and user are:

- The Oracle Inventory group (`oinstall`)

You must create this group the first time you install Oracle software on the system. The usual name for this group is `oinstall`. Members of this group own the Oracle inventory, which is a catalog of all of the Oracle software installed on the system. Group membership in `oinstall` is also required to perform some tasks involving Oracle Cluster Registry (OCR) keys that are created during Oracle Clusterware installation.

- The OSDBA group (`dba`)

You must create the OSDBA group the first time you install Oracle software on the system.

The OSDBA group provides operating system verification of users that have database administrative privileges (the SYSDBA and SYSOPER privileges). The default name for this group is `dba`. During installation, if you want to specify a group name other than the default, then you are prompted during installation for the name of the OSDBA group.

You must create a new OSDBA group if you have an existing OSBDA group, but you want to give a different group of users database administrative privileges in a new Oracle server installation.

- The OSOPER group (`oper`)

The OSOPER group is optional. Create this group if you want a separate group of users to have a limited set of database administrative privileges (the SYSOPER privilege), to perform such operations as backing up, recovering, starting up, and shutting down the database. The default name for this group is `oper`. To use this group, choose the **Custom** installation type to install the software. To use an OSOPER group, you must create it in the following circumstances:

- If an OSOPER group does not exist (for example, if this is the first installation of Oracle server software on the system)
- If an OSOPER group exists, but you want to give a different group of users database operator privileges in a new Oracle server installation
- The Oracle Software Owner user (`oracle`)

You must create the Oracle user the first time you install Oracle software on the system. The Oracle user owns all of the software installed during the installation. The usual name for the Oracle user is `oracle`. The Oracle user must have the

Oracle Inventory group as its primary group and the OSDBA group as its secondary group. It must also have the OSOPER group as a secondary group if you choose to create that group.

If an Oracle software owner user exists, but you want to use a different user with different group membership in a new Oracle server installation, then you must give database administrative privileges to those groups.

A single Oracle Inventory group is required for all installations of Oracle software on the system. However, you can create different Oracle software owner users, OSDBA groups, and OSOPER groups (other than `oracle`, `dba`, and `oper`) for separate installations. In addition, you can create a separate owner for Oracle Clusterware. Using different groups lets you grant DBA privileges to a particular operating system user on one database, which they would not have on another database on the same system.

See Also: *Oracle Database Administrator's Reference, 10g Release 2 (10.2) for UNIX Systems* and *Oracle Database 10g Administrator's Guide for AIX* for additional information about the OSDBA and OSOPER groups, and the `SYSDBA` and `SYSOPER` privileges.

Cloning Oracle Clusterware and RAC in Grid Environments

The following section provides a summary of the procedure for deployments of RAC in grid environments with large numbers of nodes using cloned Clusterware and RAC images.

See Also: For detailed information about cloning RAC and Oracle Clusterware images, refer to the following documents:

Cloning, and adding and deleting nodes:

Oracle Universal Installer and OPatch User's Guide

Additional information about adding and deleting nodes:

Oracle10i Real Application Clusters Administration

This section contains the following:

- [Cloning Oracle Clusterware Homes](#)
- [Cloning RAC Homes](#)

Cloning Oracle Clusterware Homes

Complete the following tasks to clone an Oracle Clusterware home on multiple nodes:

1. On the source node, install Oracle Clusterware software. All required root scripts must run successfully.
2. As root, create a tar file of the Oracle Clusterware home
3. On the target node, create an Oracle Clusterware home, and copy the Oracle Clusterware tar file from the source node to the target node Oracle Clusterware home.
4. As root, uncompress the tar file.
5. Run OUI in clone mode, as described in *Oracle Universal Installer and OPatch User's Guide*.

6. Run root scripts.
7. Repeat steps 1 through 6 on each node that you want to add to the cluster. On the last node that you install, run the tool `oifcfg` to configure the network interfaces.

Cloning RAC Homes

Complete the following tasks to Clone a RAC database image on multiple nodes:

1. On the source node, install a RAC database Oracle home. All required root scripts must run successfully. Do not create a database, and do not run any configuration tools.
2. As root, create a tar file of the RAC database Oracle home.
3. On the target node, create an Oracle home directory for the RAC database, and copy the RAC database tar from the source node to the target node Oracle home.
4. Create required Oracle users and groups, ensuring that you use the same names, user ID numbers and group ID numbers as those on the source node.
5. As root, uncompress the tar file.
6. Run OUI in clone mode, as described in *Oracle Universal Installer and OPatch User's Guide*.
7. Run root scripts.
8. Repeat steps 1 through 7 for on each node that you want to add to the cluster.
9. Run the configuration assistant NetCA on a local node of the cluster, and provide a list when prompted of all nodes that are part of the cluster. This procedure creates the listener.
10. Run the configuration assistant DBCA to create the database.
11. Follow post-cloning phase instructions as provided in *Oracle Universal Installer and OPatch User's Guide*.

Part II

Oracle Clusterware and Oracle Real Application Clusters Pre-Installation Procedures

Part II describes the pre-installation procedures for AIX that you must complete before installing Oracle Clusterware and Oracle Database 10g Real Application Clusters (RAC). Part II contains the following chapters:

- [Chapter 2, "Pre-Installation Tasks"](#)
- [Chapter 3, "Configuring Oracle Clusterware and Oracle Database Storage"](#)

Pre-Installation Tasks

This chapter describes the system configuration tasks that you must complete before you start Oracle Universal Installer. It includes information about the following tasks:

- [Understanding and Using Cluster Verification Utility](#)
- [Logging In to the System as root](#)
- [Creating Required Operating System Groups and User](#)
- [Configuring Shell Limits, System Configuration, and Network Tuning Parameters](#)
- [Configuring the oracle User's Environment](#)
- [Checking the Hardware Requirements](#)
- [Checking the Network Requirements](#)
- [Checking the Network Setup with CVU](#)
- [Checking the Software Requirements](#)
- [Checking the Hardware and Operating System Setup with CVU](#)
- [Checking the Operating System Requirements Setup with CVU](#)
- [Identifying Required Software Directories](#)
- [Identifying or Creating an Oracle Base Directory](#)
- [Creating the Oracle Clusterware Home Directory](#)
- [Stopping Existing Oracle Processes for Upgrades or Co-existing Databases](#)

Understanding and Using Cluster Verification Utility

Cluster Verification Utility (CVU) is a tool that performs system checks. This guide provides CVU commands to assist you with confirming that your system is properly configured for Oracle Clusterware and Oracle Real Application Clusters installation.

This section describes the following topics:

- [Using CVU to Determine if Installation Prerequisites are Complete](#)
- [Entering Cluster Verification Utility Commands](#)
- [Using the Cluster Verification Utility Help](#)
- [Using Cluster Verification Utility with Oracle 10g Release 1](#)
- [Verbose Mode and "Unknown" Output](#)

Entering Cluster Verification Utility Commands

To enter a CVU command, use the following syntax:

```
$ /mountpoint/clusterware/cluvfy/runcluvfy.sh options
```

In the preceding syntax example, the variable *mountpoint* represents the mountpoint path for the installation media, and the variable *options* represents the CVU command options that you select. For example:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh comp nodereach -n node1,node2 -verbose
```

By default, when you enter a CVU command, CVU provides a summary of the test. During pre-installation, Oracle recommends that you obtain detailed output by using the `-verbose` argument with the CVU command. The `-verbose` argument produces detailed output of individual checks. Where applicable, it shows results for each node in a tabular layout.

Using CVU to Determine if Installation Prerequisites are Complete

You can use CVU to determine which system prerequisites for installation are already completed. Use this option if you are installing Oracle 10g Release 2 (10.2) on a system with a pre-existing Oracle software installation. In using this option, note the following:

- You must complete the prerequisites for using CVU
- CVU can assist you by finding pre-installation steps that need to be completed, but it cannot perform pre-installation tasks

Use the following syntax to determine what pre-installation steps are completed, and what pre-installation steps must be performed

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -pre crsinst -n node_list
```

In the preceding syntax example, replace the variable *mountpoint* with the installation media mountpoint, and replace the variable *node_list* with the names of the nodes in your cluster, separated by commas.

For example, for a cluster with mountpoint `/dev/dvdrom/`, and with nodes `node1`, `node2`, and `node3`, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -pre crsinst -n  
node1,node2,node3
```

Review the CVU report, and proceed to the sections of the pre-installation chapter to complete additional steps as needed.

Using the Cluster Verification Utility Help

The `cluvfy` commands have context-sensitive help that shows correct syntax usage based on the command line arguments that you enter.

If you enter an invalid CVU command, then CVU shows the correct usage for that command. For example, if you type `runcluvfy.sh stage -pre dbinst`, then CVU shows the correct syntax for the database pre-installation checks that CVU performs with the `dbinst` stage option. The following is a list of context help commands.

- `cluvfy`: CVU displays high-level generic usage text describing the stage and component syntax.

- `cluvfy -help`: CVU displays detailed CVU command information.
- `cluvfy comp -list`: CVU displays a list of components that can be checked, and brief descriptions of how each component is checked.
- `cluvfy comp -help`: CVU displays detailed syntax for each of the valid component checks.
- `cluvfy stage -list`: CVU displays a list of valid stages.
- `cluvfy stage -help`: CVU displays detailed syntax for each of the valid stage checks.

Using Cluster Verification Utility with Oracle 10g Release 1

You can use CVU on the Oracle 10g Release 2 (10.2) media to check system requirements for Oracle 10g Release 1 (10.1) installations. To use CVU to check 10.1 installations, append the command flag `-r 10gR1` to the standard CVU system check commands.

For example, to perform a verification check for a Cluster Ready Services 10.1 installation, on a system where the media mountpoint is `/dev/dvdrom/`, and the cluster nodes are `node1`, `node2`, and `node3`, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -pre crsinst -n
node1,node2,node3 -r 10gR1
```

Verbose Mode and "Unknown" Output

If you run CVU using the `-verbose` argument, and a CVU command responds with `UNKNOWN` for a particular node, then this is because the CVU cannot determine whether a check passed or failed. The following is a list of possible causes for an "Unknown" response:

- The node is down
- Executables required by CVU are missing in the `CRS_home /bin` or Oracle home directory
- The user account starting CVU does not have privileges to run common operating system executables on the node
- The node is missing an operating system patch, or a required package
- The node has exceeded the maximum number of processes or maximum number of open files, or there is a problem with IPC segments, such as shared memory or semaphores

Logging In to the System as root

Before you install the Oracle software, you must complete several tasks as the `root` user. To log in as the `root` user, complete one of the following procedures:

- If you are installing the software from an X Window System workstation or X terminal, then:
 1. Start a local terminal session, for example, an X terminal (`xterm`).
 2. If you are not installing the software on the local system, then enter the following command to enable remote hosts to display X applications on the local X server:

```
$ xhost + hostname
```

The *hostname* is the name of the local host.

3. If you are not installing the software on the local system, then use the `ssh`, `rlogin`, or `telnet` command to connect to the system where you want to install the software:

```
$ telnet remote_host
```

4. If you are not logged in as the `root` user, then enter the following command to switch the user to `root`:

```
$ su - root
password:
#
```

- If you are installing the software from a PC or other system with X server software installed, then:

Note: If necessary, refer to your X server documentation for more information about completing this procedure. Depending on the X server software that you are using, you may need to complete the tasks in a different order.

1. Start the X server software.
2. Configure the security settings of the X server software to permit remote hosts to display X applications on the local system.
3. Connect to the remote system where you want to install the software and start a terminal session on that system, for example, an X terminal (`xterm`).
4. If you are not logged in as the `root` user on the remote system, then enter the following command to switch user to `root`:

```
$ su - root
password:
#
```

Creating Required Operating System Groups and User

Depending on whether this is the first time Oracle software is being installed on this system and on the products that you are installing, you may need to create several operating system groups and an operating system user account.

The following operating system groups and user are required if you are installing Oracle Database:

- The OSDBA group (typically, `dba`)

You must create this group the first time you install Oracle Database software on the system. This group identifies operating system user accounts that have database administrative privileges (the SYSDBA privilege). The default name for this group is `dba`.

If you want to specify a group name other than the default `dba` group, then you must choose the Custom installation type to install the software or start Oracle Universal Installer as a user that is not a member of this group. In this case, Oracle Universal Installer prompts you to specify the name of this group.

- The OSOPER group (typically, `oper`)

This is an optional group. Create this group if you want a separate group of operating system users to have a limited set of database administrative privileges (the SYSOPER privilege). By default, members of the OSDBA group also have the SYSOPER privilege.

If you want to specify a separate OSOPER group, other than the default `dba` group, then you must choose the Custom installation type to install the software or start Oracle Universal Installer as a user that is not a member of the `dba` group. In this case, Oracle Universal Installer prompts you to specify the name of this group. The usual name chosen for this group is `oper`.

- An unprivileged user

Verify that the unprivileged user `nobody` exists on the system. The `nobody` user must own the external jobs (`extjob`) executable after the installation.

The following operating system group and user are required for all installations:

- The Oracle Inventory group (typically, `oinstall`)

You must create this group the first time you install Oracle software on the system. The usual name chosen for this group is `oinstall`. This group owns the Oracle Inventory, which is a catalog of all Oracle software installed on the system.

Note: If Oracle software is already installed on the system, then the existing Oracle Inventory group must be the primary group of the operating system user that you use to install new Oracle software. The following sections describe how to identify an existing Oracle Inventory group.

- The Oracle software owner user (typically, `oracle`)

You must create this user the first time you install Oracle software on the system. This user owns all of the software installed during the installation. The usual name chosen for this user is `oracle`. This user must have the Oracle Inventory group as its primary group. It must also have the OSDBA and OSOPER groups as secondary groups. In Oracle documentation, when this user account is referred to, it is called the `oracle` user.

A single Oracle Inventory group is required for all installations of Oracle software on the system. After the first installation of Oracle software, you must use the same Oracle Inventory group for all subsequent Oracle software installations on that system. However, you can choose to create different Oracle software owner users, OSDBA groups, and OSOPER groups (other than `oracle`, `dba`, and `oper`) for separate installations. By using different groups for different installations, members of these different groups have DBA privileges only on the associated databases rather than on all databases on the system.

See Also: *Oracle Database Administrator's Reference for UNIX Systems* and *Oracle Database Administrator's Guide* for more information about the OSDBA and OSOPER groups and the SYSDBA and SYSOPER privileges

The following sections describe how to create the required operating system user and groups:

- [Creating the Oracle Inventory Group](#)

- [Creating the OSDBA Group](#)
- [Creating an OSOPER Group \(Optional\)](#)
- [Creating the Oracle Software Owner User](#)
- [Verifying That the User nobody Exists](#)
- [Creating Identical Users and Groups on Other Cluster Nodes](#)
- [Configuring SSH on All Cluster Nodes](#)

Note: The following sections describe how to create local users and groups. As an alternative to creating local users and groups, you can create the appropriate users and groups in a directory service, such as Network Information Services (NIS). For information about using directory services, contact your system administrator or refer to your operating system documentation.

Creating the Oracle Inventory Group

Oracle Universal Installer (OUI) helps you to choose a group to use as the Oracle Inventory group. If you have an existing Oracle Inventory group, then provide this group name and path when prompted.

The following subsections describe how to determine the Oracle Inventory group name, if it exists, and how to create it if necessary.

Determining If the Oracle Inventory Exists

When you install Oracle software on the system for the first time, Oracle Universal Installer creates the `oraInst.loc` file. This file identifies the name of the Oracle Inventory group (typically, `oinstall`), and the path of the Oracle Inventory directory.

If you have an existing Oracle Inventory, then ensure that you use the same Oracle Inventory for all Oracle software installations.

If you do not have an existing Oracle Inventory, then you should create an Oracle Inventory group.

To determine whether you have an Oracle Inventory on your system, enter the following command:

```
# more /etc/oraInst.loc
```

If the `oraInst.loc` file exists, then the output from this command is similar to the following:

```
inventory_loc=/u01/app/oracle/oraInventory
inst_group=oinstall
```

In the previous output example:

- The `inventory_loc` group shows the location of the Oracle inventory
- The `inst_group` parameter shows the name of the Oracle Inventory group (in this example, `oinstall`).

Creating the Oracle Inventory Group If an Oracle Inventory Does Not Exist

If the `oraInst.loc` file does not exist, then create the Oracle Inventory group by entering a command similar to the following:

```
# /bin/mkgroup oinstall
```

Creating the OSDBA Group

You must create an OSDBA group in the following circumstances:

- An OSDBA group does not exist, for example, if this is the first installation of Oracle Database software on the system
- An OSDBA group exists, but you want to give a different group of operating system users database administrative privileges for a new Oracle Database installation

If the OSDBA group does not exist or if you require a new OSDBA group, then create it as follows. In the following procedure, use the group name `dba` unless a group with that name already exists:

```
# /bin/mkgroup dba
```

Creating an OSOPER Group (Optional)

Create an OSOPER group only if you want to identify a group of operating system users with a limited set of database administrative privileges (SYSOPER operator privileges). For most installations, it is sufficient to create only the OSDBA group. If you want to use an OSOPER group, then you must create it in the following circumstances:

- If an OSOPER group does not exist; for example, if this is the first installation of Oracle Database software on the system
- If an OSOPER group exists, but you want to give a different group of operating system users database operator privileges in a new Oracle installation

If you require a new OSOPER group, then create it as follows. In the following, use the group name `oper` unless a group with that name already exists.

```
# /bin/mkgroup oper
```

Creating a HAGSUSER Group (Optional)

If your system uses High Availability Cluster Multiprocessing (HACMP) clusterware, then create or check for the existence of the group `hagsuser`. Ensure that the users `oracle` and `root` are members of this group.

If you require a new HAGSUSER group, then create it as follows:

```
# /bin/mkgroup hagsuser
```

Creating the Oracle Software Owner User

You must create an Oracle software owner user in the following circumstances:

- If an Oracle software owner user does not exist; for example, if this is the first installation of Oracle software on the system
- If an Oracle software owner user exists, but you want to use a different operating system user, with different group membership, to give database administrative privileges to those groups in a new Oracle Database installation

Note: If you intend to use multiple Oracle software owners for different Oracle homes, then you should create a separate Oracle software owner for Oracle Clusterware, and install Oracle Clusterware using the Oracle Clusterware software owner.

Determining if an Oracle Software Owner User Exists

To determine whether an Oracle software owner user named `oracle` exists, enter the following command:

```
# id oracle
```

If the `oracle` user exists, then the output from this command is similar to the following:

```
uid=440(oracle) gid=200(oinstall) groups=201(dba),202(oper)
```

If the user exists, then determine whether you want to use the existing user, or create another `oracle` user. If you want to use the existing user, then ensure that the user's primary group is the Oracle Inventory group and that it is a member of the appropriate OSDBA and OSOPER groups. Refer to one of the following sections for more information:

Note: If necessary, contact your system administrator before using or modifying an existing user.

- To modify an existing user, refer to the "[Modifying an Existing Oracle Software Owner User](#)" section on page 2-9.
- To create a user, refer to the following section.

Creating an Oracle Software Owner User

If the Oracle software owner user does not exist, or if you require a new Oracle software owner user, then create it as follows. In the following procedure, use the user name `oracle` unless a user with that name already exists.

1. Enter the following command:

```
# smit security
```

2. Choose the appropriate menu items to create the `oracle` user, specifying the following information:

- In the **Primary GROUP** field, specify the Oracle Inventory group, for example `oinstall`.
- In the **Group SET** field, specify the OSDBA group and if required, the OSOPER group. For example, `dba` or `dba, oper`.

Note: The UID for the `oracle` user must be less than 65536.

3. Press F10 to exit.
4. Set the password of the `oracle` user:

```
# passwd oracle
```

Modifying an Existing Oracle Software Owner User

If the `oracle` user exists, but its primary group is not `oinstall`, or it is not a member of the appropriate OSDBA or OSOPER groups, then use the following procedure to modify the `oracle` user to add groups:

1. Enter the following command:


```
# smit security
```
2. Choose the appropriate menu items to modify the `oracle` user.
3. In the **Primary GROUP** field, specify the Oracle Inventory group, for example `oinstall`.
4. In the **Group SET** field, specify the required secondary groups, for example `dba` and `oper`.
5. Press F10 to exit.
6. Repeat this procedure on all of the other nodes in the cluster.

Verifying That the User `nobody` Exists

Before installing the software, complete the following procedure to verify that the user `nobody` exists on the system:

1. To determine whether the user exists, enter the following command:

```
# id nobody
```

If this command displays information about the `nobody` user, then you do not have to create that user.

2. If the `nobody` user does not exist, then enter the following command to create it:

```
# smit security
```

Specify the appropriate options to create an unprivileged `nobody` user, then press F10 to exit.

```
# /usr/sbin/useradd nobody
```

3. Repeat this procedure on all of the other nodes in the cluster.

Creating Identical Users and Groups on Other Cluster Nodes

Note: You must complete the following procedures only if you are using local users and groups. If you are using users and groups defined in a directory service such as NIS, then they are already identical on each cluster node.

The Oracle software owner user and the Oracle Inventory, OSDBA, and OSOPER groups must exist and be identical on all cluster nodes. To create these identical users and groups, you must identify the user ID and group IDs assigned them on the node where you created them, then create the user and groups with the same name and ID on the other cluster nodes.

Identifying the User and Group IDs

To determine the user ID (UID) of the Oracle software owner user and the group IDs (GID) of the Oracle Inventory, OSDBA, and OSOPER groups, follow these steps:

1. Enter following command:

```
# id oracle
```

The output from this command is similar to the following:

```
uid=440(oracle) gid=200(oinstall) groups=201(dba),202(oper)
```

2. From the output, identify the user ID (UID) for the `oracle` user and the group identities (GIDs) for the groups to which it belongs.

Creating the User and Groups on the Other Cluster Nodes

To create the user and groups on the other cluster nodes, repeat the following procedure on each node:

1. Log in to the next cluster node as `root`.
2. Enter the following command:


```
# smit security
```
3. Choose the appropriate menu items to create or modify the `oinstall` and `dba` groups, and if required, the `oper` group.

In the **Group NAME** and **Group ID** fields, specify the group names and GIDs that you identified previously.

Note: If you cannot use the same group ID for a particular group on this node, then identify a group ID that *is* available on all nodes and specify that ID for the group on all of the nodes.

4. Choose the appropriate menu items to create or modify the `oracle` user, specifying the following information:
 - In the **User ID** field, specify the user ID that you identified in the previous subsection.
 - In the **Primary GROUP** field, specify the Oracle Inventory group, for example `oinstall`.
 - In the **Group SET** field, specify the OSDBA group and if necessary, the OSOPER group, for example `dba` or `dba, oper`.

Note: If you cannot use the same user ID for the `oracle` user on this node, then identify a user ID that *is* available on all nodes and specify that ID for the user on all of the nodes.

5. Press F10 to exit.
6. Set the password of the `oracle` user:

```
# passwd oracle
```

Configuring SSH on All Cluster Nodes

Before you install and use Oracle Real Application clusters, you must configure secure shell (SSH) for the `oracle` user on all cluster nodes. Oracle Universal Installer uses the `ssh` and `scp` commands during installation to run remote commands on and copy files to the other cluster nodes. You must configure SSH so that these commands do not prompt for a password.

Note: This section describes how to configure OpenSSH version 3. If SSH is not available, then Oracle Universal Installer attempts to use `rsh` and `rcp` instead.

To determine if SSH is running, enter the following command:

```
$ ps -ef | grep sshd
```

If SSH is running, then the response to this command is process ID numbers. To find out more about SSH, enter the following command:

```
$ man ssh
```

Configuring SSH on Cluster Member Nodes

To configure SSH, you must first create RSA and DSA keys on each cluster node, and then copy the keys from all cluster node members into an authorized keys file on each node. To do this task, complete the following steps:

Create RSA and DSA keys on each node: Complete the following steps on each node:

1. Log in as the `oracle` user.
2. If necessary, create the `.ssh` directory in the `oracle` user's home directory and set the correct permissions on it:

```
$ mkdir ~/.ssh
$ chmod 700 ~/.ssh
```

3. Enter the following commands to generate an RSA key for version 2 of the SSH protocol:

```
$ /usr/bin/ssh-keygen -t rsa
```

At the prompts:

- Accept the default location for the key file.
- Enter and confirm a pass phrase that is different from the `oracle` user's password.

This command writes the public key to the `~/.ssh/id_rsa.pub` file and the private key to the `~/.ssh/id_rsa` file. *Never distribute the private key to anyone.*

4. Enter the following commands to generate a DSA key for version 2 of the SSH protocol:

```
$ /usr/bin/ssh-keygen -t dsa
```

At the prompts:

- Accept the default location for the key file
- Enter and confirm a pass phrase that is different from the `oracle` user's password

This command writes the public key to the `~/ .ssh/id_dsa .pub` file and the private key to the `~/ .ssh/id_dsa` file. Never distribute the private key to anyone.

Add keys to an authorized key file: Complete the following steps:

1. On the local node, determine if you have an authorized key file (`~/ .ssh/authorized_keys`). If the authorized key file already exists, then proceed to step 2. Otherwise, enter the following commands:

```
$ touch ~/.ssh/authorized_keys
$ cd ~/.ssh
$ ls
```

You should see the `id_dsa .pub` and `id_rsa .pub` keys that you have created.

2. Using SSH, copy the *contents* of the `~/ .ssh/id_rsa .pub` and `~/ .ssh/id_dsa .pub` files to the file `~/ .ssh/authorized_keys`, and provide the Oracle user password as prompted. This process is illustrated in the following syntax example with a two-node cluster, with nodes `node1` and `node2`, where the Oracle user path is `/home/oracle`:

```
[oracle@node1 .ssh]$ ssh node1 cat /home/oracle/.ssh/id_rsa.pub >>
authorized_keys
oracle@node1's password:
[oracle@node1 .ssh]$ ssh node1 cat /home/oracle/.ssh/id_dsa.pub >>
authorized_keys
[oracle@node1 .ssh]$ ssh node2 cat /home/oracle/.ssh/id_rsa.pub >>
authorized_keys
oracle@node2's password:
[oracle@node1 .ssh]$ ssh node2 cat /home/oracle/.ssh/id_dsa.pub
>>authorized_keys
oracle@node2's password:
```

Note: Repeat this process for each node in the cluster

3. Use SCP (Secure Copy) or SFTP (Secure FTP) to copy the `authorized_keys` file to the Oracle user `.ssh` directory on a remote node. The following example is with SCP, on a node called `node2`, where the Oracle user path is `/home/oracle`:

```
[oracle@node1 .ssh]scp authorized_keys node2:/home/oracle/.ssh/
```

4. Repeat step 2 and 3 for each cluster node member. When you have added keys from each cluster node member to the `authorized_keys` file on the last node you want to have as a cluster node member, then use SCP to copy the complete `authorized_keys` file back to each cluster node member

Note: The Oracle user's `~/ .ssh/authorized_keys` file on every node must contain the contents from all of the `~/ .ssh/id_rsa .pub` and `~/ .ssh/id_dsa .pub` files that you generated on all cluster nodes.

5. Change the permissions on the Oracle user's `/.ssh/authorized_keys` file on all cluster nodes:

```
$ chmod 600 ~/.ssh/authorized_keys
```

At this point, if you use `ssh` to log in to or run a command on another node, you are prompted for the pass phrase that you specified when you created the DSA key.

Enabling SSH User Equivalency on Cluster Member Nodes

To enable Oracle Universal Installer to use the `ssh` and `scp` commands without being prompted for a pass phrase, follow these steps:

1. On the system where you want to run Oracle Universal Installer, log in as the `oracle` user.

2. Enter the following commands:

```
$ exec /usr/bin/ssh-agent $SHELL
$ /usr/bin/ssh-add
```

3. At the prompts, enter the pass phrase for each key that you generated.

If you have configured SSH correctly, then you can now use the `ssh` or `scp` commands without being prompted for a password or a pass phrase.

4. If you are on a remote terminal, and the local node has only one visual (which is typical), then use the following syntax to set the `DISPLAY` environment variable:

Bourne, Korn, and Bash shells

```
$ export DISPLAY=hostname:0
```

C shell:

```
$ setenv DISPLAY 0
```

For example, if you are using the Bash shell, and if your hostname is `node1`, then enter the following command:

```
$ export DISPLAY=node1:0
```

5. To test the SSH configuration, enter the following commands from the same terminal session, testing the configuration of each cluster node, where `nodename1`, `nodename2`, and so on, are the names of nodes in the cluster:

```
$ ssh nodename1 date
$ ssh nodename2 date
.
.
.
```

These commands should display the date set on each node.

If any node prompts for a password or pass phrase, then verify that the `/.ssh/authorized_keys` file on that node contains the correct public keys.

If you are using a remote client to connect to the local node, and you see a message similar to "Warning: No xauth data; using fake authentication data for X11 forwarding," then this means that your authorized keys file is configured correctly, but your `ssh` configuration has X11 forwarding enabled. To correct this, proceed to step 6.

Note: The first time you use SSH to connect to a node from a particular system, you may see a message similar to the following:

```
The authenticity of host 'node1 (140.87.152.153)' can't be
established.
RSA key fingerprint is
7z:ez:e7:f6:f4:f2:4f:8f:9z:79:85:62:20:90:92:z9.
Are you sure you want to continue connecting (yes/no)?
```

Enter **yes** at the prompt to continue. You should not see this message again when you connect from this system to that node.

If you see any other messages or text, apart from the date, then the installation can fail. Make any changes required to ensure that only the date is displayed when you enter these commands.

You should ensure that any parts of login scripts that generate any output, or ask any questions, are modified so that they act only when the shell is an interactive shell

6. To ensure that X11 forwarding will not cause the installation to fail, create a user-level SSH client configuration file for the Oracle software owner user, as follows:
 - a. Using any text editor, edit or create the `~oracle/.ssh/config` file.
 - b. Make sure that the `ForwardX11` attribute is set to `no`. For example:

```
Host *
    ForwardX11 no
```

7. You must run Oracle Universal Installer from this session or remember to repeat steps 2 and 3 before you start Oracle Universal Installer from a different terminal session.

Preventing Oracle Clusterware Installation Errors Caused by stty Commands

During an Oracle Clusterware installation, Oracle Universal Installer uses SSH (if available) to run commands and copy files to the other nodes. During the installation, hidden files on the system (for example, `.bashrc` or `.cshrc`) will cause installation errors if they contain `stty` commands.

To avoid this problem, you must modify these files to suppress all output on `STDERR`, as in the following examples:

- Bourne, Bash, or Korn shell:

```
if [ -t 0 ]; then
    stty intr ^C
fi
```

- C shell:

```
test -t 0
if ($status == 0) then
    stty intr ^C
endif
```

Note: When SSH is not available, the Installer uses the `rsh` and `rcp` commands instead of `ssh` and `scp`.

If there are hidden files that contain `stty` commands that are loaded by the remote shell, then OUI indicates an error and stops the installation.

Configuring Shell Limits, System Configuration, and Network Tuning Parameters

On AIX systems, you do not need to configure kernel parameters. However, Oracle recommends that you set shell limits, system configuration parameters, and network tuning parameters as described in this section. Perform this configuration task on all cluster nodes.

Note: The parameter and shell limit values shown in this section are recommended values only. For production database systems, Oracle recommends that you tune these values to optimize the performance of the system. See your operating system documentation for more information about tuning kernel parameters.

Configure Shell Limits

Verify that the shell limits shown in the following table are set to the values shown. The procedure following the table describes how to verify and set the values.

Shell Limit (As Shown in <code>smit</code>)	Recommended Value
Soft FILE size	-1 (Unlimited)
Soft CPU time	-1 (Unlimited) Note: This is the default value.
Soft DATA segment	-1 (Unlimited)
Soft STACK size	-1 (Unlimited)

To view the current value specified for these shell limits, and to change them if necessary:

1. Enter the following command:


```
# smit chuser
```
2. In the **User NAME** field, enter the user name of the Oracle software owner. Example: `oracle`.
3. Scroll down the list and verify that the value shown for the soft limits listed in the previous table is -1.
If necessary, edit the existing value.
4. When you have finished making changes, press F10 to exit.

Configure System Configuration Parameters

Verify that the maximum number of processes allowed for each user is set to 2048 or greater:

Note: For production systems, this value should be at least 128 plus the sum of the `PROCESSES` and `PARALLEL_MAX_SERVERS` initialization parameters for each database running on the system.

1. Enter the following command:

```
# smit chgsys
```

2. Verify that the value shown for **Maximum number of PROCESSES allowed for each user** is greater than or equal to 2048.

If necessary, edit the existing value.

3. When you have finished making changes, press F10 to exit.

Configure Network Tuning Parameters

Verify that the network tuning parameters shown in the following table are set to the values shown or higher values. The procedure following the table describes how to verify and set the values.

Network Tuning Parameter	Recommended Value
<code>ipqmaxlen</code>	512
<code>rfc1323</code>	1
<code>sb_max</code>	2*655360
<code>tcp_recvspace</code>	65536
<code>tcp_sendspace</code>	65536
<code>udp_recvspace</code>	655360
	Note: The recommended value of this parameter is 10 times the value of the <code>udp_sendspace</code> parameter. The value must be less than the value of the <code>sb_max</code> parameter.
<code>udp_sendspace</code>	65536
	Note: This value is suitable for a default database installation. For production databases, the minimum value for this parameter is 4 KB plus the value of the database <code>DB_BLOCK_SIZE</code> initialization parameter multiplied by the value of the <code>DB_MULTIBLOCK_READ_COUNT</code> initialization parameter: $(DB_BLOCK_SIZE * DB_MULTIBLOCK_READ_COUNT) + 4\text{ KB}$

To view the current value specified for these parameters, and to change them if necessary:

1. To check the current values of the network tuning parameters, enter commands similar to the following:

```
# /usr/sbin/no -a | more
```

2. If you must change the value of any parameter, then enter the following command to determine whether the system is running in compatibility mode:

```
# /usr/sbin/lsattr -E -l sys0 -a pre520tune
```

If the system is running in compatibility mode, then the output is similar to the following, showing that the value of the `pre520tune` attribute is enable:

```
pre520tune enable Pre-520 tuning compatibility mode True
```

3. If the system is running in compatibility mode, then follow these steps to change the parameter values:

- a. Enter commands similar to the following to change the value of each parameter:

```
# /usr/sbin/no -o parameter_name=value
```

For example:

```
# /usr/sbin/no -o udp_recvspace=655360
```

- b. Add entries similar to the following to the `/etc/rc.net` file for each parameter that you changed in the previous step:

```
if [ -f /usr/sbin/no ] ; then
  /usr/sbin/no -o udp_sendspace=65536
  /usr/sbin/no -o udp_recvspace=655360
  /usr/sbin/no -o tcp_sendspace=65536
  /usr/sbin/no -o tcp_recvspace=65536
  /usr/sbin/no -o rfc1323=1
  /usr/sbin/no -o sb_max=2*655360
  /usr/sbin/no -o ipqmaxlen=512
fi
```

By adding these lines to the `/etc/rc.net` file, the values persist when the system restarts.

4. If the system is not running in compatibility mode, then enter commands similar to the following to change the parameter values:

- `ipqmaxlen` parameter:

```
/usr/sbin/no -r -o ipqmaxlen=512
```

- Other parameter:

```
/usr/sbin/no -p -o parameter=value
```

Note: If you modify the `ipqmaxlen` parameter, then you must restart the system.

These commands modify the `/etc/tunables/nextboot` file, causing the attribute values to persist when the system restarts.

Configuring the oracle User's Environment

You run Oracle Universal Installer from the `oracle` account. However, before you start Oracle Universal Installer you must configure the environment of the `oracle` user.

To configure the environment, you must:

- Set the default file mode creation mask (`umask`) to 022 in the shell startup file
- Set the `DISPLAY`, `ORACLE_BASE`, and `ORACLE_HOME` environment variables in preparation for the Oracle Clusterware installation

You should also ensure that the `PATH` variable contains `$ORACLE_HOME/bin` before `/usr/X11R6/bin`

To set the `oracle` user's environment, follow these steps:

1. Start a new terminal session; for example, start an X terminal (`xterm`).
2. Enter the following command to ensure that X Window applications can display on this system:

```
$ xhost + hostname
```

The *hostname* is the name of the local host.

3. If you are not already logged in to the system where you want to install the software, then log in to that system as the `oracle` user.
4. If you are not logged in as the `oracle` user, then switch user to `oracle`:

```
$ su - oracle
```

5. To determine the default shell for the `oracle` user, enter the following command:

```
$ echo $SHELL
```

6. Open the `oracle` user's shell startup file in any text editor:

- Bourne shell (`sh`), Bash shell (`bash`) or Korn shell (`ksh`):

```
% vi .bash_profile
```

- C shell (`csh` or `tcsh`):

```
% vi .login
```

7. Enter or edit the following line, specifying a value of 022 for the default file mode creation mask:

```
umask 022
```

8. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variable is set in the file, then remove the appropriate lines from the file.

9. Save the file, and exit from the text editor.

10. To run the shell startup script, enter one of the following commands:

- Bourne, Bash, or Korn shell:

```
$ . ./profile
```

- C shell:

```
% source ./login
```

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ DISPLAY=local_host:0.0 ; export DISPLAY
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, *local_host* is the host name or IP address of the system that you want to use to display Oracle Universal Installer (your workstation or PC).

12. If you determined that the `/tmp` directory has less than 400 MB of free disk space, then identify a file system with at least 400 MB of free space and set the `TEMP` and `TMPDIR` environment variables to specify a temporary directory on this file system:

Note: You cannot use a shared file system as the location of the temporary file directory (typically `/tmp`) for RAC installation. If you place `/tmp` on a shared file system, then the installation fails.

- a. Use the `df -k` command to identify a suitable file system with sufficient free space.
- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ su - root
# mkdir /mount_point/tmp
# chmod 775 /mount_point/tmp
# exit
```

- c. Enter commands similar to the following to set the `TEMP` and `TMPDIR` environment variables:

- * Bourne, Bash, or Korn shell:

```
$ TEMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TEMP TMPDIR
```

- * C shell:

```
% setenv TEMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```

Checking the Hardware Requirements

Each system must meet the following minimum hardware requirements:

- At least 1 GB of physical RAM
- Swap space equivalent to the multiple of the available RAM, as indicated in the following table:

Available RAM	Swap Space Required
Between 1 GB and 2 GB	1.5 times the size of RAM

On AIX systems with 1 GB or more of memory, do not increase the swap space above 2 GB. Refer to *Oracle Database Administrator's Reference for AIX* for more information about configuring swap space.

- 400 MB of disk space in the `/tmp` directory
- Up to 4 GB of disk space for the Oracle software
- 1.2 GB of disk space for a preconfigured database that uses file system storage (optional)

Note: The disk space requirement for databases that use Automatic Storage Management or raw device storage is described in [Chapter 3](#).

Additional disk space, either on a file system or in an Automatic Storage Management disk group, is required for the flash recovery area if you choose to configure automated backups.

To ensure that each system meets these requirements, follow these steps:

1. To determine the physical RAM size, enter the following command:

```
# /usr/sbin/lssattr -E -l sys0 -a realmem
```

If the size of the physical RAM installed in the system is less than the required size, then you must install more memory before continuing.

2. To determine the size of the configured swap space, enter the following command:

```
# /usr/sbin/lssps -a
```

If necessary, refer to your operating system documentation for information about how to configure additional swap space.

3. To determine the amount of disk space available in the `/tmp` directory, enter the following command:

```
# df -k /tmp
```

If there is less than 400 MB of disk space available in the `/tmp` directory, then complete one of the following steps:

- Delete unnecessary files from the `/tmp` directory to make available the disk space required.
 - Set the `TEMP` and `TMPDIR` environment variables when setting the `oracle` user's environment (described later).
 - Extend the file system that contains the `/tmp` directory. If necessary, contact your system administrator for information about extending file systems.
4. To determine the amount of free disk space on the system, enter the following command:

```
# df -k
```


The following table shows the approximate disk space requirements for software files for each installation type:

Installation Type	Requirement for Software Files (GB)
Enterprise Edition	4 GB
Standard Edition	4 GB
Custom (maximum)	4 GB

- To determine whether the system architecture can run the software, enter the following command:

```
# /usr/bin/getconf HARDWARE_BITMODE
```

Note: The expected output of this command is 64. If you do not see the expected output, then you cannot install the software on this system.

Checking the Network Requirements

Check that you have the networking hardware and internet protocol (IP) addresses required for an Oracle Real Application Clusters installation.

Note: For the most up-to-date information about supported network protocols and hardware for RAC installations, refer to the Certify pages on the Oracle *MetaLink* Web site at

<http://metalink.oracle.com>

Network Hardware Requirements

Each node in the cluster must meet the following requirements:

- Each node must have at least two network adapters: one for the public network interface, and one for the private network interface (the interconnect).
- The public interface names associated with the network adapters for each network must be the same on all nodes, and the private interface names associated with the network adaptors should be the same on all nodes.

For example: With a two-node cluster, you cannot configure network adapters on node1 with en0 as the public interface, but on node2 have en1 as the public interface. Public interface names must be the same, so you must configure en0 as public on *both* nodes. You should configure the private interfaces on the same network adapters as well. If en1 is the private interface for node 1, then en1 should be the private interface for node 2.

- For increased reliability, configure redundant public and private network adapters for each node.
- For the public network, each network adapter must support TCP/IP.
- For the private network, the interconnect must support the user datagram protocol (UDP) using high-speed network adapters and switches that support TCP/IP (Gigabit Ethernet or better recommended).

Note: UDP is the default interconnect protocol for RAC, and TCP is the interconnect protocol for Oracle Clusterware.

Token-Ring is not supported for the interconnect.

- For the private network, the endpoints of all designated interconnect interfaces must be completely reachable on the network. There should be no node that is not connected to every private network. You can test whether an interconnect interface is reachable using a ping command.

IP Address Requirements

Before starting the installation, you must identify or obtain the following IP addresses for each node:

- An IP address and an associated host name registered in the domain name service (DNS) for each public network interface
- One unused virtual IP address (VIP) and an associated virtual host name registered in DNS, or resolved in the host file, or both, that you will configure for the primary public network interface

The VIP address must be in the same subnet as the associated public interface. After installation, you can configure clients to use the virtual host name or IP address. If a node fails, then its VIP address fails over to another node. During installation, OUI pings the VIP, so ensure that the VIP is pingable before starting installation.

- A private IP address and optional host name for each private interface
Oracle recommends that you use non-routable IP addresses for the private interfaces; for example: 10.*.* or 192.168.*.*. You can use the `/etc/hosts` file on each node to associate private host names with private IP addresses.

In the example described in the following table, the node `rac1` has two public interfaces and one private interface. This is a proper configuration of host names and IP addresses. Each node of the cluster on which node `rac1` is a member must have similar host names and IP addresses:

Host Name	Type	IP Address	Registered In
<code>rac1.mydomain.com</code>	Public	143.47.43.100	DNS (optional)
<code>rac1_2.mydomain.com</code>	Public	143.46.51.101	DNS (optional)
<code>rac1_vip.mydomain.com</code>	Virtual	143.47.43.104	DNS (optional)
<code>rac1_priv1</code>	Private	10.0.0.1	<code>/etc/hosts</code>

Node Time Requirements

Before starting the installation, ensure that each member node of the cluster is set as closely as possible to the same date and time. Oracle strongly recommends using the Network Time Protocol feature of most operating systems for this purpose, with all nodes using the same reference Network Time Protocol server.

Configuring the Network Requirements

To verify that each node meets the requirements, follow these steps:

1. If necessary, install the network adapters for the public and private networks and configure them with either public or private IP addresses.
2. Register the host names and IP addresses for the public network interfaces in DNS.
3. For each node, register one virtual host name and IP address in DNS.
4. For each private interface on every node, add a line similar to the following to the `/etc/hosts` file on all nodes, specifying the private IP address and associated private host name:

```
10.0.0.1    rac1-priv1
```

5. To identify the interface name and associated IP address for every network adapter, enter the following command:

```
# /sbin/ifconfig
```

From the output, identify the interface name and IP address for all network adapters that you want to specify as public or private network interfaces.

Note: When you install Oracle Clusterware and RAC, you will require this information.

Checking the Network Setup with CVU

As the Oracle user, enter a command using the following syntax to verify node connectivity among all of the nodes for which your cluster is configured:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh comp nodecon -n node_list [-verbose]
```

In the preceding syntax example, the variable `node_list` is a comma-separated list of nodes in your cluster. This command detects all the network interfaces available on the cluster nodes, and verifies the connectivity among all the nodes through the network interfaces it finds.

Select the option `-verbose` to receive progress updates as the CVU performs its system checks, and detailed reporting of the test results.

For example, to verify node connectivity on a two-node cluster with nodes `node1` and `node2`, with the mountpoint `/dev/dvdrom`, and with updates and a summary of the verification checks the CVU performs, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh comp nodecon -n node1,node2 -verbose
```

Note: You can use this command to obtain a list of all the interfaces available on the nodes that are suitable for use as VIPs, as well as a list of private interconnects that are connecting successfully on all nodes.

Checking the Software Requirements

Depending on the products that you intend to install, verify that the following software is installed on the system. The procedure following the table describes how to verify whether these requirements are addressed.

Note: Oracle Universal Installer performs checks on your system to verify that it meets the listed requirements. To ensure that these checks pass, verify the requirements before you start Oracle Universal Installer.

Item	Requirement
Operating system	<p>The following operating system versions and maintenance level are required:</p> <p>AIX 5L version 5.2, Maintenance Level 04 or later</p> <p>AIX 5L version 5.3 Maintenance Level 02 or later</p>
Operating system filesets	<p>The following operating system filesets are required:</p> <p> bos.adt.base bos.adt.lib bos.adt.libm bos.perf.libperfstat bos.perf.perfstat bos.perf.proctools rsct.basic.rte rsct.compat.client.rte </p> <p> xlc.aix50.rte 7.0.0.4 xlc.rte 7.0.0.1 </p> <p>To obtain the previous two xlc filesets mentioned here, Oracle Database10gR2 users who do not install the IBM XL C/C++ Enterprise Edition V7.0 compiler should install the IBM XL C/C++ Enterprise Edition V7.0 for AIX Runtime Environment Component. Download all runtime environment file sets, with no license requirement, in one package from the following Web site:</p> <p>http://www-1.ibm.com/support/docview.wss?uid=swg24009788</p>
RAC	<p>High Availability Cluster Multi-Processing (HACMP) v5.2</p> <p>Note: HACMP is required only if you want to use raw logical volumes for Oracle Clusterware or database file storage. However, it is supported for all installations.</p> <p>General Parallel File System (GPFS) v2.3.0.3 or later</p> <p>Note: GPFS is required only if you want to use a cluster file system for Oracle Clusterware or database files.</p>
ADA	OC Systems PowerAda 5.3
Oracle JDBC/OCI Drivers	<p>You can use the following optional IBM JDK versions with the Oracle JDBC/OCI drivers, however they are not required for the installation:</p> <ul style="list-style-type: none"> ■ JDK 1.4.2.1 (64-bit) ■ JDK 1.4.2.2 (32-bit) ■ JDK 1.3.1.16 (32-bit) <p>Note: IBM JDK 1.4.2 is installed with this release.</p>
Pro*FORTRAN	IBM XL Fortran V9.1 for AIX

Item	Requirement
PL/SQL native compilation, Pro*C/C++, Oracle Call Interface, Oracle C++ Call Interface, Oracle XML Developer's Kit (XDK), GNU Compiler Collection (GCC)	<ul style="list-style-type: none"> ■ May 2005 XL C/C++ Enterprise Edition V7.0 for AIX PTF (7.0.0.2): You can download the PTF from the following link: http://www-1.ibm.com/support/docview.wss?uid=swg24009787 ■ gcc 3.3.2
Pro*COBOL	<ul style="list-style-type: none"> ■ MicroFocus Cobol 4.0 SP1 (64bit) ■ MicroFocus Cobol 4.0 SP1 (32bit)
Oracle Messaging Gateway	IBM WebSphere MQ V5.3, client and server: mqm.Client.Bnd mqm.Server.Bnd
JDK	<ul style="list-style-type: none"> ■ IBM JDK 1.4.2
Utilities	<ul style="list-style-type: none"> ■ GNUfind 4.1 ■ gdb 6.0 ■ Gmake 3.80 ■ Gnutar 1.13 ■ Perl 5.005_03 + MIME 2.21 ■ Perl 5.6 + MIME 2.21 ■ Perl 5.8.3 ■ Python 2.2 ■ Unzip 5.4.2 ■ Zip 2.3

To ensure that the system meets these requirements:

1. To determine the version of AIX installed, enter the following command:

```
# oslevel -r
```

If the operating system version is lower than AIX 5.3, then upgrade your operating system to at least this maintenance level. AIX 5L version 5.3 maintenance packages are available from the following Web site:

<http://www-912.ibm.com/eserver/support/fixes/>

2. To determine whether the required filesets are installed and committed, enter a command similar to the following:

```
# lspp -l bos.adt.base bos.adt.lib bos.adt.libm bos.perf.perfstat \
bos.perf.libperfstat bos.perf.proctools rsct.basic.rte
```

If a fileset is not installed and committed, then install it. Refer to your operating system or software documentation for information about installing filesets.

Verify that the following patches are installed on the system. The procedure following the table describes how to check these requirements

Note: There may be more recent versions of the patches listed installed on your system. If a listed patch is not installed, then determine if you have a more recent patch installed that includes the listed patch before you install the patch version listed.

Installation Type or Product	Requirement
All AIX 5L v5.2 installations	<p>Authorized Problem Analysis Reports (APARs) for AIX 5L v5.2 ML 4:</p> <ul style="list-style-type: none"> ■ IY63133: large percentage of CPU time spent in ldata_balance routine ■ IY63366: dlsym returns null even for valid symbol in AIX520 ML-4 ■ IY64691: chvg -b can cause corruption and crash ■ IY64737: AIO can hang in knotunlock ■ IY65001: mklvcopy on a striped lv is failing to update lvcb ■ IY64978: deadlock with concurrent renaming and unlinking under JFS
All AIX 5L v5.3 installations	<p>Authorized Problem Analysis Reports (APARs) for AIX 5L v5.3 ML02:</p> <ul style="list-style-type: none"> ■ IY68989
PL/SQL native compilation, Pro*C/C++, Oracle Call Interface, Oracle C++ Call Interface, Oracle XML Developer's Kit (XDK) AIX 5L v5.3 and v5.2	<p>May 2005 XL C/C++ Enterprise Edition V7.0 for AIX PTF (7.0.0.2):</p> <ul style="list-style-type: none"> ■ IY65361: May 2005 XL C Enterprise Edition V7.0 for AIX PTF ■ IY65362: MAY 2005 XL C/C++ Enterprise Edition V7 for AIX
Oracle JDBC/OCI Drivers AIX 5L v5.3 and v5.2	<p>Note: These APARs are required only if you are using the associated JDK version.</p> <p>APAR required for JDK 1.4.2 (64-bit):</p> <ul style="list-style-type: none"> ■ IY63533: JDK 1.4.2 64-bit SR1 caix64142-20040917 <p>APARs required for JDK 1.3.1.16 (32-bit):</p> <ul style="list-style-type: none"> ■ IY58350: SDK 1.3.1 32-BIT SR7P : CA131IFX-20040721A ■ IY65305: JAVA142 32-BIT PTF : CA142IFX-20041203
Oracle Messaging Gateway	<p>Corrective service diskettes (CSDs) for WebSphere MQ: CSD03 or later for WebSphere MQ V5.3 FP 9</p>

Installation Type or Product	Requirement
RAC AIX 5L v5.3	<p>APARs required for HACMP version 5.2 on AIX 5L v5.3 ML 02:</p> <ul style="list-style-type: none"> ■ IY60759 (efix): Application fails reading the HACMP cluster configuration ■ IY61034: HACMP support of the DS4100 Storage Server ■ IY61770: HACMP support of the DS4100 Storage Server ■ IY62191: HACMP support of the DS4100 Storage Server <p>APARs required for GPFS v2.3:</p> <ul style="list-style-type: none"> ■ IY63969: mandatory service for GPFS v2.3 for AIX ■ IY69911: corrupted kernel using direct I/O across GPFS block boundary ■ IY70276: GPFS returns out of space when there is still space in the filesystem ■ IY70277: receive enospc on mkfile in a GPFS filesystem when filesystem not full ■ IY74097 (efix): corrupt archive library after adding members
RAC AIX 5L v5.2	<p>APARs required for HACMP version 5.2 on AIX 5L v5.2 ML 04:</p> <ul style="list-style-type: none"> ■ IY60759 (efix): Application fails reading the HACMP cluster configuration <p>APARs required for GPFS v2.3:</p> <ul style="list-style-type: none"> ■ IY63969: mandatory service for GPFS v2.3 for AIX ■ IY69911: corrupted kernel using direct I/O across GPFS block boundary ■ IY70276: GPFS returns out of space when there is still space in the filesystem ■ IY70277: receive enospc on mkfile in a GPFS filesystem when filesystem not full ■ IY74097 (efix): corrupt archive library after adding members
JDK	<p>AIX 5L v5.2</p> <ul style="list-style-type: none"> ■ IY58350 Patch for SDK 1.3.1.16 (32-bit) ■ IY63533 Patch for SDK 1.4.2.1 (64-bit) ■ IY65305 Patch for SDK 1.4.2.2 (32-bit) <p>AIX 5L v5.3</p> <ul style="list-style-type: none"> ■ IY58350 Patch for SDK 1.3.1.16 (32-bit) ■ IY63533 Patch for SDK 1.4.2.1 (64-bit) ■ IY65305 Patch for SDK 1.4.2.2 (32-bit)

To ensure that the system meets these requirements:

1. To determine whether an APAR is installed, enter a command similar to the following:

```
# /usr/sbin/instfix -i -k "IY43980 IY44810 IY45462 IY45707 IY46214 IY46605 \
IY48525 IY51801 IY56024"
```

If an APAR is not installed, then download it from the following Web site and install it:

<http://www-03.ibm.com/servers/eserver/support/pseries/aixfixes.html>

2. To determine whether a PTF is installed, enter a command similar to the following:

```
# lslpp -l -B U489726 U485561 ...
```

If a PTF is not installed, then download it from the following Web site and install it:

<http://www-03.ibm.com/servers/eserver/support/pseries/aixfixes.html>

3. If you require a CSD for WebSphere MQ, then refer to the following Web site for download and installation information:

<http://www.ibm.com/software/integration/mqfamily/support/summary/aix.html>

Running the rootpre.sh Script

Note: Do not run the `rootpre.sh` script if you have a later release of the Oracle Database software already installed on this system.

Run the `rootpre.sh` script:

1. Switch user to root:

```
$ su - root
```

2. Complete one of the following steps, depending on the location of the installation

If the installation files are on disc, enter a command similar to the following, where `directory_path` is the disc mount point directory or the path of the database directory on the DVD:

```
# /directory_path/rootpre.sh
```

If the installation files are on the hard disk, change `directory` to the `Disk1` directory and enter the following command:

```
# ./rootpre.sh
```

3. Exit from the root account:

```
# exit
```

4. Repeat steps 1 through 3 on all nodes of the cluster.

Note: Do not run the `rootpre.sh` script if you have a later release of Oracle Database software already installed on this system.

Checking the Hardware and Operating System Setup with CVU

As the `oracle` user, use the following command syntax to start Cluster Verification Utility (CVU) stage verification to check hardware and operating system setup:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -post hws -n node_list  
[-verbose]
```


In the preceding syntax example, replace the variable *node_list* with the names of the nodes in your cluster, separated by commas. For example, to check the hardware and operating system of a two-node cluster with nodes *node1* and *node2*, with the mountpoint */dev/dvdrom/* and with the option to limit the output to the test results, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -post hwos -n node1,node2
```

Select the option *-verbose* to receive detailed reports of the test results, and progress updates about the system checks performed by Cluster Verification Utility.

Checking the Operating System Requirements Setup with CVU

As the *oracle* user, use the following command syntax to check if your system meets the operating system requirement pre-installation tasks:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh comp sys -n node_list -p  
{crs|database} -osdba osdba_group -orainv orainv_group -verbose
```

In the preceding syntax example:

- The variable *mountpoint* is the mountpoint of the Oracle 10g Release 2 (10.2) installation media
- The variable *node_list* is the list of nodes in your cluster, separated by commas
- The *-p* flag identifies either *crs* or *database*, and indicates that checks are performed for Oracle Clusterware or Oracle Database system requirements
- The variable *osdba_group* is the name of your OSDBA group, typically *dba*
- The variable *orainv_group* is the name of your Oracle Inventory group, typically *oinstall*

You can select the option *-verbose* to receive progress updates as the CVU performs its system checks, and detailed reporting of the test results.

For example, to perform a system check for an Oracle Clusterware installation on a two-node cluster with nodes *node1* and *node2*, with the OSDBA *dba* and Oracle inventory group *oinstall*, and with the media mountpoint */dev/dvdrom/*, then enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh comp sys -n node1,node2 -p crs -osdba  
crs -orainv oinstall
```

Identifying Required Software Directories

You must identify or create the following directories for the Oracle software, as follows:

- [Oracle Base Directory](#)
- [Oracle Inventory Directory](#)
- [Oracle Clusterware Home Directory](#)
- [Oracle Home Directory](#)

The following subsections describe the requirements for these directories.

Oracle Base Directory

The Oracle base directory acts as a top-level directory for Oracle software installations. Optimal Flexible Architecture (OFA) guidelines recommend that you use a path similar to the following for the Oracle base directory:

```
/mount_point/app/oracle_sw_owner
```

In this example:

- *mount_point* is the mount point directory for the file system that will contain the Oracle software.

The examples in this guide use `/u01` for the mount point directory. However, you could choose another mount point directory, `/oracle` or `/opt/oracle` for example.

- *oracle_sw_owner* is the operating system user name of the Oracle software owner, for example `oracle`.

You can use the same Oracle base directory for more than one installation or you can create separate Oracle base directories for different installations. If different operating system users install Oracle software on the same system, then each user must create a separate Oracle base directory. The following example Oracle base directories could all exist on the same system:

```
/u01/app/oracle  
/u01/app/orauser  
/opt/oracle/app/oracle
```

The following sections describe how to identify existing Oracle base directories that might be suitable for your installation and how to create an Oracle base directory if necessary.

Regardless of whether you create an Oracle base directory or decide to use an existing one, you must set the `ORACLE_BASE` environment variable to specify the full path to the Oracle base directory.

Note: The Oracle base directory can be on a local file system or on a GPFS file system.

Oracle Inventory Directory

The Oracle Inventory directory (`oraInventory`) stores an inventory of all software installed on the system. It is required by, and shared by, all Oracle software installations on a single system. The first time you install Oracle software on a system, Oracle Universal Installer prompts you to specify the path to this directory. If you are installing the software on a local file system, then Oracle recommends that you choose the following path:

```
oracle_base/oraInventory
```

If the Oracle base directory is on a cluster file system, then you must specify a path for the Oracle Inventory directory on a local file system. The Oracle base directory must be on a local file system to enable all of the nodes to have separate inventories.

Note: The Oracle Inventory directory should not be placed on a device that is shared across nodes

Oracle Universal Installer creates the directory that you specify, and sets the correct owner, group, and permissions for it. You do not need to create it.

Note: All Oracle software installations rely on the Oracle base directory. Make sure that you back it up regularly.

Do not delete the Oracle base directory unless you have completely removed all Oracle software from the system.

Oracle Clusterware Home Directory

The Oracle Clusterware home directory is the directory where you choose to install the software for Oracle Clusterware. You must install Oracle Clusterware in a separate home directory. When you run Oracle Universal Installer, it prompts you to specify the path to this directory, as well as a name that identifies it. Oracle recommends that you specify a path similar to the following for the Oracle Clusterware home directory:

```
/u01/app/oracle/product/crs
```

Note: Because you must change the permissions of all of the parent directories of the Oracle Clusterware home directory after installing the software to grant write access only to the `root` user, the Oracle Clusterware home directory must not be a subdirectory of the Oracle base directory.

Oracle Home Directory

The Oracle home directory is the directory where you choose to install the software for a particular Oracle product. You must install different Oracle products, or different releases of the same Oracle product, in separate Oracle home directories. When you run Oracle Universal Installer, it prompts you to specify the path to this directory, as well as a name that identifies it. The directory that you specify must be a subdirectory of the Oracle base directory. Oracle recommends that you specify a path similar to the following for the Oracle home directory:

```
oracle_base/product/10.2.0/db_1
```

Oracle Universal Installer creates the directory path that you specify under the Oracle base directory. It also sets the correct owner, group, and permissions on it. You do not need to create this directory.

Identifying or Creating an Oracle Base Directory

Before starting the installation, you must either identify an existing Oracle base directory or if required, create one. This section contains information about the following:

- [Identifying an Existing Oracle Base Directory](#)
- [Creating an Oracle Base Directory](#)

Note: You can choose to create an Oracle base directory, even if other Oracle base directories exist on the system.

Identifying an Existing Oracle Base Directory

Existing Oracle base directories might not have paths that comply with OFA guidelines. However, if you identify an existing Oracle Inventory directory or existing Oracle home directories, you can usually identify the Oracle base directories, as follows:

- Identifying an existing Oracle Inventory directory

Enter the following command on all nodes in the cluster to view the contents of the `oraInst.loc` file:

```
# more /etc/oraInst.loc
```

If the `oraInst.loc` file exists, then the output from this command is similar to the following:

```
inventory_loc=/u01/app/oracle/oraInventory
inst_group=oinstall
```

The `inventory_loc` parameter identifies the Oracle Inventory directory (`oraInventory`) on that system. The parent directory of the `oraInventory` directory is typically an Oracle base directory. In the previous example, `/u01/app/oracle` is an Oracle base directory.

- Identifying existing Oracle home directories

Enter the following command on all nodes in the cluster to view the contents of the `oratab` file:

```
# more /etc/oratab
```

If the `oratab` file exists, then it contains lines similar to the following:

```
*/u03/app/oracle/product/10.2.0/db_1:N
*/opt/orauser/infra_904:N
*/oracle/9.2.0:N
```

The directory paths specified on each line identify Oracle home directories. Directory paths that end with the user name of the Oracle software owner that you want to use are valid choices for an Oracle base directory. If you intend to use the `oracle` user to install the software, then you could choose one of the following directories from the previous example:

```
/u03/app/oracle
/oracle
```

Note: If possible, choose a directory path similar to the first (`/u03/app/oracle`). This path complies with the OFA guidelines.

Before deciding to use an existing Oracle base directory for this installation, make sure that it satisfies the following conditions:

- It should not be on the same file system as the operating system.
- It must have an identical path on all nodes in the cluster.
- It must have 1.4 GB free disk space on all the nodes in the cluster

To determine the free disk space on the file system where the Oracle base directory is located, enter the following command:

```
# df -k oracle_base_path
```

When you are configuring the `oracle` user's environment in the section "[Creating the Oracle Clusterware Home Directory](#)" on page 2-33, set the `ORACLE_BASE` environment variable to specify the directory you choose.

If an Oracle base directory does not exist on the system, or if you want to create an Oracle base directory, then refer to the following section.

Creating an Oracle Base Directory

Before you create an Oracle base directory, you must identify an appropriate file system. The Oracle base directory requires 1.5 GB of free disk space.

To identify an appropriate file system, follow these steps:

1. Use the `df -k` command to determine the free disk space on each mounted file system.
2. From the display, identify a file system that has appropriate free space.

Note: The Oracle base directory can be on a local file system or on a GPFS file system.

The path to the Oracle base directory must be the same on all nodes.

3. Note the name of the mount point directory for the file system that you identified.

To create the Oracle base directory and specify the correct owner, group, and permissions for it, follow these steps:

1. Enter commands similar to the following to create the recommended subdirectories in the mount point directory that you identified, and to set the appropriate owner, group, and permissions on them:

```
# mkdir -p /mount_point/app/oracle_sw_owner
# chown -R oracle:oinstall /mount_point/app/oracle_sw_owner
# chmod -R 775 /mount_point/app/oracle_sw_owner
```

For example, if the mount point you identify is `/u01`, and `oracle` is the user name of the Oracle software owner, then the recommended Oracle base directory path is as follows:

```
/u01/app/oracle
```

2. If necessary, repeat the commands listed in the previous step to create the same directory on the other nodes in the cluster.
3. When you configure the `oracle` user's environment later in this chapter, set the `ORACLE_BASE` environment variable to specify the Oracle base directory you have created in this task.

Creating the Oracle Clusterware Home Directory

Oracle Universal Installer (OUI) creates the Oracle Clusterware home directory for you. Ensure before you start the installation that you provide sufficient disk space on a file system for the Oracle Clusterware directory, and the parent directory of the Oracle Clusterware directory space is writable by the Oracle user.

To identify an appropriate file system, follow these steps:

1. Use the `df -k` command to determine the free disk space on each mounted file system.
2. From the display, identify a file system that has at least 120 MB of free disk space.
If you are using the same file system for the Oracle base directory, then this 120 MB of disk space is additional to the free disk space requirement that you identified previously.

Note: The file system can be on a local file system or on a GPFS file system.

The path to the Oracle Clusterware home directory must be the same on all nodes.

3. Note the name of the mount point directory for the file system that you identified.

To create the Oracle Clusterware home directory and specify the correct owner, group, and permissions for it, follow these steps:

1. Enter commands similar to the following to create the recommended subdirectories in the mount point directory that you identified and set the appropriate owner, group, and permissions on them:

```
# mkdir -p /mount_point/crs/oracle_sw_owner/product/10/app
# chown -R root:oinstall /mount_point/crs
# chmod -R 775 /mount_point/crs/oracle_sw_owner
```

If the mount point you identified is `/u01`, then the recommended Oracle Clusterware home directory path is as follows:

```
/u01/crs/oracle/product/10/crs
```

Note: After installation, you should change permissions so that only the root user can write to the Oracle Clusterware home directory.

2. If necessary, repeat the commands listed in the previous step to create the same directory on the other nodes in the cluster.
3. Enter commands similar to the following to set the `ORACLE_BASE` and `ORACLE_HOME` environment variable in preparation for the Oracle Clusterware installation:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_BASE=/u01/app/oracle
$ ORACLE_HOME=/u01/crs/oracle/product/10/app
$ export ORACLE_BASE
$ export ORACLE_HOME
```

- C shell:

```
% setenv ORACLE_BASE /u01/app/oracle
% setenv ORACLE_HOME /u01/crs/oracle/product/10/app
```

4. Enter the following commands to ensure that the `TNS_ADMIN` environment variable is not set:

- Bourne, Bash, or Korn shell:

```
$ unset TNS_ADMIN
```

- C shell:

```
% unsetenv TNS_ADMIN
```

5. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the `umask` command displays a value of 22, 022, or 0022 and the environment variables that you set in this section have the correct values.

Stopping Existing Oracle Processes for Upgrades or Co-existing Databases

[Table 2–1](#) provides an overview of what you need to do if you have an existing Oracle database on the system where you plan to install Oracle Database 10g Release 2 (10.2). Review the table, and perform tasks as required.

See Also: *Oracle Database Upgrade Guide* for additional information about preparing for and performing upgrades.

Table 2–1 Overview of System Preparation for Upgrades or Co-existing Databases

Installation Scenario	What you need to do
Upgrading from Oracle Database 10g Release 1 (10.1) to 10g Release 2 (10.2)	No additional tasks. Refer to Installing Oracle 10g Release 2 on a System with Oracle 10g Release 1 on page 2-36
installing Oracle Database 10g Release 2 (10.2) on a system to co-exist with Oracle Database 10g Release 1 (10.1)	No additional tasks. Refer to Installing Oracle 10g Release 2 on a System with Oracle 10g Release 1 on page 2-36
Upgrading from Oracle9i Release 9.2 to Oracle Database 10g Release 2 (10.2)	Shut down the Global Service Daemon, and shut down a default listener on port 1521, if present. Refer to Installing Oracle 10g Release 2 on a System with Oracle9i Release 2 on page 2-36
Installing Oracle Database 10g Release 2 (10.2) on a system to co-exist with Oracle9i Release 9.2	Shut down a default listener on port 1521, if present, and shut down the Global Service Daemon. Refer to Installing Oracle 10g Release 2 on a System with Oracle9i Release 2 on page 2-36

Installing Oracle 10g Release 2 on a System with Oracle 10g Release 1

If your system has an Oracle Database Release 10g Release 10.1 installation, and you install an Oracle Database 10g Release 2 (10.2) either to coexist with or to upgrade the 10.1, then most installation types configure and start a default Oracle Net listener using TCP/IP port 1521 and the IPC key value EXTPROC. One of the following occurs:

- During a co-existing installation, Database Configuration Assistant (DBCA) automatically migrates the listener and related files from the 10.1 Oracle home to the 10.2 Oracle home.
- During an upgrade, Oracle Database Upgrade Assistant (DBUA) automatically locates the Oracle 10g release 1 (10.1) listener, and migrates it to Oracle 10g release 2.

Proceed to [Chapter 3](#).

Installing Oracle 10g Release 2 on a System with Oracle9i Release 2

This section provides instructions for preparing

Explanation of Tasks If you are installing an Oracle Database 10g Release 2 (10.2) on a system with an existing Oracle9i Release 2 (9.2) database, and the Oracle Net listener process is using the *same* port or key value as the default used with the Oracle 10g Release 2 (10.2) installation, port 1521, then Oracle Universal Installer can only configure the new listener; it cannot start it. To ensure that the new listener process starts during the installation, you must shut down any existing listeners before starting Oracle Universal Installer. To do this, refer to "[Shutting Down the Listener](#)" on page 2-36

You must shut down the Global Services Daemon (GSD), because otherwise, during 10g Release 2 (10.2) installation, the Oracle9i Release 9.2 SRVM shared data is upgraded into an Oracle Cluster Registry that the 9.2 GSD will not be able to use. The 10.2 Oracle Clusterware installation starts a 10g Release 2 (10.2) GSD to serve the Oracle9i 9.2 clients. To do this, refer to "[Shutting down the Global Services Daemon](#)" on page 2-37

Shutting Down the Listener To determine whether an existing Oracle9i listener process is running and to shut it down if necessary, follow these steps:

1. Switch user to oracle:

```
# su - oracle
```

2. Enter the following command to determine whether an Oracle9i listener process is running and to identify its name and the Oracle home directory in which it is installed:

```
$ ps -ef | grep tnslnsr
```

This command displays information about the Oracle Net listeners running on the system:

```
... oracle_home1/bin/tnslnsr LISTENER -inherit
```

In this example, *oracle_home1* is the Oracle home directory where the listener is installed and LISTENER is the listener name.

Note: If no Oracle Net listeners are running, then proceed to [Chapter 3](#).

3. Set the ORACLE_HOME environment variable to specify the appropriate Oracle home directory for the listener:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_HOME=oracle_home1  
$ export ORACLE_HOME
```

- C or tcsh shell:

```
% setenv ORACLE_HOME oracle_home1
```

4. Enter the following command to identify the TCP/IP port number and IPC key value that the listener is using:

```
$ $ORACLE_HOME/bin/lsnrctl status listenername
```

Note: If the listener uses the default name LISTENER, then you do not have to specify the listener name in this command.

5. Enter a command similar to the following to stop the listener process:

```
$ $ORACLE_HOME/bin/lsnrctl stop listenername
```

6. Repeat this procedure to stop all listeners running on this system and on all other nodes in the cluster.

Shutting down the Global Services Daemon As the Oracle user, on each node of the cluster, use the following syntax to shut down the GSD:

```
$ cd 92_Oracle_home  
$ bin/gsdctl stop
```

In the preceding syntax example, the variable *92_Oracle_home* is the Oracle9i Release 2 (9.2) database home.

Configuring Oracle Clusterware and Oracle Database Storage

This chapter describes the storage configuration tasks that you must complete before you start Oracle Universal Installer. It includes information about the following tasks:

- [Reviewing Storage Options for Oracle Clusterware, Database, and Recovery Files](#)
- [Configuring Storage for Oracle Clusterware Files on a Supported Shared File System](#)
- [Configuring Storage for Oracle Clusterware Files on Raw Devices](#)
- [Choosing a Storage Option for Oracle Database Files](#)
- [Configuring Disks for Automatic Storage Management](#)
- [Configuring Database File Storage on Raw Devices](#)

Reviewing Storage Options for Oracle Clusterware, Database, and Recovery Files

This section describes supported options for storing Oracle Clusterware files, Oracle Database files, and data files. It includes the following sections:

- [Overview of Storage Options](#)
- [Checking for Available Shared Storage with CVU](#)

Overview of Storage Options

Use the following overview to help you select your storage option:

Overview of Oracle Clusterware Storage Options

There are two ways of storing Oracle Clusterware files:

- **A supported shared file system:** The supported file system is:
 - General Parallel File System (GPFS): A cluster file system for AIX that provides concurrent file access
- **Raw partitions:** Raw partitions are raw disks that are accessed either through a logical volume manager (LVM), or through non-LVM file systems.

Overview of Oracle Database and Recovery File Options

There are three ways of storing Oracle Database and recovery files:

- **Automatic Storage Management:** Automatic Storage Management (ASM) is an integrated, high-performance database file system and disk manager for Oracle files.
- **A supported shared file system:** The supported file system is:
 - General Parallel File System (GPFS): Note that if you intend to use GPFS for your data files, then you should create partitions large enough for the database files when you create partitions for Oracle Clusterware. If you intend to store Oracle Clusterware files on GPFS, then you must ensure that GPFS volume sizes are at least 500 MB each.
- **Raw partitions (database files only):** A raw partition is required for each database file.

See Also: For information about certified compatible storage options, refer to the Oracle Storage Compatibility Program (OSCP) Web site, which is at the following URL:

<http://www.oracle.com/technology/deploy/availability/htdocs/oscp.html>

General Storage Considerations

For all installations, you must choose the storage option that you want to use for Oracle Clusterware files and Oracle Database files. If you want to enable automated backups during the installation, then you must also choose the storage option that you want to use for recovery files (the flash recovery area). You do not have to use the same storage option for each file type.

For single-instance Oracle Database installations using Oracle Clusterware for failover, you must use GPFS, ASM, or shared raw disks if you do not want the failover processing to include dismounting and remounting disks.

The following table shows the storage options supported for storing Oracle Clusterware files, Oracle Database files, and Oracle Database recovery files. Oracle Database files include data files, control files, redo log files, the server parameter file, and the password file. Oracle Clusterware files include the Oracle Cluster Registry (OCR), a mirrored OCR file (optional), the Oracle Clusterware voting disk, and additional voting disk files (optional).

Note: For the most up-to-date information about supported storage options for RAC installations, refer to the Certify pages on the *OracleMetaLink* Web site:

<http://metalink.oracle.com>

Storage Option	File Types Supported			
	OCR and Voting Disk	Oracle Software	Database	Recovery
Automatic Storage Management	No	No	Yes	Yes
General Parallel File System (GPFS)	Yes	Yes	Yes	Yes
Local storage	No	Yes	No	No
Raw Logical Volumes Managed by HACMP	Yes	No	Yes	Yes

Use the following guidelines when choosing the storage options that you want to use for each file type:

- You can choose any combination of the supported storage options for each file type as long as you satisfy any requirements listed for the chosen storage options.
 - Oracle recommends that you choose Automatic Storage Management (ASM) as the storage option for database and recovery files.
 - For Standard Edition RAC installations, ASM is the only supported storage option for database or recovery files.
 - You cannot use ASM to store Oracle Clusterware files, because these files must be accessible before any Oracle instance starts.
 - If you intend to use ASM with RAC, and you are configuring a new ASM instance, then you must ensure that your system meets the following conditions:
 - All nodes on the cluster have the release 2 (10.2) version of Oracle Clusterware installed
 - Any existing ASM instance on any node in the cluster is shut down
 - If you intend to upgrade an existing RAC database, or a RAC database with ASM instances, then you must ensure that your system meets the following conditions:
 - The RAC database or RAC database with ASM instance is running on the node from which the Oracle Universal Installer (OUI) and Database Configuration Assistant (DBCA) is run
 - The RAC database or RAC database with an ASM instance is running on the *same* nodes that you intend to make members of the new cluster installation. For example, if you have an existing RAC database running on a three-node cluster, then you must install the upgrade on all three nodes. You cannot upgrade only 2 nodes of the cluster, removing the third instance in the upgrade.
- See Also:** *Oracle Database Upgrade Guide* for information about how to prepare for upgrading an existing database
- If you do not have a storage option that provides external file redundancy, then you must configure at least three voting disk areas to provide voting disk redundancy.

After You Have Selected Disk Storage Options

When you have determined your disk storage options, you must perform the following tasks in the following order:

1: Check for available shared storage with CVU

Refer to [Checking for Available Shared Storage with CVU](#) on page 3-4

2: Configure shared storage for Oracle Clusterware files

- **To use a file system (local or GPFS) for Oracle Clusterware files**, refer to [Configuring Storage for Oracle Clusterware Files on a Supported Shared File System](#) on page 3-4
- **To use raw devices (partitions) for Oracle Clusterware files**, refer to ["Configuring Storage for Oracle Clusterware Files on Raw Devices"](#) on page 3-7

3: Configure storage for Oracle Database files and recovery files

- To use a file system for database or recovery file storage, refer to [Configuring Storage for Oracle Clusterware Files on a Supported Shared File System](#) on page 3-4, and ensure that in addition to the volumes you create for Oracle Clusterware files, you also create additional volumes with sizes sufficient to store database files.
- To use Automatic Storage Management for database or recovery file storage, refer to "[Configuring Database File Storage for ASM and Raw Devices](#)" on page 3-19.
- To use raw devices (partitions) for database file storage, refer to "[Configuring Database File Storage on Raw Devices](#)" on page 3-22.

Checking for Available Shared Storage with CVU

To check for all shared file systems available across all nodes on the cluster with GPFS, use the following command:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh comp ssa -n node_list
```

If you want to check the shared accessibility of a specific shared storage type to specific nodes in your cluster, then use the following command syntax:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh comp ssa -n node_list -s storageID_list
```

In the preceding syntax examples, the variable *mountpoint* is the mountpoint path of the installation media, the variable *node_list* is the list of nodes you want to check, separated by commas, and the variable *storageID_list* is the list of storage device IDs for the storage devices managed by the file system type that you want to check.

For example, if you want to check the shared accessibility from node1 and node2 of storage devices */dev/sdb* and */dev/sdc*, and your mountpoint is */dev/dvdrom/*, then enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh comp ssa -n node1,node2 -s /dev/sdb,/dev/sdc
```

If you do not specify specific storage device IDs in the command, then the command searches for all available storage devices connected to the nodes on the list

Configuring Storage for Oracle Clusterware Files on a Supported Shared File System

Oracle Universal Installer (OUI) does not suggest a default location for the Oracle Cluster Registry (OCR) or the Oracle Clusterware voting disk. If you choose to create these files on a file system, then review the following sections to complete storage requirements for Oracle Clusterware files:

- [Requirements for Using a File System for Oracle Clusterware Files](#)
- [Creating Required Directories for Oracle Clusterware Files on Shared File Systems](#)

Requirements for Using a File System for Oracle Clusterware Files

To use a file system for Oracle Clusterware files, the file system must comply with the following requirements

- To use a cluster file system on AIX you must use GPFS

- If you choose to place your Oracle Cluster Registry (OCR) files on a shared file system, then you should ensure one of the following is true:
 - Either ensure that the disks used for the file system are on a highly available storage device, (for example, a RAID device that implements file redundancy), or mount at least two file systems, and use the features of Oracle Database 10g Release 2 (10.2) to provide redundancy for the OCR.
- If you intend to use a shared file system to store database files, then you should ensure that you use at least two independent file systems, with the database files on one file system, and the recovery files on a different file system.
- The `oracle` user must have write permissions to create the files in the path that you specify.

Note: If you are upgrading from Oracle9i release 2, then you can continue to use the raw device or shared file that you used for the SRVM configuration repository instead of creating a new file for the OCR.

Use [Table 3–1](#) to determine the partition size for shared file systems:

Table 3–1 Shared file system Volume Size Requirements

File Types Stored	Number of Volumes	Volume Size
Oracle Clusterware files (OCR and voting disks) with external redundancy	1	At least 120 MB for each volume
Oracle Clusterware files (OCR and voting disks) with redundancy provided by Oracle	1	At least 120 MB for each volume
Redundant Oracle Clusterware files with redundancy provided by Oracle (mirrored OCR and two additional voting disks)	1	At least 140 MB (100 MB for the mirrored OCR, and 20 MB each for the additional voting disks)
Oracle Database files	1	At least 1.2 GB for each volume
Recovery files	1	At least 2 GB for each volume
Note: Recovery files must be on a different volume than database files		

In [Table 3–1](#), the total required volume size is cumulative. For example, to store all files on the shared file system, you should have at least 3.4 GB of storage available over a minimum of two volumes.

Creating Required Directories for Oracle Clusterware Files on Shared File Systems

Use the following instructions to create directories for Oracle Clusterware files. If you intend to use a file system to store Oracle Clusterware files, then you can also configure file systems for the Oracle Database and recovery files.

Note: For GPFS storage, you must complete this procedure only if you want to place the Oracle Clusterware files on a separate file system to the Oracle base directory.

To create directories for the Oracle Clusterware files on separate file systems to the Oracle base directory, follow these steps:

1. If necessary, configure the shared file systems that you want to use and mount them on each node.

Note: The mount point that you use for the file system must be identical on each node. Make sure that the file systems are configured to mount automatically when a node restarts.

2. Use the `df -k` command to determine the free disk space on each mounted file system.
3. From the display, identify the file systems that you want to use:

File Type	File System Requirements
Oracle Clusterware files	Choose a file system with at least 120 MB of free disk space
Database files	Choose either: <ul style="list-style-type: none"> ■ A single file system with at least 1.2 GB of free disk space ■ Two or more file systems with at least 1.2 GB of free disk space in total
Recovery files	Choose a file system with at least 2 GB of free disk space.

If you are using the same file system for more than one type of file, then add the disk space requirements for each type to determine the total disk space requirement.

4. Note the names of the mount point directories for the file systems that you identified.
5. If the user performing installation (typically, `oracle`) has permissions to create directories on the disks where you plan to install Oracle Clusterware and Oracle Database, then OUI creates the Oracle Clusterware file directory, and DBCA creates the Oracle Database file directory, and the Recovery file directory.

If the user performing the installation does not have write access, then you must create these directories manually using commands similar to the following to create the recommended subdirectories in each of the mount point directories and set the appropriate owner, group, and permissions on them:

- Oracle Clusterware file directory:

```
# mkdir /mount_point/oracrs
# chown oracle:oinstall /mount_point/oracrs
# chmod 775 /mount_point/oracrs
```
- Database file directory:

```
# mkdir /mount_point/oradata
# chown oracle:oinstall /mount_point/oradata
# chmod 775 /mount_point/oradata
```
- Recovery file directory (flash recovery area):

```
# mkdir /mount_point/flash_recovery_area
```



```
# chown oracle:oinstall /mount_point/flash_recovery_area
# chmod 775 /mount_point/flash_recovery_area
```

By making the Oracle user the owner of these directories, this permits them to be read by multiple Oracle homes, including those with different OSDBA groups.

When you have completed creating subdirectories in each of the mount point directories and set the appropriate owner, group, and permissions, you have completed the GPFS configuration.

Configuring Storage for Oracle Clusterware Files on Raw Devices

The following subsection describes how to configure Oracle Clusterware files on raw partitions.

- [Identifying Required Raw Partitions for Clusterware Files](#)
- [Configuring Raw Disk Devices for Oracle Clusterware Without HACMP or GPFS](#)
- [Configuring Raw Logical Volumes for Oracle Clusterware](#)
- [Creating a Volume Group for Oracle Clusterware](#)
- [Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group](#)
- [Importing the Volume Group on the Other Cluster Nodes](#)
- [Activating the Volume Group in Concurrent Mode on All Cluster Nodes](#)

Identifying Required Raw Partitions for Clusterware Files

Table 3–2 lists the number and size of the raw partitions that you must configure for Oracle Clusterware files.

Note: Because each file requires exclusive use of a complete disk device, Oracle recommends that, if possible, you use disk devices with sizes that closely match the size requirements of the files that they will store. You cannot use the disks that you choose for these files for any other purpose.

Table 3–2 Raw Partitions Required for Oracle Clusterware Files on AIX

Number	Size for Each Partition (MB)	Purpose
2 (or 1, if you have external redundancy support for this file)	100	Oracle Cluster Registry Note: You need to create these raw partitions only once on the cluster. If you create more than one database on the cluster, then they all share the same Oracle Cluster Registry (OCR). You should create two partitions: One for the OCR, and one for a mirrored OCR. If you are upgrading from Oracle9i release 2, then you can continue to use the raw device that you used for the SRVM configuration repository instead of creating this new raw device.

Table 3–2 (Cont.) Raw Partitions Required for Oracle Clusterware Files on AIX

Number	Size for Each Partition (MB)	Purpose
3 (or 1, if you have external redundancy support for this file)	20	Oracle Clusterware voting disks Note: You need to create these raw partitions only once on the cluster. If you create more than one database on the cluster, then they all share the same Oracle Clusterware voting disk. You should create three partitions: One for the voting disk, and two for additional voting disks.

Configuring Raw Disk Devices for Oracle Clusterware Without HACMP or GPFS

If you are installing RAC on an AIX cluster without HACMP or GPFS, then you must use shared raw disk devices for the Oracle Clusterware files. You can also use shared raw disk devices for database file storage, however, Oracle recommends that you use Automatic Storage Management to store database files in this situation. This section describes how to configure the shared raw disk devices for Oracle Clusterware files (Oracle Cluster Registry and Oracle Clusterware voting disk) and database files.

To configure shared raw disk devices for Oracle Clusterware files:

1. Identify or configure the required disk devices.

The disk devices must be shared on all of the cluster nodes.

2. As the `root` user, enter the following command on any node to identify the device names for the disk devices that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk device that is not configured in a volume group:

```
hdisk17          0009005fb9c23648          None
```

In this example, `hdisk17` is the device name of the disk and `0009005fb9c23648` is the physical volume ID (PVID).

3. If a disk device that you want to use does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

4. On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i "0009005fb9c23648"
```

The output from this command should be similar to the following:

```
hdisk18          0009005fb9c23648          None
```

In this example, the device name associated with the disk device (`hdisk18`) is different on this node.

5. If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices:

- OCR device:

```
# chown root:oinstall /dev/rhdiskn
```

```
# chmod 640 /dev/rhdiskn
```

- Other devices:

```
# chown oracle:dba /dev/rhdiskn
# chmod 660 /dev/rhdiskn
```

6. If the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. The previous table suggests alternative device file names for each file. For database files, replace *dbname* in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example `hdisk99`.

To create a new common device file for a disk device on all nodes, perform these steps on each node:

- a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system    24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system    24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file `/dev/rhdiskn` represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

- b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the character `c` to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_100m c 24 8192
```

- c. Enter commands similar to the following to change the owner, group, and permissions on the character raw device file for the disk:

- OCR:

```
# chown root:oinstall /dev/ora_ocr_raw_100m
# chmod 640 /dev/ora_ocr_raw_100m
```

- Oracle Clusterware voting disk:

```
# chown oracle:dba /dev/ora_vote_raw_20m
# chmod 660 /dev/ora_vote_raw_20m
```

- d. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root    system  24,8192 Dec 05 2001 /dev/hdiskn
crw-r----- 1 root    oinstall 24,8192 Dec 05 2001 /dev/ora_ocr_raw_100m
crw----- 1 root    system  24,8192 Dec 05 2001 /dev/rhdiskn
```

7. To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute listed in the following table to the value shown, depending on the disk type:

Disk Type	Attribute	Value
SSA, FASTT, or non-MPIO-capable disks	reserve_lock	no
ESS, EMC, HDS, CLARiiON, or MPIO-capable disks	reserve_policy	no_reserve

To determine whether the attribute has the correct value, enter a command similar to the following on all cluster nodes for each disk device that you want to use:

```
# /usr/sbin/lsattr -E -l hdiskn
```

If the required attribute is not set to the correct value on any node, then enter a command similar to one of the following on that node:

- SSA and FASTT devices

```
# /usr/sbin/chdev -l hdiskn -a reserve_lock=no
```

- ESS, EMC, HDS, CLARiiON, and MPIO-capable devices

```
# /usr/sbin/chdev -l hdiskn -a reserve_policy=no_reserve
```

8. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:

```
# /usr/sbin/chdev -l hdiskn -a pv=clear
```

When you are installing Oracle Clusterware, you must enter the paths to the appropriate device files when prompted for the path of the OCR and Oracle Clusterware voting disk, for example:

```
/dev/rhdisk10
```

Configuring Raw Logical Volumes for Oracle Clusterware

Note: To use raw logical volumes for Oracle Clusterware, HACMP must be installed and configured on all cluster nodes.

This section describes how to configure raw logical volumes for Oracle Clusterware and database file storage. The procedures in this section describe how to create a new volume group that contains the logical volumes required for both types of files.

Before you continue, review the following guidelines which contain important information about using volume groups with this release of RAC:

- You must use concurrent-capable volume groups for Oracle Clusterware.
- The Oracle Clusterware files require less than 200 MB of disk space. To make efficient use of the disk space in a volume group, Oracle recommends that you use the same volume group for the logical volumes for both the Oracle Clusterware files and the database files.
- If you are upgrading an existing Oracle9i release 2 RAC installation that uses raw logical volumes, then you can use the existing SRVM configuration repository logical volume for the OCR and create a new logical volume in the same volume group for the Oracle Clusterware voting disk. However, you must remove this volume group from the HACMP concurrent resource group that activates it before you install Oracle Clusterware.

See Also: The HACMP documentation for information about removing a volume group from a concurrent resource group.

Note: If you are upgrading a database, then you must also create a new logical volume for the SYSAUX tablespace. Refer to the ["Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group"](#) section on page 3-13 for more information about the requirements for the Oracle Clusterware voting disk and SYSAUX logical volumes.

- You must use a HACMP concurrent resource group to activate new or existing volume groups that contain only database files (not Oracle Clusterware files).

See Also: The HACMP documentation for information about adding a volume group to a new or existing concurrent resource group.

- All volume groups that you intend to use for Oracle Clusterware must be activated in concurrent mode before you start the installation.
- The procedures in this section describe how to create basic volumes groups and volumes. If you want to configure more complex volumes, (using mirroring, for example), then use this section in conjunction with the HACMP documentation.

Creating a Volume Group for Oracle Clusterware

To create a volume group for the Oracle Clusterware files:

1. If necessary, install the shared disks that you intend to use.
2. To ensure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdisk0 Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L      SSA Logical Disk Drive
```

- If a disk is not listed as available on any node, then enter the following command to configure the new disks:

```
# /usr/sbin/cfgmgr
```

- Enter the following command on any node to identify the device names and any associated volume group for each disk:

```
# /usr/sbin/lspv
```

The output from this command is similar to the following:

```
hdisk0      0000078752249812   rootvg
hdisk1      none                none
hdisk4      00034b6fd4ac1d71    ccvg1
```

For each disk, this command shows:

- The disk device name
- Either the 16 character physical volume identifier (PVID) if the disk has one, or none
- Either the volume group to which the disk belongs, or none

The disks that you want to use may have a PVID, but they must not belong to existing volume groups.

- If a disk that you want to use for the volume group does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

- To identify used device major numbers, enter the following command on each node of the cluster:

```
# ls -la /dev | more
```

This command displays information about all configured devices, similar to the following:

```
crw-rw----  1 root      system    45,  0 Jul 19 11:56 vg1
```

In this example, 45 is the major number of the vg1 volume group device.

- Identify an appropriate major number that is unused on all nodes in the cluster.
- To create a volume group, enter a command similar to the following, or use SMIT (smit mkvg):

```
# /usr/sbin/mkvg -y VGname -B -s PPSize -V majornum -n \
-C PhysicalVolumes
```

- The following table describes the options and variables used in this example. Refer to the mkvg man page for more information about these options.

Command Option	SMIT Field	Sample Value and Description
-y <i>VGname</i>	VOLUME GROUP name	oracle_vg1 Specify the name for the volume group. The name that you specify could be a generic name, as shown, or it could specify the name of the database that you intend to create.
-y <i>VGname</i>	VOLUME GROUP name	oracle_vg1 Specify the name for the volume group. The name that you specify could be a generic name, as shown, or for a database volume group, it could specify the name of the database that you intend to create.
-B	Create a big VG format Volume Group	Specify this option to create a big VG format volume group. Note: If you are using SMIT, then choose yes for this field.
-s <i>PPsize</i>	Physical partition SIZE in megabytes	32 Specify the size of the physical partitions for the database. The sample value shown enables you to include a disk up to 32 GB in size (32 MB * 1016).
-V <i>Majornum</i>	Volume Group MAJOR NUMBER	46 Specify the device major number for the volume group that you identified in Step 7.
-n	Activate volume group AUTOMATICALLY at system restart	Specify this option to prevent the volume group from being activated at system restart. Note: If you are using SMIT, then choose no for this field.
-C	Create VG Concurrent Capable	Specify this option to create a concurrent capable volume group. Note: If you are using SMIT, then choose yes for this field.
<i>PhysicalVolumes</i>	PHYSICAL VOLUME names	hdisk3 hdisk4 Specify the device names of the disks that you want to add to the volume group.

10. Enter a command similar to the following to vary on the volume group that you created:

```
# /usr/sbin/varyonvg VGname
```

Configuring Raw Logical Volumes in the New Oracle Clusterware Volume Group

To create the required raw logical volumes in the new Oracle Clusterware volume group:

1. Identify the logical volumes that you must create.
2. If you prefer, you can also use the command `smit mklv` to create raw logical volumes.

The following example shows the command used to create a logical volume for the `ocr` volume group in the `SYSAUX` tablespace with a physical partition size of 114 MB ($800/7 = 114$):

```
# /usr/sbin/mklv -y test_sysaux_raw_800m -T O -w n -s n -r n ocr 7
```

3. Change the owner, group, and permissions on the character device files associated with the logical volumes that you created, as follows:

Note: The device file associated with the Oracle Cluster Registry must be owned by `root`. All other device files must be owned by the Oracle software owner user (`oracle`).

```
# chown oracle:dba /dev/rora_vote_raw_20m
# chmod 660 /dev/rora_vote_raw_20m
# chown root:oinstall /dev/rora_ocr_raw_100m
# chmod 640 /dev/rora_ocr_raw_100m
```

Importing the Volume Group on the Other Cluster Nodes

To make the volume group available to all nodes in the cluster, you must import it on each node, as follows:

1. Because the physical volume names may be different on the other nodes, enter the following command to determine the PVID of the physical volumes used by the volume group:

```
# /usr/sbin/lspv
```

2. Note the PVIDs of the physical devices used by the volume group.
3. To vary off the volume group that you want to use, enter a command similar to the following on the node where you created it:

```
# /usr/sbin/varyoffvg VGname
```

4. On each cluster node, complete the following steps:
 - a. Enter the following command to determine the physical volume names associated with the PVIDs you noted previously:

```
# /usr/sbin/lspv
```

- b. On each node of the cluster, enter commands similar to the following to import the volume group definitions:

```
# /usr/sbin/importvg -y VGname -V MajorNumber PhysicalVolume
```

In this example, *MajorNumber* is the device major number for the volume group and *PhysicalVolume* is the name of one of the physical volumes in the volume group.

For example, to import the definition of the `oracle_vg1` volume group with device major number 45 on the `hdisk3` and `hdisk4` physical volumes, enter the following command:


```
# /usr/sbin/importvg -y oracle_vg1 -V 45 hdisk3
```

- c. Change the owner, group, and permissions on the character device files associated with the logical volumes you created, as follows:

```
# chown oracle:dba /dev/rora_vote_raw_20m
# chmod 660 /dev/rora_vote_raw_20m
# chown root:oinstall /dev/rora_ocr_raw_100m
# chmod 640 /dev/rora_ocr_raw_100m
```

- d. Enter the following command to ensure that the volume group will not be activated by the operating system when the node starts:

```
# /usr/sbin/chvg -a n VGname
```

Activating the Volume Group in Concurrent Mode on All Cluster Nodes

To activate the volume group in concurrent mode on all cluster nodes, enter the following command on each node:

```
# /usr/sbin/varyonvg -c VGname
```

Choosing a Storage Option for Oracle Database Files

Database files consist of the files that make up the database, and the recovery area files. There are four options for storing database files:

- General Parallel File System (GPFS)
- Automatic Storage Management (ASM)
- Raw partitions (Database files only--not for the recovery area)

During configuration of Oracle Clusterware, if you selected GPFS and the volumes that you created are large enough to hold the database files and recovery files, then you have completed required pre-installation steps. You can proceed to [Chapter 4, "Installing Oracle Clusterware"](#) on page 4-1.

If you want to place your database files on ASM, then proceed to ["Configuring Disks for Automatic Storage Management"](#) on page 3-15.

If you want to place your database files on raw devices, and manually provide storage management for your database and recovery files, then proceed to ["Configuring Database File Storage on Raw Devices"](#) on page 3-22.

Note: Databases can consist of a mixture of ASM files and non-ASM files. Refer to *Oracle Database Administrator's Guide* for additional information about ASM.

Configuring Disks for Automatic Storage Management

This section describes how to configure disks for use with ASM. Before you configure the disks, you must determine the number of disks and the amount of free disk space that you require. The following sections describe how to identify the requirements and configure the disks on each platform:

- [Identifying Storage Requirements for ASM](#)
- [Using an Existing ASM Disk Group](#)

- [Configuring Database File Storage for ASM and Raw Devices](#)

Note: Although this section refers to disks, you can also use zero-padded files on a certified NAS storage device in an ASM disk group. Refer to the *Oracle Database Installation Guide for UNIX Systems* for information about creating and configuring NAS-based files for use in an ASM disk group.

Identifying Storage Requirements for ASM

To identify the storage requirements for using ASM, you must determine how many devices and the amount of free disk space that you require. To complete this task, follow these steps:

1. Determine whether you want to use ASM for Oracle database files, recovery files, or both.

Note: You do not have to use the same storage mechanism for database files and recovery files. You can use the file system for one file type and ASM for the other.

For RAC installations, if you choose to enable automated backups and you do not have a shared file system available, you must choose ASM for recovery file storage.

If you enable automated backups during the installation, you can choose ASM as the storage mechanism for recovery files by specifying an ASM disk group for the flash recovery area. Depending on how you choose to create a database during the installation, you have the following options:

- If you select an installation method that runs DBCA in interactive mode, by choosing the Advanced database configuration option for example, you can decide whether you want to use the same ASM disk group for database files and recovery files, or you can choose to use different disk groups for each file type.

The same choice is available to you if you use DBCA after the installation to create a database.

- If you select an installation method that runs DBCA in non-interactive mode, you must use the same ASM disk group for database files and recovery files.

2. Choose the ASM redundancy level that you want to use for the ASM disk group.

The redundancy level that you choose for the ASM disk group determines how ASM mirrors files in the disk group and determines the number of disks and amount of disk space that you require, as follows:

- External redundancy

An external redundancy disk group requires a minimum of one disk device. The effective disk space in an external redundancy disk group is the sum of the disk space in all of its devices.

Because ASM does not mirror data in an external redundancy disk group, Oracle recommends that you use only RAID or similar devices that provide their own data protection mechanisms as disk devices in this type of disk group.

- Normal redundancy

In a normal redundancy disk group, ASM uses two-way mirroring by default, to increase performance and reliability. A normal redundancy disk group requires a minimum of two disk devices (or two failure groups). The effective disk space in a normal redundancy disk group is *half* the sum of the disk space in all of its devices.

For most installations, Oracle recommends that you use normal redundancy disk groups.

- High redundancy

In a high redundancy disk group, ASM uses three-way mirroring to increase performance and provide the highest level of reliability. A high redundancy disk group requires a minimum of three disk devices (or three failure groups). The effective disk space in a high redundancy disk group is *one-third* the sum of the disk space in all of its devices.

While high redundancy disk groups do provide a high level of data protection, you must consider the higher cost of additional storage devices before deciding to use this redundancy level.

3. Determine the total amount of disk space that you require for the database files and recovery files.

Use the following table to determine the minimum number of disks and the minimum disk space requirements for the installation:

Redundancy Level	Minimum Number of Disks	Database Files	Recovery Files	Both File Types
External	1	1.15 GB	2.3 GB	3.45 GB
Normal	2	2.3 GB	4.6 GB	6.9 GB
High	3	3.45 GB	6.9 GB	10.35 GB

For RAC installations, you must also add additional disk space for the ASM metadata. You can use the following formula to calculate the additional disk space requirements (in MB):

$$15 + (2 * \text{number_of_disks}) + (126 * \text{number_of_ASM_instances})$$

For example, for a four-node RAC installation, using three disks in a high redundancy disk group, you require an additional 525 MB of disk space:

$$15 + (2 * 3) + (126 * 4) = 525$$

If an ASM instance is already running on the system, you can use an existing disk group to meet these storage requirements. If necessary, you can add disks to an existing disk group during the installation.

The following section describes how to identify existing disk groups and determine the free disk space that they contain.

4. Optionally identify failure groups for the ASM disk group devices.

Note: You need to complete this step only if you intend to use an installation method that runs DBCA in interactive mode, for example, if you intend to choose the Custom installation type or the Advanced database configuration option. Other installation types do not enable you to specify failure groups.

If you intend to use a normal or high redundancy disk group, you can further protect your database against hardware failure by associating a set of disk devices in a custom failure group. By default, each device comprises its own failure group. However, if two disk devices in a normal redundancy disk group are attached to the same SCSI controller, the disk group becomes unavailable if the controller fails. The controller in this example is a single point of failure.

To protect against failures of this type, you could use two SCSI controllers, each with two disks, and define a failure group for the disks attached to each controller. This configuration would enable the disk group to tolerate the failure of one SCSI controller.

Note: If you define custom failure groups, you must specify a minimum of two failure groups for normal redundancy disk groups and three failure groups for high redundancy disk groups.

5. If you are sure that a suitable disk group does not exist on the system, install or identify appropriate disk devices to add to a new disk group. Use the following guidelines when identifying appropriate disk devices:
 - All of the devices in an ASM disk group should be the same size and have the same performance characteristics.
 - Do not specify more than one partition on a single physical disk as a disk group device. ASM expects each disk group device to be on a separate physical disk.
 - Although you can specify a logical volume as a device in an ASM disk group, Oracle does not recommend their use. Logical volume managers can hide the physical disk architecture, preventing ASM from optimizing I/O across the physical devices.

For information about completing this task, refer to the "[Configuring Database File Storage for ASM and Raw Devices](#)" section on page 3-19.

Using an Existing ASM Disk Group

If you want to store either database or recovery files in an existing ASM disk group, you have the following choices, depending on the installation method that you select:

- If you select an installation method that runs DBCA in interactive mode, by choosing the Advanced database configuration option for example, you can decide whether you want to create a new disk group or use an existing one.

The same choice is available to you if you use DBCA after the installation to create a database.

- If you select an installation method that runs DBCA in non-interactive mode, you must choose an existing disk group for the new database; you cannot create a new

disk group. However, you can add disk devices to an existing disk group if it has insufficient free space for your requirements.

Note: The ASM instance that manages the existing disk group can be running in a different Oracle home directory.

To determine whether an existing ASM disk group exists, or to determine whether there is sufficient disk space in a disk group, you can use Oracle Enterprise Manager Grid Control or Database Control. Alternatively, you can use the following procedure:

1. View the contents of the `oratab` file to determine whether an ASM instance is configured on the system:

```
# more /etc/oratab
```

If an ASM instance is configured on the system, the `oratab` file should contain a line similar to the following:

```
+ASM:oracle_home_path:N
```

In this example, `+ASM` is the system identifier (SID) of the ASM instance and `oracle_home_path` is the Oracle home directory where it is installed. By convention, the SID for an ASM instance begins with a plus sign.

2. Set the `ORACLE_SID` and `ORACLE_HOME` environment variables to specify the appropriate values for the ASM instance that you want to use.
3. Connect to the ASM instance as the `SYS` user with `SYSDBA` privilege and start the instance if necessary:

```
# $ORACLE_HOME/bin/sqlplus "SYS/SYS_password as SYSDBA"
SQL> STARTUP
```

4. Enter the following command to view the existing disk groups, their redundancy level, and the amount of free disk space in each one:

```
SQL> SELECT NAME,TYPE,TOTAL_MB,FREE_MB FROM V$ASM_DISKGROUP;
```

5. From the output, identify a disk group with the appropriate redundancy level and note the free space that it contains.
6. If necessary, install or identify the additional disk devices required to meet the storage requirements listed in the previous section.

Note: If you are adding devices to an existing disk group, Oracle recommends that you use devices that have the same size and performance characteristics as the existing devices in that disk group.

Configuring Database File Storage for ASM and Raw Devices

To configure disks for use with ASM on AIX, follow these steps:

1. On AIX-based systems, you must apply Program Technical Fix (PTF) U496549 or higher to your system before you use ASM.
2. If necessary, install the shared disks that you intend to use for the ASM disk group and restart the system.

3. To make sure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdisk0 Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L      SSA Logical Disk Drive
```

4. If a disk is not listed as available on any node, enter the following command to configure the new disks:

```
# /usr/sbin/cfgmgr
```

5. Enter the following command on any node to identify the device names for the physical disks that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk that is not configured in a volume group:

```
hdisk2      0000078752249812  None
```

In this example, `hdisk2` is the device name of the disk and `0000078752249812` is the physical volume ID (PVID). The disks that you want to use might have a PVID, but they must not belong to a volume group.

6. If a disk that you want to use for the disk group does not have a PVID, enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

7. On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i 0000078752249812
```

The output from this command should be similar to the following:

```
hdisk18      0000078752249812      None
```

Depending on how each node is configured, the device names may differ between nodes.

8. If the device names are the same on all nodes, enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices:

- OCR device:

```
# chown root:oinstall /dev/rhdiskn
# chmod 640 /dev/rhdiskn
```

- Other devices:

```
# chown oracle:dba /dev/rhdiskn
# chmod 660 /dev/rhdiskn
```

9. If the device name associated with the PVID for a disk that you want to use is different on any node, you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. The previous table suggests alternative device file names for each file. For database files, replace *dbname* in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example `hdisk99`.

To create a new common device file for a disk device on all nodes, follow these steps on each node:

- a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system    24,8192 Dec 05 2001  /dev/hdiskn
crw----- 1 root system    24,8192 Dec 05 2001  /dev/rhdiskn
```

In this example, the device file `/dev/rhdiskn` represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

- b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the character `c` to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_100m c 24 8192
```

- c. Enter commands similar to the following to change the owner, group, and permissions on the character raw device file for the disk:

– OCR:

```
# chown root:oinstall /dev/ora_ocr_raw_100m
# chmod 640 /dev/ora_ocr_raw_100m
```

– Voting disk or database files:

```
# chown oracle:dba /dev/ora_vote_raw_20m
# chmod 660 /dev/ora_vote_raw_20m
```

- d. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root  system    24,8192 Dec 05 2001  /dev/hdiskn
crw-r----- 1 root  oinstall 24,8192 Dec 05 2001  /dev/ora_ocr_raw_100m
crw----- 1 root  system    24,8192 Dec 05 2001  /dev/rhdiskn
```

10. To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute listed in the following table to the value shown, depending on the disk type:

Disk Type	Attribute	Value
SSA or FAStT disks	reserve_lock	no
ESS, EMC, HDS, CLARiiON, or MPIIO-capable disks	reserve_policy	no_reserve

To determine whether the attribute has the correct value, enter a command similar to the following on all cluster nodes for each disk device that you want to use:

```
# /usr/sbin/lsattr -E -l hdiskn
```

If the required attribute is not set to the correct value on any node, enter a command similar to one of the following on that node:

- SSA and FAStT devices:

```
# /usr/sbin/chdev -l hdiskn -a reserve_lock=no
```

- ESS, EMC, HDS, CLARiiON, and MPIIO-capable devices:

```
# /usr/sbin/chdev -l hdiskn -a reserve_policy=no_reserve
```

11. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:

```
# /usr/sbin/chdev -l hdiskn -a pv=clear
```

12. Enter commands similar to the following on every node to change the owner, group, and permissions on the character raw device file for each disk that you want to add to the disk group:

```
# chown oracle:dba /dev/rhdiskn
# chmod 660 /dev/rhdiskn
```

Note: If you are using a multi-pathing disk driver with ASM, make sure that you set the permissions only on the correct logical device name for the disk.

The device name associated with a disk might be different on other nodes. Make sure that you specify the correct device name on each node.

When you are installing Oracle Clusterware Services, you must enter the paths to the appropriate device files when prompted for the path of the OCR and voting disk, for example:

```
/dev/rhdisk10
```

When you have completed creating and configuring ASM with raw partitions, proceed to [Chapter 4, "Installing Oracle Clusterware"](#) on page 4-1

Configuring Database File Storage on Raw Devices

The following subsections describe how to configure raw partitions for database files.

- Identifying Required Raw Partitions for Database Files
- Configuring Raw Disk Devices for Database File Storage Without HACMP or GPFS
- Configuring Raw Logical Volumes for Database File Storage
- Creating a Volume Group for Database Files
- Creating Database File Raw Logical Volumes in the New Volume Group
- Importing the Database File Volume Group on the Other Cluster Nodes
- Activating the Database File Volume Group in Concurrent Mode on All Cluster Nodes

Identifying Required Raw Partitions for Database Files

Table 3–3 lists the number and size of the raw partitions that you must configure for database files.

Note: Because each file requires exclusive use of a complete disk device, Oracle recommends that, if possible, you use disk devices with sizes that closely match the size requirements of the files that they will store. You cannot use the disks that you choose for these files for any other purpose.

Table 3–3 Raw Disk Devices Required for Database Files on AIX

Number	Size (MB)	Purpose and Sample Alternative Device File Name
1	500	SYSTEM tablespace: <i>dbname_system_raw_500m</i>
1	300 + (Number of instances * 250)	SYSAUX tablespace: <i>dbname_sysaux_raw_800m</i>
Number of instances	500	UNDOTBS n tablespace (One tablespace for each instance, where n is the number of the instance): <i>dbname_undotbsn_raw_500m</i>
1	250	TEMP tablespace: <i>dbname_temp_raw_250m</i>
1	160	EXAMPLE tablespace: <i>dbname_example_raw_160m</i>
1	120	USERS tablespace: <i>dbname_users_raw_120m</i>
2 * number of instances	120	Two online redo log files for each instance (where n is the number of the instance and m is the log number, 1 or 2): <i>dbname_redonm_raw_120m</i>
2	110	First and second control files: <i>dbname_control{1 2}_raw_110m</i>
1	5	Server parameter file (SPFILE): <i>dbname_spfile_raw_5m</i>

Table 3–3 (Cont.) Raw Disk Devices Required for Database Files on AIX

Number	Size (MB)	Purpose and Sample Alternative Device File Name
1	5	Password file: <i>dbname_pwdfile_raw_5m</i>

Note: If you prefer to use manual undo management, instead of automatic undo management, then, instead of the UNDOTBS*n* raw devices, you must create a single rollback segment tablespace (RBS) raw device that is at least 500 MB in size.

Configuring Raw Disk Devices for Database File Storage Without HACMP or GPFS

If you are installing RAC on an AIX cluster without HACMP or GPFS, you can use shared raw disk devices for database file storage. However, Oracle recommends that you use Automatic Storage Management to store database files in this situation. This section describes how to configure the shared raw disk devices for database files.

To configure shared raw disk devices for Oracle Clusterware files, database files, or both:

1. If you intend to use raw disk devices for database file storage, then specify a name for the database that you want to create.

The name that you specify must start with a letter and have no more than four characters. For example: `orcl`.

2. Identify or configure the required disk devices.

The disk devices must be shared on all of the cluster nodes.

3. As the `root` user, enter the following command on any node to identify the device names for the disk devices that you want to use:

```
# /usr/sbin/lspv | grep -i none
```

This command displays information similar to the following for each disk device that is not configured in a volume group:

```
hdisk17          0009005fb9c23648          None
```

In this example, `hdisk17` is the device name of the disk and `0009005fb9c23648` is the physical volume ID (PVID).

4. If a disk device that you want to use does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

5. On each of the other nodes, enter a command similar to the following to identify the device name associated with each PVID on that node:

```
# /usr/sbin/lspv | grep -i "0009005fb9c23648"
```

The output from this command should be similar to the following:

```
hdisk18          0009005fb9c23648          None
```

In this example, the device name associated with the disk device (`hdisk18`) is different on this node.

6. If the device names are the same on all nodes, then enter commands similar to the following on all nodes to change the owner, group, and permissions on the character raw device files for the disk devices you want to use for database files:

```
# chown oracle:dba /dev/rhdiskn
# chmod 660 /dev/rhdiskn
```

7. If the device name associated with the PVID for a disk that you want to use is different on any node, then you must create a new device file for the disk on each of the nodes using a common unused name.

For the new device files, choose an alternative device file name that identifies the purpose of the disk device. The previous table suggests alternative device file names for each file. For database files, replace *dbname* in the alternative device file name with the name that you chose for the database in step 1.

Note: Alternatively, you could choose a name that contains a number that will never be used on any of the nodes, for example `hdisk99`.

To create a new common device file for a disk device on all nodes, perform these steps on each node:

- a. Enter the following command to determine the device major and minor numbers that identify the disk device, where *n* is the disk number for the disk device on this node:

```
# ls -alF /dev/*hdiskn
```

The output from this command is similar to the following:

```
brw----- 1 root system    24,8192 Dec 05 2001 /dev/hdiskn
crw----- 1 root system    24,8192 Dec 05 2001 /dev/rhdiskn
```

In this example, the device file `/dev/rhdiskn` represents the character raw device, 24 is the device major number, and 8192 is the device minor number.

- b. Enter a command similar to the following to create the new device file, specifying the new device file name and the device major and minor numbers that you identified in the previous step:

Note: In the following example, you must specify the character `c` to create a character raw device file.

```
# mknod /dev/ora_ocr_raw_100m c 24 8192
```

- c. Enter a command similar to the following to verify that you have created the new device file successfully:

```
# ls -alF /dev | grep "24,8192"
```

The output should be similar to the following:

```
brw----- 1 root    system    24,8192 Dec 05 2001 /dev/hdiskn
crw-r----- 1 root    oinstall 24,8192 Dec 05 2001 /dev/ora_ocr_raw_100m
crw----- 1 root    system    24,8192 Dec 05 2001 /dev/rhdiskn
```

8. To enable simultaneous access to a disk device from multiple nodes, you must set the appropriate Object Data Manager (ODM) attribute listed in the following table to the value shown, depending on the disk type:

Disk Type	Attribute	Value
SSA, FASTT, or non-MPIO-capable disks	reserve_lock	no
ESS, EMC, HDS, CLARiiON, or MPIO-capable disks	reserve_policy	no_reserve

To determine whether the attribute has the correct value, enter a command similar to the following on all cluster nodes for each disk device that you want to use:

```
# /usr/sbin/lsattr -E -l hdiskn
```

If the required attribute is not set to the correct value on any node, then enter a command similar to one of the following on that node:

- SSA and FASTT devices

```
# /usr/sbin/chdev -l hdiskn -a reserve_lock=no
```

- ESS, EMC, HDS, CLARiiON, and MPIO-capable devices

```
# /usr/sbin/chdev -l hdiskn -a reserve_policy=no_reserve
```

9. Enter commands similar to the following on any node to clear the PVID from each disk device that you want to use:

```
# /usr/sbin/chdev -l hdiskn -a pv=clear
```

10. If you are using raw disk devices for database files, then follow these steps to create the Database Configuration Assistant raw device mapping file:

Note: You must complete this procedure only if you are using raw devices for database files. The Database Configuration Assistant raw device mapping file enables Database Configuration Assistant to identify the appropriate raw disk device for each database file. You do not specify the raw devices for the Oracle Clusterware files in the Database Configuration Assistant raw device mapping file.

- a. Set the ORACLE_BASE environment variable to specify the Oracle base directory that you identified or created previously:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_BASE=/u01/app/oracle ; export ORACLE_BASE
```

- C shell:

```
% setenv ORACLE_BASE /u01/app/oracle
```

- b. Create a database file subdirectory under the Oracle base directory and set the appropriate owner, group, and permissions on it:

```
# mkdir -p $ORACLE_BASE/oradata/dbname
# chown -R oracle:oinstall $ORACLE_BASE/oradata
# chmod -R 775 $ORACLE_BASE/oradata
```

In this example, *dbname* is the name of the database that you chose previously.

- c. Change directory to the `$ORACLE_BASE/oradata/dbname` directory.
- d. Using any text editor, create a text file similar to the following that identifies the disk device file name associated with each database file.

Oracle recommends that you use a file name similar to `dbname_raw.conf` for this file.

Note: The following example shows a sample mapping file for a two-instance RAC cluster. Some of the devices use alternative disk device file names. Ensure that the device file name that you specify identifies the same disk device on all nodes.

```
system=/dev/rhdisk11
sysaux=/dev/rhdisk12
example=/dev/rhdisk13
users=/dev/rhdisk14
temp=/dev/rhdisk15
undotbs1=/dev/rhdisk16
undotbs2=/dev/rhdisk17
redo1_1=/dev/rhdisk18
redo1_2=/dev/rhdisk19
redo2_1=/dev/rhdisk20
redo2_2=/dev/rhdisk22
control1=/dev/rhdisk23
control2=/dev/rhdisk24
spfile=/dev/dbname_spfile_raw_5m
pwdfile=/dev/dbname_pwdfile_raw_5m
```

In this example, *dbname* is the name of the database.

Use the following guidelines when creating or editing this file:

- Each line in the file must have the following format:

```
database_object_identifier=device_file_name
```

The alternative device file names suggested in the previous table include the database object identifier that you must use in this mapping file. For example, in the following alternative disk device name, `redo1_1` is the database object identifier:

```
/dev/rac_redo1_1_raw_120m
```

- For a RAC database, the file must specify one automatic undo tablespace datafile (`undotbsn`) and two redo log files (`redon_1`, `redon_2`) for each instance.
 - Specify at least two control files (`control1`, `control2`).
 - To use manual instead of automatic undo management, specify a single RBS tablespace datafile (`rbs`) instead of the automatic undo management tablespace data files.
- e. Save the file and note the file name that you specified.

- f. When you are configuring the `oracle` user's environment later in this chapter, set the `DBCA_RAW_CONFIG` environment variable to specify the full path to this file.
- 11. When you are installing Oracle Clusterware, you must enter the paths to the appropriate device files when prompted for the path of the OCR and Oracle Clusterware voting disk, for example:

```
/dev/rhdisk10
```

Configuring Raw Logical Volumes for Database File Storage

Note: To use raw logical volumes for database file storage, HACMP must be installed and configured on all cluster nodes.

This section describes how to configure raw logical volumes for database file storage. The procedures in this section describe how to create a new volume group that contains the logical volumes required for both types of files.

Before you continue, review the following guidelines which contain important information about using volume groups with this release of RAC:

- You must use concurrent-capable volume groups for database files.
- Oracle Clusterware files require less than 200 MB of disk space. To make efficient use of the disk space in a volume group, Oracle recommends that you use the same volume group for the logical volumes for both the Oracle Clusterware files and the database files.
- If you are upgrading a database, then you must also create a new logical volume for the SYSAUX tablespace. Refer to the "[Configuring Raw Logical Volumes for Database File Storage](#)" section on page 3-23 for more information about the requirements for the SYSAUX logical volumes.

See Also: The HACMP documentation for information about removing a volume group from a concurrent resource group.

- You must use a HACMP concurrent resource group to activate new or existing volume groups that contain only database files (not Oracle Clusterware files).

See Also: The HACMP documentation for information about adding a volume group to a new or existing concurrent resource group.

- All volume groups that you intend to use for database files must be activated in concurrent mode before you start the installation.
- The procedures in this section describe how to create basic volumes groups and volumes. If you want to configure more complex volumes (for example, using mirroring), then use this section in conjunction with the HACMP documentation.

Creating a Volume Group for Database Files

To create a volume group for the Oracle Database files:

1. If necessary, install the shared disks that you intend to use.

2. To ensure that the disks are available, enter the following command on every node:

```
# /usr/sbin/lsdev -Cc disk
```

The output from this command is similar to the following:

```
hdisk0 Available 1A-09-00-8,0 16 Bit LVD SCSI Disk Drive
hdisk1 Available 1A-09-00-9,0 16 Bit LVD SCSI Disk Drive
hdisk2 Available 17-08-L      SSA Logical Disk Drive
```

3. If a disk is not listed as available on any node, then enter the following command to configure the new disks:

```
# /usr/sbin/cfgmgr
```

4. Enter the following command on any node to identify the device names and any associated volume group for each disk:

```
# /usr/sbin/lspv
```

The output from this command is similar to the following:

```
hdisk0      0000078752249812  rootvg
hdisk1      none                none
hdisk4      00034b6fd4ac1d71  ccvg1
```

For each disk, this command shows:

- The disk device name
- Either the 16 character physical volume identifier (PVID) if the disk has one, or none
- Either the volume group to which the disk belongs, or none

The disks that you want to use may have a PVID, but they must not belong to existing volume groups.

5. If a disk that you want to use for the volume group does not have a PVID, then enter a command similar to the following to assign one to it:

```
# /usr/sbin/chdev -l hdiskn -a pv=yes
```

6. To identify used device major numbers, enter the following command on each node of the cluster:

```
# ls -la /dev | more
```

This command displays information about all configured devices, similar to the following:

```
crw-rw---- 1 root system 45, 0 Jul 19 11:56 vg1
```

In this example, 45 is the major number of the vg1 volume group device.

7. Identify an appropriate major number that is unused on all nodes in the cluster.
8. To create a volume group, enter a command similar to the following, or use SMIT (`smit mkvg`):

```
# /usr/sbin/mkvg -y VGname -B -s PPSize -V majornum -n \
-C PhysicalVolumes
```

9. The following table describes the options and variables used in this example. Refer to the `mkvg` man page for more information about these options.

Command Option	SMIT Field	Sample Value and Description
<code>-y VGname</code>	VOLUME GROUP name	oracle_vg1 Specify the name for the volume group. The name that you specify could be a generic name, as shown, or it could specify the name of the database that you intend to create.
<code>-y VGname</code>	VOLUME GROUP name	oracle_vg1 Specify the name for the volume group. The name that you specify could be a generic name, as shown, or for a database volume group, it could specify the name of the database that you intend to create.
<code>-B</code>	Create a big VG format Volume Group	Specify this option to create a big VG format volume group. Note: If you are using SMIT, then choose yes for this field.
<code>-s PPsize</code>	Physical partition SIZE in megabytes	32 Specify the size of the physical partitions for the database. The sample value shown enables you to include a disk up to 32 GB in size (32 MB * 1016).
<code>-V Majornum</code>	Volume Group MAJOR NUMBER	46 Specify the device major number for the volume group that you identified in Step 7.

Command Option	SMIT Field	Sample Value and Description
-n	Activate volume group AUTOMATICALLY at system restart	Specify this option to prevent the volume group from being activated at system restart. Note: If you are using SMIT, then choose no for this field.
-C	Create VG Concurrent Capable	Specify this option to create a concurrent capable volume group. Note: If you are using SMIT, then choose yes for this field.
<i>PhysicalVolumes</i>	PHYSICAL VOLUME names	hdisk3 hdisk4 Specify the device names of the disks that you want to add to the volume group.

10. Enter a command similar to the following to vary on the volume group that you created:

```
# /usr/sbin/varyonvg VGname
```

Creating Database File Raw Logical Volumes in the New Volume Group

To create the required raw logical volumes in the new volume group:

1. Choose a name for the database that you want to create.

The name that you choose must start with a letter and have no more than four characters, for example, `orcl`.

2. Identify the logical volumes that you must create.

[Table 3–4](#) lists the number and size of the logical volumes that you must create for database files.

Table 3–4 Raw Logical Volumes Required for Database Files

Number	Size (MB)	Purpose and Sample Logical Volume Name
1	500	SYSTEM tablespace: <i>dbname_system_raw_500m</i>
1	500	SYSAUX tablespace: <i>dbname_sysaux_raw_500m</i>
1	300 + (Number of instances * 250)	SYSAUX tablespace: <i>dbname_sysaux_raw_800m</i>
1	500	UNDOTBS1 tablespace: <i>dbname_undotbs1_raw_500m</i>
Number of instances	500	UNDOTBS n tablespace (One tablespace for each instance, where n is the number of the instance): <i>dbname_undotbsn_raw_500m</i>
1	250	TEMP tablespace: <i>dbname_temp_raw_250m</i>

Table 3–4 (Cont.) Raw Logical Volumes Required for Database Files

Number	Size (MB)	Purpose and Sample Logical Volume Name
1	160	EXAMPLE tablespace: <i>dbname_example_raw_160m</i>
1	120	USERS tablespace: <i>dbname_users_raw_120m</i>
2	120	Two online redo log files (where <i>m</i> is the log number, 1 or 2): <i>dbname_redo1_m_raw_120m</i>
2 * number of instances	120	Two online redo log files for each instance (where <i>n</i> is the number of the instance and <i>m</i> is the log number, 1 or 2): <i>dbname_redon_m_raw_120m</i>
2	110	First and second control files: <i>dbname_control{1 2}_raw_110m</i>
1	5	Server parameter file (SPFILE): <i>dbname_spfile_raw_5m</i>
1	5	Password file: <i>dbname_pwdfile_raw_5m</i>

3. To create each required logical volume for data files, Oracle recommends that you use a command similar to the following to create logical volumes with a zero offset:

```
# /usr/sbin/mkLV -y LVname -T 0 -w n -s n -r n VGname NumPPs
```

In this example:

- *LVname* is the name of the logical volume that you want to create
- The `-T 0` option specifies that the device subtype should be *z*, which causes Oracle to use a zero offset when accessing this raw logical volume
- *VGname* is the name of the volume group where you want to create the logical volume
- *NumPPs* is the number of physical partitions to use

To determine the value to use for *NumPPs*, divide the required size of the logical volume by the size of the physical partition and round the value up to an integer. For example, if the size of the physical partition is 32 MB and you want to create a 500 MB logical volume, then you should specify 16 for the *NumPPs* ($500/32 = 15.625$).

Using a zero offset improves database performance and fixes the issues described in Oracle bug 2620053.

Note: On raw logical volumes, if you create tablespaces in datafiles that are not created in this way, a message is recorded in the alert.log file.

If you prefer, you can also use the command `smit mkLV` to create raw logical volumes.

The following example shows the command used to create a logical volume for the SYSAUX tablespace of the `test` database in the `oracle_vg1` volume group with a physical partition size of 32 MB ($800/32 = 25$):

```
# /usr/sbin/mklnv -y test_sysaux_raw_800m -T 0 -w n -s n -r n oracle_vg1 25
```

4. Change the owner, group, and permissions on the character device files associated with the logical volumes that you created, as follows:

Note: The device file associated with the Oracle Cluster Registry must be owned by `root`. All other device files must be owned by the Oracle software owner user (`oracle`).

```
# chown oracle:dba /dev/rdbname*
# chmod 660 /dev/rdbname*
```

Importing the Database File Volume Group on the Other Cluster Nodes

To make the database file volume group available to all nodes in the cluster, you must import it on each node, as follows:

1. Because the physical volume names may be different on the other nodes, enter the following command to determine the PVID of the physical volumes used by the volume group:

```
# /usr/sbin/lspv
```

2. Note the PVIDs of the physical devices used by the volume group.
3. To vary off the volume group that you want to use, enter a command similar to the following on the node where you created it:

```
# /usr/sbin/varyoffvg VGname
```

4. On each cluster node, complete the following steps:
 - a. Enter the following command to determine the physical volume names associated with the PVIDs you noted previously:

```
# /usr/sbin/lspv
```

- b. On each node of the cluster, enter commands similar to the following to import the volume group definitions:

```
# /usr/sbin/importvg -y VGname -V MajorNumber PhysicalVolume
```

In this example, *MajorNumber* is the device major number for the volume group and *PhysicalVolume* is the name of one of the physical volumes in the volume group.

For example, to import the definition of the `oracle_vg1` volume group with device major number 45 on the `hdisk3` and `hdisk4` physical volumes, enter the following command:

```
# /usr/sbin/importvg -y oracle_vg1 -V 45 hdisk3
```

- c. Change the owner, group, and permissions on the character device files associated with the logical volumes you created, as follows:

```
# chown oracle:dba /dev/rdbname*
```

```
# chmod 660 /dev/rdbname*
```

- d. Enter the following command to ensure that the volume group will not be activated by the operating system when the node starts:

```
# /usr/sbin/chvg -a n VGname
```

Activating the Database File Volume Group in Concurrent Mode on All Cluster Nodes

To activate the volume group in concurrent mode on all cluster nodes, enter the following command on each node:

```
# /usr/sbin/varyonvg -c VGname
```

Creating the Database Configuration Assistant Raw Device Mapping File

Note: You must complete this procedure only if you are using raw devices for database files. You do not specify the raw devices for the Oracle Clusterware files in the Database Configuration Assistant raw device mapping file.

To enable Database Configuration Assistant to identify the appropriate raw device for each database file, you must create a raw device mapping file, as follows:

1. Set the ORACLE_BASE environment variable to specify the Oracle base directory that you identified or created previously:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_BASE=/u01/app/oracle ; export ORACLE_BASE
```

- C shell:

```
% setenv ORACLE_BASE /u01/app/oracle
```

2. Create a database file subdirectory under the Oracle base directory and set the appropriate owner, group, and permissions on it:

```
# mkdir -p $ORACLE_BASE/oradata/dbname
# chown -R oracle:oinstall $ORACLE_BASE/oradata
# chmod -R 775 $ORACLE_BASE/oradata
```

In this example, *dbname* is the name of the database that you chose previously.

3. Change directory to the `$ORACLE_BASE/oradata/dbname` directory.
4. Enter the following command to create a text file that you can use to create the raw device mapping file:

```
# find /dev -user oracle -name 'r*' -print > dbname_raw.conf
```

5. Edit the `dbname_raw.conf` file in any text editor to create a file similar to the following:

Note: The following example shows a sample mapping file for a two-instance RAC cluster.

```

system=/dev/rdbname_system_raw_500m
sysaux=/dev/rdbname_sysaux_raw_800m
example=/dev/rdbname_example_raw_160m
users=/dev/rdbname_users_raw_120m
temp=/dev/rdbname_temp_raw_250m
undotbs1=/dev/rdbname_undotbs1_raw_500m
undotbs2=/dev/rdbname_undotbs2_raw_500m
redo1_1=/dev/rdbname_redo1_1_raw_120m
redo1_2=/dev/rdbname_redo1_2_raw_120m
redo2_1=/dev/rdbname_redo2_1_raw_120m
redo2_2=/dev/rdbname_redo2_2_raw_120m
control1=/dev/rdbname_control1_raw_110m
control2=/dev/rdbname_control2_raw_110m
spfile=/dev/rdbname_spfile_raw_5m
pwdfile=/dev/rdbname_pwdfile_raw_5m

```

In this example, *dbname* is the name of the database.

Use the following guidelines when creating or editing this file:

- Each line in the file must have the following format:

```
database_object_identifier=logical_volume
```

The logical volume names suggested in this manual include the database object identifier that you must use in this mapping file. For example, in the following logical volume name, *redo1_1* is the database object identifier:

```
/dev/rrac_redo1_1_raw_120m
```

- The file must specify one automatic undo tablespace datafile (*undotbsn*) and two redo log files (*redon_1*, *redon_2*) for each instance.
 - Specify at least two control files (*control1*, *control2*).
 - To use manual instead of automatic undo management, specify a single RBS tablespace datafile (*rbs*) instead of the automatic undo management tablespace data files.
6. Save the file and note the file name that you specified.
 7. When you are configuring the `oracle` user's environment later in this chapter, set the `DBCA_RAW_CONFIG` environment variable to specify the full path to this file.

Part III

Installing Oracle Clusterware and Oracle Database 10g with Oracle Real Application Clusters, Creating Oracle Real Application Clusters Databases, and Performing Post-Installation Tasks

Part III describes the two-phase installation process of how to install Oracle Clusterware and Oracle Database 10g with Real Application Clusters (RAC). It also explains how to create RAC databases, and it describes the post-installation tasks. The chapters in Part III are:

- [Chapter 4, "Installing Oracle Clusterware"](#)
- [Chapter 5, "Installing Oracle Database 10g with Real Application Clusters"](#)
- [Chapter 6, "Creating Real Application Clusters Databases with Database Configuration Assistant"](#)
- [Chapter 7, "Oracle Real Application Clusters Post-Installation Procedures"](#)

Installing Oracle Clusterware

This chapter describes the procedures for installing Oracle Clusterware on AIX. If you are installing Oracle Database 10g Real Application Clusters installation, then this is phase one of a two-phase installation. The topics in this chapter are:

- [Verifying Oracle Clusterware Requirements with CVU](#)
- [Preparing to Install Oracle Clusterware with OUI](#)
- [Installing Oracle Clusterware with OUI](#)

Verifying Oracle Clusterware Requirements with CVU

Using the following command syntax, start the Cluster Verification Utility (CVU) to check system requirements for installing Oracle Clusterware:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -pre crsinst -n node_list
```

In the preceding syntax example, replace the variable *mountpoint* with the installation media mountpoint, and replace the variable *node_list* with the names of the nodes in your cluster, separated by commas.

For example, for a cluster with mountpoint `/dev/dvdrom/`, and with nodes `node1`, `node2`, and `node3`, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -pre crsinst -n  
node1,node2,node3
```

The Cluster Verification Utility Oracle Clusterware pre-installation stage check verifies the following:

- **Node Reachability:** All of the specified nodes are reachable from the local node
- **User Equivalence:** Required user equivalence exists on all of the specified nodes
- **Node Connectivity:** Connectivity exists between all the specified nodes through the public and private network interconnections, and at least one subnet exists that connects each node and contains public network interfaces that are suitable for use as virtual IPs (VIPs)
- **Administrative Privileges:** The `oracle` user has proper administrative privileges to install Oracle Clusterware on the specified nodes
- **Shared Storage Accessibility:** If specified, the OCR device and voting disk are shared across all the specified nodes
- **System Requirements:** All system requirements are met for installing Oracle Clusterware software, including kernel version, kernel parameters, memory, swap directory space, temp directory space, and required users and groups

- **Kernel Packages:** All required operating system software packages are installed
- **Node Applications:** The virtual IP (VIP), Oracle Notification Service (ONS) and Global Service Daemon (GSD) node applications are functioning on each node

Troubleshooting Oracle Clusterware Setup

If the CVU report indicates that your system fails to meet the requirements for Oracle Clusterware installation, then use the topics in this section to correct the problem or problems indicated in the report, and run the CVU command again.

User Equivalence Check Failed

Cause: Failure to establish user equivalency across all nodes. This can be due to not creating the required users, or failing to complete SSH configuration properly.

Action: The CVU provides a list of nodes on which user equivalence failed. For each node listed as a failure node, review the Oracle user configuration to ensure that the user configuration is properly completed, and that SSH configuration is properly completed.

See Also: ["Creating Identical Users and Groups on Other Cluster Nodes"](#) and ["Configuring SSH on All Cluster Nodes"](#) in Chapter 2 for user equivalency configuration instructions.

Use the command `su - oracle` and check user equivalence manually by running the `ssh` command on the local node with the `date` command argument using the following syntax:

```
ssh node_name date
```

The output from this command should be the timestamp of the remote node identified by the value that you use for `node_name`. If `ssh` is in the default location, the `/usr/bin` directory, then use `ssh` to configure user equivalence. You can also use `rsh` to confirm user equivalence.

If `ssh` is in a location other than the default, `/usr/bin`, then CVU reports a user equivalence check failure. To avoid this error, navigate to the directory `$CV_HOME/cv/admin`, open the file `cvu_config` with a text editor, and add or update the key `ORACLE_SRVM_REMOTESHELL` to indicate the `ssh` path location on your system. For example:

```
# Locations for ssh and scp commands
ORACLE_SRVM_REMOTESHELL=/usr/local/bin/ssh
ORACLE_SRVM_REMOTECOPY=/usr/local/bin/scp
```

Note the following rules for modifying the `cvu_config` file:

- Key entries have the syntax `name=value`
- Each key entry and the value assigned to the key defines one property only
- Lines beginning with the number sign (`#`) are comment lines, and are ignored
- Lines that do not follow the syntax `name=value` are ignored

When you have changed the path configuration, run the CVU check again. If `ssh` is in another location than the default, you also need to start OUI with additional arguments to specify a different location for the remote shell and remote copy commands. Enter `runInstaller -help` to obtain information about how to use these arguments.

Note: When you or the Oracle Universal Installer run `ssh` or `rsh` commands, including any login or other shell scripts they start, you may see errors about invalid arguments or standard input if the scripts generate any output. You should correct the cause of these errors.

To stop the errors, remove all commands from the Oracle user's login scripts that generate output when you run `ssh` or `rsh` commands.:

If you see messages about X11 forwarding, then perform step 6 in [Chapter 2, "Enabling SSH User Equivalency on Cluster Member Nodes"](#) on page 2-13 to resolve this issue.

If you see errors similar to the following:

```
stty: standard input: Invalid argument
stty: standard input: Invalid argument
```

These errors are produced if hidden files on the system (for example, `.bashrc` or `.cshrc`) contain `stty` commands. If you see these errors, then refer to [Chapter 2, "Preventing Oracle Clusterware Installation Errors Caused by stty Commands"](#) on page 2-14 to correct the cause of these errors.

Node Reachability Check or Node Connectivity Check Failed

Cause: One or more nodes in the cluster cannot be reached using TCP/IP protocol, through either the public or private interconnects.

Action: Use the command `/usr/sbin/ping address` to check each node address. When you find an address that cannot be reached, check your list of public and private addresses to make sure that you have them correctly configured. If you use third-party vendor clusterware, then refer to the vendor documentation for assistance. Ensure that the public and private network interfaces have the same interface names on each node of your cluster.

User Existence Check or User-Group Relationship Check Failed

Cause: The administrative privileges for users and groups required for installation are missing or incorrect.

Action: Use the `id` command on each node to confirm that the Oracle user is created with the correct group membership. Ensure that you have created the required groups, and create or modify the user account on affected nodes to establish required group membership.

See Also: ["Creating Required Operating System Groups and User"](#) in [Chapter 2](#) for instructions about how to create required groups, and how to configure the Oracle user.

Preparing to Install Oracle Clusterware with OUI

Before you install Oracle Clusterware, use the following checklist to ensure that you have all the information you will need during installation, and you have completed all tasks that must be done before starting to install Oracle Clusterware. Mark the check box for each task as you complete it, and write down the information needed, so that you can provide it during installation.

- Shut Down Running Oracle Processes

If you are installing Oracle Clusterware on a node that already has a single-instance Oracle Database 10g installation, then stop the existing ASM instances. After Oracle Clusterware is installed, start up the ASM instances again. When you restart the single-instance Oracle database and then the ASM instances, the ASM instances use the Cluster Synchronization Services (CSSD) Daemon instead of the daemon for the single-instance Oracle database.

You can upgrade some or all nodes of an existing Cluster Ready Services installation. For example, if you have a six-node cluster, then you can upgrade two nodes each in three upgrading sessions. Base the number of nodes that you upgrade in each session on the load the remaining nodes can handle. This is called a "rolling upgrade."

If a Global Services Daemon (GSD) from Oracle9i Release 9.2 or earlier is running, then stop it before installing Oracle Database 10g Oracle Clusterware by running the following command from the GSD's Oracle home:

```
ORACLE_home/bin/gsdctl stop
```

where *Oracle_home* is the home that is running the GSD.

Caution: If you have an existing 9.2 Oracle Cluster Manager (Oracle CM) installation, then *do not* shut down the Oracle CM service. Doing so prevents the Oracle Clusterware 10g Release 2 (10.2) software from detecting the Oracle 9.2 nodelist, and causes failure of the Oracle Clusterware installation.

Note: If you receive a warning to stop all Oracle services after starting OUI, then run the command

```
Oracle_home/bin/localconfig delete
```

where *Oracle_home* is the home that is running CSS.

❑ **Prepare for Clusterware Upgrade If You Have Existing Oracle Cluster Ready Services Software**

During an Oracle Clusterware installation, if OUI detects an existing Oracle Database 10g Release 1 (10.1) Cluster Ready Services, then you are given the option to perform a rolling upgrade by installing Oracle Database 10g Release 2 (10.2) Oracle Clusterware on a subset of cluster member nodes.

If you intend to perform a rolling upgrade, then you should shut down the CRS stack on the nodes you intend to upgrade, and unlock the CRS home using the script *mountpoint/clusterware/upgrade/preupdate.sh*, which is available on the 10g Release 2 (10.2) installation media.

If you intend to perform a standard upgrade, then shut down the CRS stack on all nodes, and unlock the CRS home using the script *mountpoint/clusterware/upgrade/preupdate.sh*.

When you run OUI and select the option to install Oracle Clusterware on a subset of nodes, OUI installs Oracle Database 10g Release 2 (10.2) Oracle Clusterware software into the existing CRS home on the local and remote node subset. When you run the root script, it starts the Oracle Clusterware 10g Release 2 (10.2) stack on the subset cluster nodes, but lists it as an inactive version.

When all member nodes of the cluster are running Oracle Clusterware 10g Release 2 (10.2), then the new clusterware becomes the active version.

If you intend to install RAC, then you must first complete the upgrade to Oracle Clusterware 10g Release 2 (10.2) on all cluster member nodes before you install the Oracle Database 10g Release 2 (10.2) version of RAC.

❑ **Prevent Oracle Clusterware Installation Errors Caused by stty Commands**

During an Oracle Clusterware installation, OUI uses SSH (if available) to run commands and copy files to the other nodes. If you see errors similar to the following, then you have hidden files on the system (for example, `.bashrc` or `.cshrc`) that contain `stty` commands:

```
stty: standard input: Invalid argument
stty: standard input: Invalid argument
```

If you see these errors, then stop the installation, and refer to [Chapter 2, "Preventing Oracle Clusterware Installation Errors Caused by stty Commands"](#) on page 2-14 to correct the cause of these errors.

❑ **Determine the Oracle Inventory location**

If you have already installed Oracle software on your system, then OUI detects the existing Oracle Inventory directory from the `/etc/oraInst.loc` file, and uses this location.

If you are installing Oracle software for the first time on your system, and your system does not have an Oracle inventory, then you are asked to provide a path for the Oracle inventory, and you are also asked the name of the Oracle Inventory group (typically, `oinstall`).

See Also: The pre-installation chapters in [Part II](#) for information about creating the Oracle Inventory, and completing required system configuration.

❑ **Obtain root account access**

During installation, you are asked to run configuration scripts as the root user. You must run these scripts as root, or be prepared to have your system administrator run them for you.

❑ **Decide if you want to install other languages**

During installation, you are asked if you want to install a language other than the default.

❑ **Determine your cluster name, public node names, private node names, and virtual node names for each node in the cluster**

If you install the clusterware during installation, and are not using third-party vendor clusterware, then you are asked to provide a public node name and a private node name for each node. Use your third-party vendor documentation to complete setup of your public and private domain addresses.

When you enter the public node name, use the primary host name of each node. In other words, use the name displayed by the `hostname` command. This node name can be either the permanent or the virtual host name.

In addition, ensure that the following are true:

- Determine a cluster name with the following characteristics:

- * It must be globally unique throughout your host domain
 - * It must be at least one character long and less than 15 characters long
 - * It must consist of the same character set used for host names: underscores (`_`), hyphens (`-`), and single-byte alphanumeric characters (a to z, A to Z, and 0 to 9). If you use third-party vendor clusterware, then Oracle recommends that you use the vendor cluster name.
- Determine a private node name or private IP address for each node. The private IP address is an address that is only accessible by the other nodes in this cluster. Oracle uses private IP addresses for inter-node, or instance-to-instance Cache Fusion traffic. Oracle recommends that you provide a name in the format *public_hostname-priv*. For example: myclstr2-priv.
 - Determine a virtual host name for each node. A virtual host name is a public node name that is used to reroute client requests sent to the node if the node is down. Oracle uses VIPs for client-to-database connections, so the VIP address must be publicly accessible. Oracle recommends that you provide a name in the format *public_hostname-vip*. For example: myclstr2-vip

Note: The following is a list of additional information about node IP addresses:

The IP addresses that you use for all of the nodes in the current installation process must be from the same subnet.

If you create private and virtual host names in the format *nodename-priv* and *nodename-vip*, then OUI looks up these addresses and fills them in by default during the installation. Otherwise, you are required to provide node names using the default formats.

Host names, private names, and virtual host names are not domain-qualified. If you provide a domain in the address field during installation, then OUI removes the domain from the address.

Private IP addresses should not be accessible as public interfaces. Using public interfaces for Cache Fusion can cause performance problems.

❑ **Identify shared storage for Oracle Clusterware files and prepare disk partitions if necessary**

During installation, you are asked to provide paths for two files that must be shared across all nodes of the cluster, either on a shared raw device, or a shared file system file:

- The voting disk is a partition that Oracle Clusterware uses to verify cluster node membership and status.
The voting disk must be owned by the oracle user, must be in the dba group, and must have permissions set to 644. Provide at least 20 MB disk space for the voting disk.
- The Oracle Cluster Registry (OCR) contains cluster and database configuration information for the RAC database and for Oracle Clusterware, including the node list, and other information about cluster configuration and profiles.
The OCR disk must be owned by root, must be in the oinstall group, and must have permissions set to 640. Provide at least 100 MB disk space for the OCR.

If your disks do not have external storage redundancy, then Oracle recommends that you provide one additional location for the OCR disk, and two additional

locations for the voting disk. Creating redundant storage locations protects the OCR and voting disk in the event of a disk failure on the partitions you choose for the OCR and the voting disk.

See Also: The pre-installation chapter in [Part II](#) for information about the minimum raw device sizes

Installing Oracle Clusterware with OUI

This section provides you with information about how to use the Oracle Universal Installer (OUI) to install Oracle Clusterware.

Running OUI to Install Oracle Clusterware

Complete the following steps to install Oracle Clusterware on your cluster. At any time during installation, if you have a question about what you are being asked to do, click the **Help** button on the OUI page.

1. Start the `runInstaller` command from the `clusterware` directory on the 10g Release 2 (10.2) installation media. When OUI displays the Welcome page, click **Next**.
2. Provide information or run scripts as root when prompted by OUI. If you need assistance during installation, click **Help**.
3. After you run `root.sh` on all of the nodes, OUI runs the Oracle Notification Server Configuration Assistant, Oracle Private Interconnect Configuration Assistant, and Cluster Verification Utility. These assistants run without user intervention.

When you have verified that your Oracle Clusterware installation is completed successfully, Oracle Clusterware installation is complete.

If you intend to install Oracle Database 10g with RAC, then continue to [Chapter 5, "Installing Oracle Database 10g with Real Application Clusters"](#). If you intend to use Oracle Clusterware by itself, then refer to the single-instance Oracle Database installation guide.

Troubleshooting Oracle Clusterware Installation Verification

If the CVU report indicates that your Oracle Clusterware installation has a component issue, then use the topics in this section to correct the problem or problems indicated in the report, and run the CVU command again.

CSS is probably working with a non-clustered, local-only configuration on nodes:

Cause: OCR configuration error. The error message specifies the nodes on which this error is found.

This error occurs when, for each specified node, either the contents of the OCR configuration file `ocr.loc` cannot be retrieved, or the configuration key `local_only` is set to `TRUE` in the configuration file of nodes listed in the error message.

Action: Confirm that Oracle Clusterware was installed on the node. Correct the OCR configuration, if it is incorrect. Also, ensure that you have typed the node name correctly when entering the CVU command.

Unable to obtain OCR integrity details from nodes:

Cause: Unable to run the `ocrcheck` tool successfully on the nodes listed in the error message.

Action: If the `ocrcheck` tool indicates an error on only some nodes in the cluster, then OCR is not configured on that set of nodes. If the `ocrcheck` tool indicates that the OCR integrity check failed on all nodes, then the OCR storage area is corrupted. Refer to *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for instructions about how to use `ocrconfig -repair` to resolve this issue.

To configure OCR, you can use `ocrconfig -repair`, as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*, or you can configure OCR manually.

To configure OCR manually, as the Oracle user, enter the following command from the `bin` directory in the CRS home:

```
$ ./ocrcheck
```

To test whether the OCR storage area is corrupted, complete the following task:

1. Enter the following command:

```
ocrconfig -showbackups
```

2. View the contents of the OCR file using the following command syntax:

```
ocrdump -backupfile OCR_filename
```

3. Select a backup file, and use the following command to attempt to restore the file:

```
ocrconfig -restore backupfile
```

if the command returns a failure message, then both the primary OCR and the OCR mirror have failed.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for additional information about testing and restoring the Oracle Cluster Registry.

OCR version is inconsistent among the nodes.

Cause: The OCR version does not match on all the cluster member nodes. Either all nodes are not part of the same cluster, or nodes do not point to the same OCR, or an OCR configuration file has been changed manually to an invalid configuration on one or more nodes

Action: Perform the following checks:

1. Ensure that all listed nodes are part of the cluster.
2. Use the `ocrcheck` utility (`/crs/home/bin/ocrcheck`) to find the location of OCR on each node. Start `ocrcheck` with one of the following command:

As root:

```
# ocrcheck
```

As the Oracle user, or as a user with OSDBA group privileges, from the user home directory:

```
$ /crs/home/bin/ocrcheck
```


3. Repair invalid OCR configurations by logging into a node you suspect has a faulty configuration, stopping the CRS daemon, and entering the following command:

```
ocrconfig -repair ocrmirror device_name
```

the `ocrconfig -repair` command only changes the OCR configuration on the node from which you run the command.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for information about how to use the `ocrconfig` tool to repair OCR files.

Incorrect OCR version found for nodes:

Cause: the OCR version on the specified nodes does not match the version required for 10g Release 2 (10.2).

Action: Follow the same actions described in the preceding error message, "[OCR version is inconsistent among the nodes.](#)" on page 4-8.

OCR integrity is invalid.

Cause: The data integrity of the OCR is invalid, which indicates that OCR storage is corrupted

Action: Follow the same actions described in the preceding error message, "[Unable to obtain OCR integrity details from nodes:](#)" on page 4-7.

OCR ID is inconsistent among the nodes.

Cause: One or more nodes list the OCR in a different location.

Action: Follow the same actions described in the preceding error message, "[OCR version is inconsistent among the nodes.](#)" on page 4-8

Oracle Clusterware Background Processes

The following processes must be running in your environment after the Oracle Clusterware installation for Oracle Clusterware to function:

- `oproc`: Process monitor for the cluster.
- `evmd`: Event manager daemon that starts the `racgevt` process to manage callouts.
- `ocssd`: Manages cluster node membership and runs as `oracle` user; failure of this process results in node restart.
- `crsd`: Performs high availability recovery and management operations such as maintaining the OCR. Also manages application resources and runs as `root` user and restarts automatically upon failure.

Installing Oracle Database 10g with Real Application Clusters

This chapter describes phase two of the installation procedures for installing Oracle Database 10g with Real Application Clusters (RAC). This chapter also describes some of the Oracle Universal Installer (OUI) features. This chapter contains the following topics:

- [Verifying System Readiness for installing Oracle Database with CVU](#)
- [Selecting a Configuration Option](#)
- [Installation of Oracle Database 10g with RAC Using the Oracle Universal Installer](#)
- [De-Installing Real Application Clusters Software](#)

Verifying System Readiness for installing Oracle Database with CVU

To help to verify that your system is prepared to install the Oracle Database with RAC successfully, enter a Cluster Verification Utility (CVU) command using the following command syntax:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -pre dbinst -n node_list [-r {10gR1|10gR2}] [-osdba osdba_group] [-verbose]
```

In the preceding syntax example:

- The variable *mountpoint* is the mountpoint of the installation media
- The variable *node_list* is the list of nodes in your cluster, separated by commas
- The optional flag *-r* takes the options 10gR1 (test for an Oracle Database 10g Release 1 Oracle Cluster Ready Services installation) or 10gR2 (test for an Oracle Database 10g Release 2 Oracle Clusterware installation); if the *-r* flag is missing, by default, the command tests for Oracle Clusterware for Oracle Database 10g Release 2 (10.2) installation
- The variable *osdba_group* is the name of your OSDBA group, which by default is *dba*

For example, to perform a pre-installation check for an Oracle Database 10g Release 2 (10.2) with RAC installation on a two-node cluster with the mountpoint */dev/dvdrom*, with nodes *node1* and *node2*, and with the OSDBA group *dba*, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -pre dbinst -n node1,node2 -verbose
```

Oracle recommends that you select the option `-verbose` to receive progress updates as the CVU performs its system checks. The `-verbose` option provides detailed test reporting, which you can use to identify the cause of any checks that fail.

If the cluster verification check fails, then review and correct the relevant system configuration steps, and run the test again. Use the system configuration checks described in "[Troubleshooting Installation Setup for AIX](#)" to assist you.

Troubleshooting Installation Setup for AIX

If you run the CVU and your system fails system configuration checks, then review the the CVU report, and use the output to resolve failed configuration checks.

User Equivalence Check Failed

Cause: Failure to establish user equivalency across all nodes.

Action: Check user equivalence on each node for the Oracle account.

Check for user equivalence for the oracle account by performing a remote login (rlogin) to each node in the cluster. For example:

```
# su - oracle
$ rlogin node_name
```

If you are prompted for a password, then you have not given the oracle account the same attributes on all nodes.

Check permissions on each node to ensure that the oracle user can write to the new mount points. For example:

```
# su - oracle
$ touch /u01/test
$ ls -l /u01/test
-rw-rw-r-- 1 oracle dba 0 Aug 15 09:36 /u01/test
```

As the `oracle` user, use SSH to connect from each node to itself, and from each node to each other node. For example, to check a two-node cluster with nodes named `node1` and `node2`:

```
[oracle@node1 oracle]:$ ssh node1
[oracle@node1 oracle]:$ ssh node2
[oracle@node2 oracle]:$ ssh node2
[oracle@node2 oracle]:$ ssh node1
[oracle@node1 oracle]:$
```

If you are prompted for a password when logging in as the `oracle` user from one node to another in the cluster, then improper SSH configuration is a probable cause. Check to ensure that you have turned off X11 forwarding, and that the `~/ .ssh/id_rsa` and `~/ .ssh/dsa.pub` files for all nodes are listed in the `~/ .ssh/authorized_keys` file that you create during pre-installation.

See Also: "[Configuring SSH on Cluster Member Nodes](#)" in [Chapter 2, "Pre-Installation Tasks"](#) on page 2-11.

Node Reachability Check Failed

Cause: Failure of one or more nodes to be properly connected for communication.

Action: Possible causes of this message include the following:

- Improper network configuration

- The node running CVU is unable to connect to one or more nodes in the cluster

Use the following command to check your current configuration on each node:

```
ifconfig -a
```

See Also: ["Checking the Network Requirements"](#) in [Chapter 2, "Pre-Installation Tasks"](#) on page 2-21.

Node Connectivity Check Failed

Cause: One or more of the cluster nodes is not able to be connected from all nodes in the cluster

Action: Check for firewalls preventing the nodes from communicating on their private network interfaces.

User Existence Check Failed or User-Group Relationship Check Failed

Cause: The administrative privileges for users and groups required for installation are missing or incorrect.

Action: Use the `id` command on each node to confirm that the oracle user is created with the correct group membership.

See Also: ["Creating Required Operating System Groups and User"](#) in [Chapter 2, "Pre-Installation Tasks"](#) on page 2-4

Shared Storage Check Failed

Cause: Shared storage access from each node in the cluster is not confirmed.

Action: If you are using shared disk storage, then as root, use the command `lspv` and `lsvg` to confirm the reachability of shared storage.

System Requirements Check Failed

Cause: insufficient system resources, missing software packages, or other operating system or hardware problem.

Action: If you did not run the CVU command with the `-verbose` flag, then run the command again using `-verbose`, and review the report to determine which system requirement failed. Correct the problem.

See Also: [Chapter 2, "Pre-Installation Tasks"](#) contains instructions for completing any system requirement configuration that CVU lists as incomplete.

Selecting a Configuration Option

This section describes OUI features that you should understand before beginning phase two of the RAC installation process.

See Also: [Appendix D, "Converting to Oracle Real Application Clusters from Single-Instance Oracle Databases"](#) for information about how to convert single-instance databases to RAC

On the Select Configuration page, you are given the following options:

- **Create a database:** Provides you with the option to create a database using a preconfigured database template designed for particular system load demands, as

described in the section "[Database Configuration Type Descriptions](#)" on page 5-4. If you select the Automatic Storage Management option for storage, then an ASM instance is installed as part of the database installation. The Oracle home is used for the ASM home when you install the database using this method. If you plan to use the ASM instance for multiple database homes, you should select the Configure Automatic Storage Management option to create a separate ASM home.

- **Configure Automatic Storage Management:** Installs an ASM instance only. You are prompted for the ASM SYS password. You should select this option to create an ASM home that is independent of your Oracle home before you install Oracle Database with RAC.
- **Install database software only:** Installs Oracle software; you must complete database configuration later.

If you are installing Oracle Database, then Oracle recommends that you use one of the preconfigured database options, or select the Advanced option and configure a custom starter database.

If you want to configure your environment and create your database manually, then select the **Do not create a database** configuration option, and refer to the manual database creation procedures posted at the following Web site:

<http://otn.oracle.com>

Automatic Storage Management Configuration

If you want to use Automatic Storage Management, then select the **Configure Automatic Storage Management (ASM)** configuration option, and provide information as prompted. Click **Help** if you need assistance.

Database Configuration Type Descriptions

When you run OUI and select Oracle Database 10g, you can select the **General Purpose, Transaction Processing, Data Warehouse**, or **Advanced** database configuration type.

For the first three configuration types, you can complete additional procedures that are described later in this chapter. If you select Advanced configuration, then you can use Database Configuration Assistant (DBCA) to create the database as described in [Chapter 6](#). Oracle recommends that you use DBCA to create your database.

General Purpose, Transaction Processing, and Data Warehouse Configuration Types

The General Purpose, Transaction Processing, and Data Warehouse configuration types use preconfigured database templates.

During installation, if you select one of the preconfigured database types, then OUI starts Oracle Network Configuration Assistant (NETCA) and DBCA, and installs the preconfigured database without further input. During database installation, OUI displays a progress indicator.

DBCA processing for these three configuration types creates a starter database, and configures the Oracle network services. If you choose raw devices on the Specify Database File Storage Option page, then DBCA verifies that you configured the raw devices for each tablespace.

If you select Advanced configuration, then you must enter specific information as described in the next section.

Using the Advanced Configuration Type

If you select the Advanced configuration type, then OUI runs DBCA, which displays General Purpose, Transaction Processing, Data Warehouse, and a fourth configuration type, Custom Database.

The first three templates are customizable versions of the preconfigured database types. The Custom Database type creates a database without using preconfigured options.

The following section provides more detail about OUI and DBCA processing when creating a RAC database.

Behavior of OUI, DBCA, and Other Assistants During Installation

After installation, OUI starts the NETCA. After the NETCA completes its processing, OUI runs DBCA to create your database using Optimal Flexible Architecture (OFA). This means that DBCA creates your database files, including the default server parameter file (SPFILE), using standard file naming and file placement practices. The primary phases of DBCA processing are:

- Verify that you correctly configured the shared disks for each tablespace if you are using raw storage
- Create the database
- Configure the Oracle network services
- Start the listeners and database instances

You can also use DBCA in standalone mode to create a database.

See Also: The *Oracle Database Net Services Administrator's Guide* if you experience problems, for example, with the listener configuration, and for further information about LDAP support

You can use your Oracle9i database language and territory definition files with Oracle Database 10g Release 2 (10.2) that you are about to install. To enable this functionality, you must run OUI from a command line, described in Step 1 in "[Installation of Oracle Database 10g with RAC Using the Oracle Universal Installer](#)" on page 5-5, and use the following statement to set the `b_cr9idata` variable to `true`:

```
runInstaller oracle.rsfnlsrtl_rsf:b_cr9idata=true
```

The remainder of this chapter explains how to use OUI to install Oracle Database 10g with RAC.

Installation of Oracle Database 10g with RAC Using the Oracle Universal Installer

Perform the following procedures to install the Oracle Database 10g software with RAC.

1. Start the `runInstaller` command from the DB directory of the Oracle Database 10g Release 2 (10.2) installation media. When OUI displays the Welcome page, click **Next**.

2. Provide information or run scripts as root when prompted by OUI. If you need assistance during installation, click **Help**. If you encounter problems during installation, then examine the OUI actions recorded in the installation log file. The log file is located in the OraInventory directory (typically, `oinstall`), in the following location:

`OraInventory/logs/installActionsdate_time.log`

Note: The Oracle home name and path that you provide during database installation *must be different* from the home that you used during the Oracle Clusterware installation in phase one. You **must not** install Oracle Database 10g with RAC software into the same home in which you installed the Oracle Clusterware software.

The following is a list of additional information to note about installation:

- If you are installing RAC from the Standard Edition, then you must use ASM for your database storage.

On the Select Database Management Option page, if you have already completed the Grid Control Management Agent installation, then you can select either Grid or Local Database control. Otherwise, only Local Database control for database management is supported for RAC. When you use the local Database Control, you can choose the email option and enter the outgoing SMTP server name and email address.

If you perform an installation that does not include Enterprise Manager, for example, a custom software install without Enterprise Manager, an installation with no Enterprise Manager configuration, or a database creation with your own scripts, then you can configure Enterprise Manager later with OUI, DBCA, or the Enterprise Manager Configuration Assistant (EMCA) utility.

See Also: *Enterprise Manager Grid Control Installation and Basic Configuration* for details about installing Grid Control with OUI, and *Enterprise Manager Advanced Configuration Guide* for details about installing Database Control with DBCA and EMCA

When you have completed the second and final phase of the installation, proceed to [Chapter 7, "Oracle Real Application Clusters Post-Installation Procedures"](#) to perform the post-installation tasks.

Caution: After installation is completed and you have created the database, if you decide that you want to install additional Oracle Database 10g products in the 10g Release 2 (10.2) database, then you must stop *all* processes running in the Oracle home before you attempt to install the additional products. For the Oracle Universal Installer to relink certain executables and libraries, all database processes must be down. Refer to [Appendix F, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#) for additional information.

De-Installing Real Application Clusters Software

If you need to de-install Real Application Cluster software, then you must run OUI to de-install the software on the same node from which you performed the installation, and you must de-install the Oracle database software first before de-installing the Oracle Clusterware software.

Perform the following procedures to de-install Oracle Database 10g RAC and Oracle Clusterware software, as described in the following sections:

- [De-Installing Oracle Database 10g RAC Software and ASM](#)
- [De-Installing Oracle Clusterware](#)

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about using RAC scalability features of adding and deleting nodes and instances from RAC databases, and for information about viewing OCR content

De-Installing Oracle Database 10g RAC Software and ASM

This section describes the procedure to de-install the Oracle Database 10g RAC software and Automatic Storage Management (ASM) software. Before you perform these steps, Oracle recommends that you make a backup of any databases that run from the Oracle home you are about to delete.

1. Examine the `oratab` file to identify the instance dependencies on this Oracle home.
2. Start DBCA, select **Oracle Real Application Clusters Database**, select Delete a database, and select the database that you want to delete. Repeat this step to delete all databases.
3. If you do not use ASM, then proceed to step 4.

If the database is in the Oracle home from which the ASM database runs, then ensure that there are no other database dependencies on these group of ASM instances, and then remove the ASM configuration by logging on as the `oracle` user and completing the following steps:

- a. Connect to the ASM instance and run the following command to determine database instances using this ASM instance.:

```
SQL> select INSTANCE_NAME from GV$ASM_CLIENT;
```

Note: This command only lists database instances that are running. It is possible that other instances are associated with the ASM instance, but they are not currently running. If you removed a database from this Oracle home but the output from the command shows that this ASM instance is supporting a database instance in another Oracle home, then do not remove the ASM instance or the Oracle home.

If your RAC database uses a different Oracle home from the Oracle home that your ASM environment uses, and you want to delete the RAC database, then perform step 5 in the RAC database home.

In the preceding syntax example, replace the variables *node1*, *node2*, and so on, with all the member nodes of the RAC database.

Note: You cannot perform a RAC installation from the same OUI session in which you perform a RAC de-installation. In other words, if you de-install RAC with OUI and want to perform another RAC installation, then you must start a new OUI session.

5. Start OUI, and remove any existing Oracle Database 10g with RAC software by selecting **Deinstall Products**, and selecting the Oracle home that you want to remove. If any of these databases is an ASM database, then de-install the Oracle home with ASM where you want to de-install the Oracle Database software, and then de-install the Oracle Database. Removing ASM does not remove the ASM data or disk groups.

De-Installing Oracle Clusterware

De-install each Oracle Database 10g RAC home by running the procedure in the previous section, "[De-Installing Oracle Database 10g RAC Software and ASM](#)". Then complete the de-installation by removing the Oracle Clusterware software using the following procedures:

1. Run the command `CRS_home/install/rootdelete.sh` to disable the Oracle Clusterware applications that are running on the cluster node. The `rootdelete.sh` script requires three arguments. If you are running this command on a remote node of the cluster, then use `remote` as the first argument, otherwise use `local` as the first argument. If the `ocr.loc` file is on a shared file system, then use `sharedvar`. Otherwise use `nosharedvar` as the second argument. If the Oracle Clusterware home is on a shared file system, then use `sharedhome`, otherwise use `nosharedhome` as the third argument. Repeat this step on each node of the cluster from which you want to de-install Oracle Clusterware.

Note: A node is a local node if you plan to run Steps 2 and 3 on that node. Removing shared OCR contents and the Oracle Clusterware home is done on the local node after you complete removal of other nodes in the cluster.

2. Run the script `CRS_home/install/rootdeinstall.sh` on a local node to remove the OCR. You only need to run this script once.
3. Start OUI. In the Welcome page, click **Deinstall Products** to display the list of installed products. Select the Oracle Clusterware home to de-install.

Creating Real Application Clusters Databases with Database Configuration Assistant

This chapter describes how to use Database Configuration Assistant (DBCA) in standalone mode to create and delete Real Application Clusters (RAC) databases. The topics in this chapter include:

- [Using Database Configuration Assistant in Real Application Clusters](#)
- [Benefits of Using Database Configuration Assistant](#)
- [Oracle Real Application Clusters High Availability Services](#)
- [Automatic Listener Migration from Release 10.1 to 10.2](#)
- [Creating an Oracle Real Application Clusters Database with DBCA](#)
- [Deleting a Real Application Clusters Database with DBCA](#)

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for procedures on using Database Configuration Assistant (DBCA) to add and delete instances

Using Database Configuration Assistant in Real Application Clusters

DBCA has the following primary functions:

- Create the database and its instances
- Set up network configuration for database, instances and database services
- Register the database in Enterprise Manager Grid Control or configure Database Control
- Configure Automatic Storage Management (ASM)
- Start up the database, its instances, services, and any other node applications

See Also:

- ["Creating an Oracle Real Application Clusters Database with DBCA"](#) on page 6-4 for more information about using DBCA in standalone mode
- *Oracle Database Net Services Administrator's Guide* to resolve problems—for example, with the listener configuration—and for further information about Lightweight Directory Access Protocol (LDAP)-compliant directory support

Benefits of Using Database Configuration Assistant

Oracle recommends that you use Database Configuration Assistant (DBCA) to create your RAC database, because DBCA's preconfigured databases optimize your environment for features such as Automatic Storage Management (ASM), the server parameter file, and automatic undo management. DBCA also provides pages to create new ASM disk groups if they are needed. If you use ASM or cluster file system storage, then DBCA also configures automated backup, which uses the flash recovery area.

With DBCA, you can create site-specific tablespaces as part of database creation. If you have data file requirements that differ from those offered by DBCA templates, then create your database with DBCA and modify the data files later. You can also run user-specified scripts as part of your database creation process.

DBCA also configures your RAC environment for various Oracle high availability features, such as services and cluster administration tools. It also starts any database instances required to support your defined configuration.

Oracle Real Application Clusters High Availability Services

When you configure high availability services with the DBCA Database Services page, you can also configure service instance preferences and Transparent Application Failover (TAF) policies.

Service Configuration and Instance Preferences

Use the Database Services page button in the column labeled Not Used, Preferred, or Available to configure service instance preferences as described in the following list:

- Preferred—The service runs primarily on the selected instance
- Available—The service may run on the instance if a preferred instance fails
- Not Used—The service never runs on the instance

Note: You can assign services to run on multiple preferred instances, and fail over to multiple available instances.

After you have created the database, you can configure service instance preferences through Oracle Enterprise Manager Database Control or Grid Control.

Transparent Application Failover Policies

Use the DBCA Database Services page to configure TAF failover policies. The DBCA Database Services page also has a TAF policy selector row under the instance

preference display. Select one of the following options in this row for your failover and reconnection policy preference:

- None—Do not use TAF
- Basic—Establish connections at failover time

Automatic Listener Migration from Release 10.1 to 10.2

If your system has an Oracle Database Release 10g Release 10.1 installation, and you install an Oracle Database 10g Release 2 (10.2) either to coexist with or to upgrade the Oracle Database 10.1 installation, then most installation types automatically migrate the Oracle Database 10.1 listener to the 10g Release 2 (10.2) Oracle home. During migration, they configure and start a default Oracle Net listener using the same TCP/IP port as the existing listener, with the IPC key value EXTPROC. This process occurs through one of the following scenarios:

- During a coexisting installation, Database Configuration Assistant (DBCA) automatically migrates the listener and related files from the 10.1 Oracle home to the 10.2 Oracle home.
- During an upgrade, Oracle Database Upgrade Assistant (DBUA) automatically locates the Oracle 10g release 1 (10.1) listener, and migrates it to Oracle 10g release 2.

The listener migration process stops the listener in the existing Oracle home, and restarts the listener from the new Oracle home. During migration, client applications may not be able to connect to any databases that are registered to the listener that is being migrated.

Verifying Requirements for DBCA

To help to verify that your system is prepared to create the Oracle Database with RAC successfully, enter a Cluster Verification Utility command using the following command syntax:

```
/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -pre dbcfg -n node_list -d
oracle_home [-verbose]
```

In the preceding syntax example, the variable *mountpoint* is the mountpoint of the installation media, the variable *node_list* is the list of nodes in your cluster, separated by commas, and the variable *oracle_home* is the path for the Oracle home directory where OUI creates or modifies the database.

For example, to perform a check to determine if your system is prepared for an Oracle Database with RAC on a two-node cluster with nodes *node1* and *node2*, with the mountpoint */dev/dvdrom/*, and with the Oracle home path */oracle/product/10.2.0*, enter the following command:

```
/dev/dvdrom/clusterware/cluvfy/runcluvfy.sh stage -pre dbcfg -n node1,node2 -d
/oracle/product/10.2.0/
```

You can select the option *-verbose* to receive progress updates as the CVU performs its system checks, and detailed reporting of the test results.

If the Cluster Verification Utility summary indicates that the cluster verification check fails, then review and correct the relevant system configuration steps, and run the test again.

The command `runcluvfy.sh stage -pre dbcfg` verifies the following:

- Node Reachability: All the specified nodes are reachable from the local node
- User Equivalence: User equivalence exists on all the specified nodes
- Node Connectivity: Connectivity exists between all the specified nodes through the available public and private network interfaces
- Administrative Privileges: The `oracle` user has proper administrative privileges on the specified nodes for creating a RAC database
- Oracle Clusterware Integrity: All the components of the Oracle Clusterware stack are fully operational

Creating an Oracle Real Application Clusters Database with DBCA

To create a database with DBCA in standalone mode without ASM or a cluster file system, you must have configured each raw device as described in [Appendix C](#). In addition, you must have run the Oracle Net Configuration Assistant to configure your Oracle Net `listener.ora` file.

If you select DBCA templates that use preconfigured data files and if you do not use ASM or a cluster file system, then during database creation, DBCA first verifies that you created the raw devices for each tablespace. If you have not configured the raw devices, then you must configure the raw devices and replace the default data file names that DBCA provides with raw device names on the DBCA Storage page to continue database creation.

To start DBCA, connect to one of your nodes with Oracle RAC installed as the Oracle owner for the `$ORACLE_HOME`, and enter the command `dbca` command from the `$ORACLE_HOME/bin` directory.

When you start DBCA, the first page it displays is the Welcome page for RAC, which includes the option to select an Oracle Real Application Clusters (RAC) database. DBCA displays this RAC-specific Welcome page only if the Oracle home from which it is started was cluster-installed.

If DBCA does not display the Welcome page for RAC, then DBCA was unable to detect whether the Oracle home is cluster-installed. In this case, check that the OUI inventory is correctly located in `/etc/oraInst.loc`, and that `oraInventory` is not corrupted. Also, perform clusterware diagnostics by running the CVU command `/mountpoint/clusterware/cluvfy/runcluvfy.sh stage -post crsinst -n nodename`.

If the RAC Welcome page opens then provide information as prompted by DBCA. Click **Help** if you need assistance.

The following is a list of information you should be aware of when using DBCA:

- If nodes that are part of your cluster installation do not appear on the Node Selection page, then run the `olsnodes` command to perform inventory diagnostics and clusterware diagnostics.
- The global database name can be up to 30 characters in length, and must begin with an alphabetical character. The SID prefix must begin with an alphabetical character.
- The maximum number of characters you can use for the SID prefix is 8 characters. DBCA uses the SID prefix to generate a unique value for the variable `ORACLE_SID` for each instance.
- On the Management Options page, If you select the option **Enterprise Manager with the Grid Control**, and DBCA discovers agents. If you select the option **Database Control**, then you can set up E-mail notification and enable daily

backups. For E-mail notifications, you provide the outgoing mail server and E-mail address. For daily backups, you enter the backup time and operating system credentials for the user that performs backup.

- To use a flash recovery area, Oracle recommends that you create two separate ASM disk groups: one for the database area and one for the recovery area.

See Also: *Oracle Database Concepts* for more information about using a flash recovery area

- On the ASM Disk Groups page, if you do not see the disks you wish to add, click **Change Disk Discovery Path** to alter the search path used by DBCA to find available disks. You can select disks with a status of `Candidate` or `Former` (never used in an ASM disk group or no longer in a group) by checking the select box. If you want to add disks that still have ASM disk headers but the disk group is no longer in use (a case that can occur if you are selecting disks after an aborted install, a de-install performed without dropping the disk group, or other configuration problems), then use the `Force` command.

- If DBCA displays the following message:

The file `oracle_home/bin/oracle` does not exist on node `node_name`.
Make sure that file exists on these nodes before proceeding.

This message means that the Oracle home from which the first ASM instance in the cluster runs is not installed on these cluster nodes. You must extend the ASM Oracle home to these nodes by performing the procedure documented in "Step 4: Adding Nodes at the Oracle RAC Database Layer" in the *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*. However, do not perform Step 5 in that section. OUI extends the ASM Oracle home to the selected nodes and performs any configuration required for running an ASM instance on these nodes.

- If DBCA displays the following message:

Please run the DBCA from one of the nodes that has an existing ASM instance `node_list`.

This message means that you are attempting to create a RAC database using ASM storage, but the ASM instance does not exist on the node from which you ran DBCA. However, ASM instances do exist on the remote nodes that appear in the message node list. In this case, DBCA cannot clone the existing ASM instance from the remote node to the local node. To correct this, start DBCA from one of the nodes shown in the node list to create your RAC database using ASM storage. This copies the local node's ASM instance and modifies its parameters and attributes to create ASM instances on the nodes in your cluster that do not have ASM instances.

- On the Recovery Configuration page, if you are using ASM or GPFS storage, then you can also select the flash recovery area and size on the Recovery Configuration page. If you are using ASM, then the flash recovery area defaults to the ASM Disk Group. If you are using GPFS, then the flash recovery area defaults to `$ORACLE_BASE/flash_recovery_area`.
- On the Initialization Parameters page, set the value of the `CLUSTER_DATABASE_INSTANCES` parameter to the number of instances you intend to use in the cluster if you are not including all the related nodes during the current execution of DBCA.

In addition, if your global database name is longer than eight characters, then the database name value (in the `db_name` parameter) is truncated to the first eight characters and the `DB_UNIQUE_NAME` parameter value is set to the global name.

After you respond to DBCA prompts, review the Summary dialog information and click **OK**, DBCA does the following:

- Creates an operative RAC database and its instances
- Creates the RAC data dictionary views
- Configures the network for the cluster database
- Starts the Oracle services if you are on a Windows-based platform
- Migrates Oracle Database 10g Release 1 (10.1) listener and related files to the 10.2 Oracle home
- Starts the listeners and database instances and then starts the high availability services
- Configures Enterprise Manager Database Control or Grid Control

Caution: After you have created the database, if you decide that you want to install additional Oracle Database 10g products in the 10g Release 2 (10.2) database you have created, then you must stop *all* processes running in the Oracle home before you attempt to install the additional products. For the Oracle Universal Installer to relink certain executables and libraries, all database processes must be down. Refer to [Appendix F, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#) for additional information.

Deleting a Real Application Clusters Database with DBCA

This section explains how to delete a RAC database with DBCA. This process deletes a database and removes a database's initialization parameter files, instances, OFA structure, and Oracle network configuration. However, this process does not remove data files if you placed the files on raw devices or on raw partitions.

To delete a database with DBCA:

1. Start DBCA on one of the nodes by running the DBCA command from the `$ORACLE_HOME/bin` directory.
The DBCA Welcome page appears.
2. Select Oracle Real Application Clusters and click **Next**.
After you click **Next**, DBCA displays the Operations page.
3. Select Delete a database, click **Next**. DBCA displays the List of Cluster Databases page.
4. If your user ID and password are not operating-system authenticated, then the List of Cluster Databases page displays the user name and password fields. If these fields appear, then enter a user ID and password that has SYSDBA privileges.
5. Select the database to delete and click **Finish**.

After you click **Finish**, DBCA displays a dialog to confirm the database and instances that DBCA is going to delete.

6. Click **OK** to begin the deletion of the database and its associated files, services, and environment settings, or click **Cancel** to stop the operation.

When you click **OK**, DBCA continues the operation and deletes all of the associated instances for this database. DBCA also removes the parameter files, password files, and oratab entries.

At this point, you have accomplished the following:

- Deleted the selected database from the cluster
- Deleted the selected database's Oracle services for Windows-based platforms
- Deleted high availability services that were assigned to the database
- Deleted the Oracle Net configuration for the database
- Deconfigures Database Control
- Deleted the OFA directory structure from the cluster
- Deleted the data files if the data files were not on raw devices

Oracle Real Application Clusters Post-Installation Procedures

This chapter describes how to complete the post-installation tasks after you have installed the Oracle Database 10g with Real Application Clusters (RAC) software. It contains the following sections:

- [Required Post-Installation Tasks](#)
- [Recommended Post-Installation Tasks](#)

Note: This chapter only describes basic configurations. Refer to the *Oracle Database 10g Administrator's Guide for UNIX Systems*, *Oracle Database Platform Guide for Microsoft Windows (32-Bit)*, and the product administration and tuning guides for more detailed configuration and tuning information.

Required Post-Installation Tasks

You must perform the following tasks after completing your installation:

- [Back Up the Voting Disk After Installation](#)
- [Download and Install Patches](#)
- [Configure Oracle Products](#)

Back Up the Voting Disk After Installation

After your Oracle Database 10g with RAC installation is complete and after you are sure that your system is functioning properly, make a backup of the contents of the voting disk. use the `dd.exe` utility.

Also make a backup of the voting disk contents after you complete any node additions or node deletions and after running any deinstallation procedures.

Download and Install Patches

Refer to the Oracle *MetaLink* Web site for required patches for your installation. To download required patches:

1. Use a Web browser to view the Oracle *MetaLink* Web site:
<http://metalink.oracle.com>
2. Log in to Oracle *MetaLink*.

Note: If you are not an Oracle*MetaLink* registered user, then click **Register for MetaLink** and register.

3. On the main Oracle*MetaLink* page click **Patches**.
4. On the Select a Patch Search Area page click **New MetaLink Patch Search**.
5. On the Simple Search page click **Advanced**.
6. On the Advanced Search page click the search icon next to the Product or Product Family field.
7. In the Search and Select: Product Family field, enter RDBMS Server in the For field and click **Go**.
8. Select RDBMS Server under the Results heading and click **Select**.
RDBMS Server appears in the Product or Product Family field and the current release appears in the Release field.
9. Select your platform from the list in the Platform field and click **Go**.
10. Any available patches appear under the Results heading.
11. Click the number of the patch that you want to download.
12. On the Patch Set page, click **View README** and read the page that appears. The README page contains information about the patch set and how to apply the patches to your installation.
13. Return to the Patch Set page, click **Download**, and save the file on your system.
14. Use the unzip utility provided with Oracle Database 10g to uncompress the Oracle patches that you downloaded from Oracle*MetaLink*. the unzip utility is located in the `$ORACLE_HOME/bin` directory.

Configure Oracle Products

Many Oracle products and options must be configured before you use them for the first time. Before using individual Oracle Database 10g database products or options, refer to the manual in the product documentation library which is available in the DOC directory on the 10g Release 2 (10.2) installation media, or on the OTN Web site.

Verify Required Post-Installation is Completed

Use the following commands to verify that all required post-installation steps are completed

Recommended Post-Installation Tasks

This section explains the tasks that Oracle recommends you perform after completing an installation. There is one task recommended on all systems and additional tasks that apply only to UNIX-based or Windows-based systems (but not both), as follows:

- [Verifying Enterprise Manager Operations](#)
- [Recommended Post-Installation Tasks](#)

Verifying Enterprise Manager Operations

Run the following command to verify the Enterprise Manager configuration in your newly installed Real Application Clusters environment:

```
srvctl config database -d db_name
```

SRVCTL displays the name of the node and the instance for the node. The following example shows a node named `db1-server` running an instance named `db1`. Run the following command:

```
srvctl config database -d db
```

The output should be similar to:

```
db1-server db1 /private/system/db
db2-server db2 /private/system/db
```

Continue with the following section, "[Recommended Post-Installation Tasks](#)". When you have completed these tasks, you should proceed with the initial configuration tasks described in [Part IV](#).

Recommended Post-Installation Tasks

Oracle recommends that you complete the following tasks after installing Oracle RAC:

- [Back Up the root.sh Script](#)
- [Set Up Users Accounts](#)
- [Set the ORACLE_HOME and ORACLE_SID Environments](#)

Back Up the root.sh Script

Oracle recommends that you back up the `root.sh` script after you complete an installation. If you install other products in the same Oracle home directory, then the Oracle Universal Installer (OUI) updates the contents of the existing `root.sh` script during the installation. If you require information contained in the original `root.sh` script, then you can recover it from the `root.sh` file copy.

Set Up Users Accounts

For information about setting up additional optional user accounts, refer to the *Oracle Database 10g Administrator's Guide for UNIX Systems*.

When you complete these procedures, you are ready to perform the initial configuration tasks described in [Part IV](#).

Set the ORACLE_HOME and ORACLE_SID Environments

To ensure that you can use Oracle tools such as SQL*Plus to connect to the database, Oracle recommends that you set the `ORACLE_HOME` and `ORACLE_SID` environment variables to the correct Oracle home and Oracle SID that you configured during installation.

Part IV

Oracle Real Application Clusters Environment Configuration

Part IV describes how to use the server parameter file (SPFILE) in Oracle Database 10g Real Application Clusters (RAC) and it describes the installed configuration. The chapters in Part IV are:

- [Chapter 8, "Configuring the Server Parameter File in Oracle Real Application Clusters Environments"](#)
- [Chapter 9, "Understanding the Oracle Real Application Clusters Installed Configuration"](#)

Configuring the Server Parameter File in Oracle Real Application Clusters Environments

This chapter describes server parameter file (SPFILE) placement and configuration in Real Application Clusters (RAC) environments. The topics in this chapter are:

- [Parameter Files and Real Application Clusters](#)
- [Using Server Parameter Files in Real Application Clusters](#)
- [Parameter File Search Order in Real Application Clusters](#)
- [Migrating to the Server Parameter File in Real Application Clusters Environments](#)
- [Server Parameter File Errors in Real Application Clusters](#)

See Also: The *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about parameters and the *Oracle Real Application Clusters Deployment and Performance Guide* for a discussion of parallel execution-related parameters in RAC data warehouse environments

Parameter Files and Real Application Clusters

Oracle uses parameter settings in parameter files to determine how to control various database resources. You can use two types of files for parameter administration: the server parameter file (SPFILE) or one or more traditional client-side parameter files.

Oracle recommends that you manage parameters using an SPFILE. If you use client-side parameter files, then Oracle does not preserve parameter changes made for self-tuning after shutdown.

See Also: Oracle Database 10g Real Application Clusters documentation for more information about using client-side parameter files

Using Server Parameter Files in Real Application Clusters

By default, Oracle creates the server parameter file based on one SPFILE. You can change parameter settings in the server parameter file only by using Oracle Enterprise Manager or `ALTER SYSTEM SET SQL` statements; the server parameter file is a binary file that you should not edit.

Note: Oracle recommends that you avoid modifying the values for self-tuning parameters; overriding these settings can adversely affect performance.

If you are upgrading from a previous Oracle release, then create and configure the server parameter file for RAC using the procedures described in the following section.

Location of The Server Parameter File

The default location of the server parameter file (SPFILE) when the database creates it from a PFILE is platform-dependent.

The default location of the server parameter file is:

```
$_ORACLE_HOME/dbs/spfile$_ORACLE_sid.ora
```

The default location of the server parameter file is inappropriate for RAC databases and ASM instances if you use raw devices, because all instances must use the same server parameter file.

Instead, Oracle recommends that you use a PFILE in this directory:

```
$_ORACLE_HOME/dbs/init$_ORACLE_sid.ora
```

This path is valid for each instance and it refers to a single, shared initialization parameter file. If you use raw storage, then the file must contain the following entry where *n* is a numeric value:

```
SPFILE= '/dev/rlracclvn
```

However, if you use a cluster file system, then use one of the following file location:

```
SPFILE= ' $_ORACLE_HOME/dbs/spfile.ora '
```

If you use ASM, then the SPFILE value will be:

```
SPFILE= '+disk_group_name/dbunique_name/spfiledbname.ora '
```

where *dbunique_name* is the unique database name and *dbname* is the database name.

You must use the same value of SPFILE so that all instances use the same server parameter file at startup.

To use DBCA to create your database and to use the server parameter file, on the Initialization Parameters page select Create server parameter file (SPFILE) under the File Locations tab which is visible only if you are using raw storage. Then enter either a shared file system filename or the raw device path name in the Server Parameters Filename field.

Note: When you use DBCA to create the server parameter file, the default PFILE file name is
\$_ORACLE_HOME/dbs/init\$_ORACLE_sid.ora.

Parameter File Search Order in Real Application Clusters

Oracle searches for your parameter file in the following order:

1. \$ORACLE_HOME/dbs/spfilesid.ora
2. \$ORACLE_HOME/dbs/spfile.ora
3. \$ORACLE_HOME/dbs/initSID.ora

Migrating to the Server Parameter File in Real Application Clusters Environments

Migrate to the server parameter file by creating and editing the server parameter file using the procedures described in this section.

Server Parameter File Placement in Real Application Clusters

For single-node cluster-enabled configurations, or if you are using ASM disk groups or a cluster file system, place the server parameter file in an ASM disk group or on a file system. Otherwise, place the server parameter file on a shared raw device that is at least 5MB in size.

Procedures for Migrating to the Server Parameter File

Migrate to the server parameter file (SPFILE) file by completing the following procedures:

1. Combine the initialization parameter files for all instances into one `initdbname.ora` file by copying all shared IFILE contents *as is*. All parameters defined in your IFILE parameter files are global. Therefore, create them as "parameter=value" without system identifier (sid) prefixes.
2. Copy all instance-specific parameter definitions from `initSID.ora` files using the following syntax, where the variable `sid` is the system identifier (SID) of the instance:

```
sid.parameter=value
```

3. If you are using a cluster file system, then create the server parameter file using the `CREATE SPFILE` statement as in the following example:

```
CREATE SPFILE='?/dbs/spfile_dbname.ora'
FROM PFILE='?/dbs/initdbname.ora'
```

If you use ASM, then use the following syntax to create the server parameter file:

```
CREATE SPFILE='+disk_group_name/db_uniquename/spfiledbname.ora'
FROM PFILE='?/dbs/initdbname.ora'
```

If you use raw storage, then use the following syntax to create the server parameter file on a raw device where `n` is a numeric value:

```
CREATE SPFILE='/dev/r1racclvn'
FROM PFILE='?/dbs/initdbname.ora'
```

These statements read your combined `initdbname.ora` file that you created by merging your IFILES. Then it transfers the settings for the parameters from the merged file into your server parameter file.

4. Oracle recommends that you use the SPFILE by using the PFILE as a pointer to the SPFILE. Do this by running the `STARTUP` command as in the following example, where the SID variable `sid` in the file `initSID.ora` is the SID that you use in the SPFILE entry from Step 3. For example:

```
STARTUP PFILE=$ORACLE_HOME/dbs/initsid.ora
```

If you use this `STARTUP` command syntax, then Oracle uses the server parameter file entry specified in `initsid.ora`.

Note: the SPFILE for ASM instance cannot be stored in ASM, as it is used to start the ASM instance. You can place an ASM instance SPFILE on a shared raw device or in a cluster file system for ASM, or you can have a traditional client-side parameter file for each ASM instance.

Server Parameter File Errors in Real Application Clusters

Oracle reports errors that occur during server parameter file creation or while reading the file during startup. If an error occurs during a parameter update, then Oracle records the error in your `ALERT.LOG` file and ignores subsequent parameter updates to the file. If this happens, then do either of the following:

- Shut down the instance, recover the server parameter file, and restart the instance.
- Enable the instance to continue running without regard for subsequent parameter updates.

Oracle displays errors for parameter changes that you attempt when you incorrectly use the `ALTER SYSTEM SET` statement. Oracle does this when an error occurs while reading from or writing to the server parameter file.

See Also: *The Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about backing up the SPFILE

Understanding the Oracle Real Application Clusters Installed Configuration

This chapter describes the Oracle Real Application Clusters (RAC) installed configuration. The topics in this chapter include:

- [Understanding the Configured Environment in Real Application Clusters](#)
- [Oracle Cluster Registry in Oracle Real Application Clusters](#)
- [Oratab Configurations for Oracle Real Application Clusters](#)
- [Database Components Created Using Database Configuration Assistant](#)
- [Managing Undo Tablespaces in Real Application Clusters](#)
- [Initialization Parameter Files](#)
- [Configuring Service Registration-Related Parameters in Real Application Clusters](#)
- [Configuring the Listener File \(listener.ora\)](#)
- [Directory Server Access \(ldap.ora File\)](#)
- [Net Service Names \(tnsnames.ora File\)](#)
- [Net Services Profile \(sqlnet.ora File\)](#)

Understanding the Configured Environment in Real Application Clusters

The Oracle Net Configuration Assistant (NetCA) and Database Configuration Assistant (DBCA) configure your environment to meet the requirements for database creation and Enterprise Manager discovery of Real Application Cluster databases.

Note: Configuration files are created on each node in your cluster database.

Oracle Cluster Registry in Oracle Real Application Clusters

DBCA uses Oracle Cluster Registry (OCR) for storing the configurations for the cluster databases that it creates. The OCR is a shared file in a cluster file system environment. If you do not use a cluster file system, then you must make this file a shared raw device. The Oracle Universal Installer (OUI) automatically initializes the OCR during the Oracle Clusterware installation.

Oratab Configurations for Oracle Real Application Clusters

Oracle creates an entry for each RAC database in the `oratab` configuration file. Oracle Enterprise Manager uses this file during service discovery to determine the name of the RAC database, and to determine whether the database should be automatically started when the system is restarted. The database entry has the following syntax:

```
db_unique_name:$ORACLE_HOME:N
```

where *db_unique_name* is the database name for your RAC database, *\$ORACLE_HOME* is the directory path to the database, and *N* indicates that the database should not be started at restart time. A sample entry for a database named `db` is:

```
db:/private/system/db:N
```

Note: Where the notation *db_name* appears in the previous example and throughout this chapter, it refers to the database name you entered when prompted by DBCA, or it refers to the entry you made for the `DATABASE` keyword of the `CREATE DATABASE` statement.

Database Components Created Using Database Configuration Assistant

This section describes the database components that DBCA creates, which include:

- [Tablespaces and Data files](#)
- [Control Files](#)
- [Redo Log Files](#)

Tablespaces and Data files

For both single-instance and cluster database environments, an Oracle Database is divided into smaller logical areas of space known as tablespaces. Each tablespace corresponds to one or more data files stored on a disk. [Table 9-1](#) shows the tablespace names used by a RAC database and the types of data they contain:

Table 9-1 Tablespace Names that Real Application Clusters Databases Use

Tablespace Name	Contents
SYSTEM	Consists of the data dictionary, including definitions of tables, views, and stored procedures needed by the database. Oracle automatically maintains information in this tablespace.
SYSAUX	An auxiliary system tablespace that contains the <code>DRSYS</code> (contains data for OracleText), <code>CWMLITE</code> (contains the OLAP schemas), <code>XDB</code> (for XML features), <code>ODM</code> (for Oracle Data Mining), <code>TOOLS</code> (contains Enterprise Manager tables), <code>INDEX</code> , <code>EXAMPLE</code> , and <code>OEM-REPO</code> tablespaces.
USERS	Consists of application data. As you create and enter data into tables, Oracle fills this space with your data.

Table 9–1 (Cont.) Tablespace Names that Real Application Clusters Databases Use

Tablespace Name	Contents
TEMP	Contains temporary tables and indexes created during SQL statement processing. You may need to expand this tablespace if you are running a SQL statement that involves significant sorting, such as <code>ANALYZE COMPUTE STATISTICS</code> on a very large table, or the constructs <code>GROUP BY</code> , <code>ORDER BY</code> , or <code>DISTINCT</code> .
UNDOTBS <i>n</i>	These are the undo tablespaces for each instance that DBCA creates for automatic undo management.
RBS	If you do not use automatic undo management, then Oracle uses the RBS tablespace for the rollback segments.

You cannot alter these tablespace names when using the preconfigured database configuration options from the Oracle Universal Installer. However, you can change the names of the tablespaces if you use the advanced database creation method.

As mentioned, each tablespace has one or more data files. The data file names created by the preconfigured database configuration options vary by storage type such as ASM, OFS, raw devices, and so on.

You can specify different symbolic names with the Advanced database configuration option.

Control Files

The database is configured with two control files that are stored on shared storage.

Redo Log Files

Each instance is configured with at least two redo log files that are stored in the shared storage. If you chose cluster file system, then these files are shared file system files. If you do not have a cluster file system, then these files are raw devices. If you use ASM, then these files are stored on the ASM disk group.

The file names of the redo log files that are created with the preconfigured database configuration options vary by storage type. You must enter the raw device names unless you are using a cluster file system.

When using raw devices, to use the advanced database creation method, locate the redo log files in the Database Storage page and replace their default filenames with the correct raw device names or symbolic link names.

Managing Undo Tablespaces in Real Application Clusters

Oracle stores rollback or undo information in undo tablespaces. To manage undo tablespaces, Oracle recommends that you use automatic undo management. Automatic undo management is an automated undo tablespace management mode that is easier to administer than manual undo management.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for more information about managing undo tablespaces

Initialization Parameter Files

Oracle recommends using the server parameter file (SPFILE). This file resides on the server on the shared disk; all instances in a cluster database can access this parameter file.

See Also: [Chapter 8, "Configuring the Server Parameter File in Oracle Real Application Clusters Environments"](#) for more information about the creation and use of parameter files

Configuring Service Registration-Related Parameters in Real Application Clusters

Two key benefits of RAC are connection load balancing and failover. RAC extends the ability of single-instance Oracle database load balancing, where connections are distributed among local dispatchers, to the balancing of connections among all instances in a cluster database. In addition, RAC provides failover by configuring multiple listeners on multiple nodes to manage client connection requests for the same database service. Connection load balancing and failover increase availability by taking advantage of the redundant resources within a cluster database. These features, however, require cross instance registration.

Cross instance registration in RAC occurs when an instance's PMON process registers with the local listener and with all other listeners. Thus, all instances in the cluster database register with all listeners that run on nodes that run instances of the cluster database. This enables all listeners to manage connections across all instances for both load balancing and failover.

Cross instance registration requires configuring the `LOCAL_LISTENER` and `REMOTE_LISTENER` initialization parameters. The `LOCAL_LISTENER` parameter identifies the local listener and the `REMOTE_LISTENER` parameter identifies the global list of listeners. The `REMOTE_LISTENER` parameter is dynamic. Oracle changes the setting for `REMOTE_LISTENER` dynamically when you reconfigure your cluster database, for example, when you add or delete instances.

By default, DBCA configures your environment with dedicated servers. However, if you select the Shared server option on DBCA, then Oracle configures the shared server. In this case, Oracle uses both dedicated and shared server processing. When shared servers are configured, the `DISPATCHERS` parameter is specified as in the following example:

```
DISPATCHERS=" (protocol=tcp) "
```

If the `DISPATCHERS` initialization parameter does not specify the `LISTENER` attribute as in the previous example, then the PMON process registers information for all dispatchers with the listeners specified by the `LOCAL_LISTENER` and `REMOTE_LISTENER` parameters.

However, when the `LISTENER` attribute is specified, the PMON process registers dispatcher information with the listeners specified by the `LISTENER` attribute. In this case, setting the `LISTENER` attribute overrides `REMOTE_LISTENER` settings for the specified dispatchers as in the following example:

```
DISPATCHERS=" (protocol=tcp) (listener=listeners_db_name) "
```

See Also: *Oracle Database Net Services Administrator's Guide* for further information about cross instance registration, shared and dedicated server configurations, and connection load balancing

Configuring the Listener File (listener.ora)

You can configure two types of listeners in the `listener.ora` file as described under the following headings:

- [Local Listeners](#)
- [Multiple Listeners](#)
- [How Oracle Database Uses the Listener \(listener.ora File\)](#)

Local Listeners

If you configured dedicated server mode using the DBCA Connection Mode tab on the Initialization Parameters page, then DBCA automatically configures the `LOCAL_LISTENER` parameter when the listener uses a nondefault address port.

If you configured the dedicated server mode by setting the `REMOTE_LISTENER` initialization parameter, then you must also configure the instance-specific `LOCAL_LISTENER` initialization parameter.

For example, to configure the `LOCAL_LISTENER` parameter, add the following entry to the initialization parameter file, where `listener_sid` is resolved to a listener address through either a `tnsnames.ora` file or through the Oracle Names Server:

```
sid.local_listener=listener_sid
```

The following entry should be in your `tnsnames.ora` file:

```
listener_sid=(address=(protocol=tcp) (host=node1-vip) (port=1522))
```

Multiple Listeners

If DBCA detects more than one listener on the node, it displays a list of the listeners. You can select one or all of these listeners with which to register your database.

How Oracle Database Uses the Listener (listener.ora File)

Services coordinate their sessions using listener file entries by running a process on the server that receives connection requests on behalf of a client application. Listeners are configured to respond to connection requests sent to protocol addresses for a database service or non-database service.

Protocol addresses are configured in the listener configuration file, `listener.ora`, for a database service or a non-database service. Clients configured with the same addresses can connect to a service through the listener.

During a preconfigured database configuration installation, the Oracle Net Configuration Assistant creates and starts a default listener called `LISTENER_NODENAME`. The listener is configured with a default protocol listening addresses for the database and external procedures. The advanced installation process prompts you to create at least one listener with the Oracle Net Configuration Assistant. The listener is configured to respond to connection requests that are directed at one protocol address you specify, as well as an address for external procedures.

Both installation modes configure service information about the RAC database and external procedures. An Oracle Database 10g Release 2 (10.2) database service automatically registers its information with the listener, such as its service name, instance names, and load information.

This feature, called service registration, does not require configuration in the `listener.ora` file. After listener creation, the Oracle Net Configuration Assistant starts the listener. A sample `listener.ora` file with an entry for an instance named `node1` is:

```
listener_node1=
  (description=
    (address=(protocol=ipc) (key=extproc))
    (address=(protocol=tcp) (host=node1-vip) (port=1521))
    (address=(protocol=tcp) (host=node1-ip) (port=1521)))
sid_list_listener_node1=
  (sid_list=
    (sid_desc=
      (sid_name=plsextproc)
      (oracle_home=/private/system/db)
      (program=extproc))
```

Listener Registration and PMON Discovery

When a listener starts after the Oracle instance starts, and the listener is listed for service registration, registration does not occur until the next time the PMON discovery routine starts. By default, PMON discovery occurs every 60 seconds.

To override the 60-second delay, use the SQL `ALTER SYSTEM REGISTER` statement. This statement forces PMON to register the service immediately.

Oracle recommends that you create a script to run this statement immediately after starting the listener. If you run this statement while the listener is up and the instance is already registered, or while the listener is down, then the statement has no effect.

See Also: *Oracle Database Net Services Administrator's Guide* for further information about the listener and the `listener.ora` file

Directory Server Access (ldap.ora File)

If you configure access to a Lightweight Directory Access Protocol (LDAP)-compliant directory server with the Oracle Net Configuration Assistant during a Custom Install or Advanced database configuration, an `ldap.ora` file is created. The `ldap.ora` file contains the following types of information:

- Type of directory
- Location of the directory
- Administrative context from which this server can look up, create, and modify a net service name, and the database service entries

See Also: *Oracle Database Net Services Administrator's Guide* for further information about directory naming configuration and directory server access configuration

Net Service Names (tnsnames.ora File)

A `tnsnames.ora` file is created on each node with net service names. A connect identifier is an identifier that maps to a connect descriptor. A connect descriptor contains the following information:

- The network route to the service, including the location of the listener through a protocol address
- The `SERVICE_NAME` for an Oracle release 8.1 or later, or `sid` for pre-8.1 Oracle releases

Note: The `SERVICE_NAME` parameter you use in `tnsnames.ora` is singular because you can only specify one service name.

DBCA creates net service names for connections as shown in [Table 9–2](#):

Table 9–2 Connections for Net Service Names

Net Service Name Type	Description
Database connections	<p>Clients that connect to any instance of the database use the net service name entry for the database. This entry also enables Oracle Enterprise Manager to discover a RAC database.</p> <p>A listener address is configured for each node that runs an instance of the database. The <code>LOAD_BALANCE</code> option causes Oracle to choose the address randomly. If the chosen address fails, then the <code>FAILOVER</code> option causes the connection request to fail over to the next address. Thus, if an instance fails, then clients can still connect using another instance.</p> <p>In the following example, <code>db.us.oracle.com</code> is used by the client to connect to the target database, <code>db.us.oracle.com</code>.</p> <pre>db.us.acme.com= (description= (load_balance=on) (address=(protocol=tcp)(host=node1-vip)(port=1521) (address=(protocol=tcp)(host=node2-vip)(port=1521) (connect_data= (service_name=db.us.acme.com)))</pre> <p>Note: <code>FAILOVER=ON</code> is set by default for a list of addresses. Thus, you do not need to explicitly specify the <code>FAILOVER=ON</code> parameter.</p> <p>When you set <code>DB_UNIQUE_NAME</code> by entering a global database name that is longer than eight characters, excluding <code>DB_DOMAIN</code>, then a net service entry similar to the following is created:</p> <pre>mydatabase.us.acme.com= (description = (address = (protocol = tcp)(host = node1-vip)(port = 1521)) (address = (protocol = tcp)(host = node2-vip)(port = 1521)) (load_balance = yes) (connect_data = (server = dedicated) (service_name = mydatabase.us.acme.com)))</pre>

Table 9–2 (Cont.) Connections for Net Service Names

Net Service Name Type	Description
Instance connections	<p>Clients that connect to a particular instance of the database use the net service name entry for the instance. This entry, for example, enables Oracle Enterprise Manager to discover the instances in the cluster. These entries are also used to start and stop instances.</p> <p>In the following example, <code>db1.us.acme.com</code>, is used by Oracle Enterprise Manager to connect to an instance named <code>db1</code> on <code>db1-server</code>:</p> <pre>db1.us.acme.com= (description= (address=(protocol=tcp)(host=node1-vip)(port=1521)) (connect_data= (service_name=db.us.acme.com) (instance_name=db1)))</pre>
Remote listeners	<p>As discussed in "Configuring Service Registration-Related Parameters in Real Application Clusters" on page 9-4, the <code>REMOTE_LISTENER</code> parameter identifies the global list of listeners and it is dynamic. Oracle changes the setting for <code>REMOTE_LISTENER</code> when you reconfigure your cluster database.</p> <p>Whether using shared servers or dedicated servers, the list of remote listeners is supplied using the <code>REMOTE_LISTENERS</code> parameter, for example:</p> <pre>REMOTE_LISTENERS=listeners_db_unique_name</pre> <p>This enables the instance to register with remote listeners on the other nodes; <code>listeners_db_unique_name</code> is resolved through a naming method such as a <code>tnsnames.ora</code> file.</p> <p>In the following example, <code>listeners_db.us.acme.com</code> is resolved to a list of listeners available on the nodes on which the cluster database has instances:</p> <pre>listeners_db.us.acme.com= (address_list= (address=(protocol=tcp)(host=node1-vip)(port=1521)) (address=(protocol=tcp)(host=node2-vip)(port=1521)))</pre> <p>The instance uses this list to determine the addresses of the remote listeners with which to register its information.</p>
Nondefault listeners	<p>As discussed in "Local Listeners" on page 9-5 and "Multiple Listeners" on page 9-5, the <code>LOCAL_LISTENER</code> parameter is set in the <code>listener_sid.ora</code> file if a nondefault listener is configured, for example:</p> <pre>listener_sid.local_listener=listener_sid</pre> <p>Where <code>listener_sid</code> is resolved to a listener address through a naming method such as a <code>tnsnames.ora</code> file.</p> <p>In the following sample, <code>listener_db1.us.acme.com</code> is resolved to the nondefault listener address:</p> <pre>listener_db1.us.acme.com= (address=(protocol=tcp)(host=node1-vip)(port=1522))</pre>

Table 9–2 (Cont.) Connections for Net Service Names

Net Service Name Type	Description
Services Entries	<p>When you configure high availability services using the DBCA Services page, then DBCA creates net service entries similar to the following. The three services in the following examples, db_svc1, db_svc2, and db_svc3, have TAF policies of NONE, BASIC and PRECONNECT respectively.</p> <pre> db_svc1.us.acme.com= (description = (address=(protocol=tcp) (host=node1-vip) (port=1521)) (address=(protocol=tcp) (host=node2-vip) (port=1521)) (load_balance=yes) (connect_data= (server = dedicated) (service_name = db_svc1.us.acme.com)))) db_svc2.us.acme.com= (description= (address=(protocol=tcp) (host=node1-vip) (port=1521)) (address=(protocol=tcp) (host=node2-vip) (port=1521)) (load_balance=yes) (connect_data = (server = dedicated) (service_name=db_svc2.us.acme.com) (failover_mode = (type=select) (method=basic) (retries=180) (delay=5))))) db_svc3.us.acme.com= (description= (address=(protocol=tcp) (host=node1-vip) (port=1521)) (address=(protocol=tcp) (host=node2-vip) (port=1521)) (load_balance=yes) (connect_data= (server=dedicated) (service_name=db_svc3.us.acme.com) (failover_mode= (backup=db_svc3_preconnect.us.acme.com) (type=select) (method=preconnect) (retries=180) (delay=5))))) </pre>

Table 9–2 (Cont.) Connections for Net Service Names

Net Service Name Type	Description
Services Entries (continued)	<p>When a service has a TAF policy of PRECONNECT, then a <code>service_name_preconnect</code> net service entry is also created as in the following example:</p> <pre>db_svc3_preconnect.us.acme.com = (description = (address = (protocol = tcp) (host = node1-vip) (port = 1521)) (address = (protocol = tcp) (host = node2-vip) (port = 1521)) (load_balance = yes) (connect_data = (server = dedicated) (service_name = db_svc3_preconnect.us.amce.com) (failover_mode = (backup = db_svc3.us.acme.com) (type = select) (method = basic) (retries = 180) (delay = 5)))))</pre>
External procedures	<p>An entry for connections to external procedures. This enables an Oracle Database 10g database to connect to external procedures.</p> <pre>extproc_connection_data.us.acme.com= (description= (address_list= (address=(protocol=ipc) (key=extproc0))) (connect_data= (sid=plsextproc))))</pre>

Example 9–1 Example tnsnames.ora File

The following is a sample `tnsnames.ora` file that is created during a preconfigured database configuration installation:

```
db.us.acme.com=
  (description=
    (load_balance=on)
    (address=(protocol=tcp) (host=node1-vip) (port=1521))
    (address=(protocol=tcp) (host=node2-vip) (port=1521))
    (connect_data=
      (service_name=db.us.acme.com)))

db1.us.acme.com=
  (description=
    (address=(protocol=tcp) (host=node1-vip) (port=1521))
    (connect_data=
      (service_name=db.us.acme.com)
      (instance_name=db1)))

db2.us.acme.com=
  (description=
    (address=(protocol=tcp) (host=node2-vip) (port=1521))
    (connect_data=
      (service_name=db.us.acme.com)
      (instance_name=db2)))

listeners_db.us.acme.com=
  (address_list=
```



```

(address=(protocol=tcp) (host=node1-vip) (port=1521))
(address=(protocol=tcp) (host=node2-vip) (port=1521))

extproc_connection_data.us.acme.com=
(description=
(address_list=
(address=(protocol=ipc) (key=extproc)))
(connect_data=
(sid=plsextproc)
(presentation=R0)))

```

See Also: *Oracle Database Net Services Administrator's Guide* for further information about the `tnsnames.ora` file

Net Services Profile (sqlnet.ora File)

Oracle Universal Installer starts Oracle Net Configuration Assistant after the database is installed, and creates the Net Services profile, or `sqlnet.ora` file.

By default, the `sqlnet.ora` file is located in the following directory:

```
$ORACLE_HOME/network/admin
```

In this directory, in addition to the default `sqlnet.ora` file generated during installation, you also can find a sample `sqlnet.ora` file in the directory `sample`.

During installation, Oracle Net Configuration Assistant creates the following entries in the `sqlnet.ora` file:

```
NAMES.DIRECTORY_PATH=(TNSNAMES, EZCONNECT)
```

The parameter `NAMES.DIRECTORY_PATH` specifies the priority order of the naming methods to use to resolve connect identifiers to connect descriptors.

The order of naming methods is as follows: directory naming (for Custom Install or Advanced database configuration options only), `tnsnames.ora` file, Easy Connect, and host naming.

The Easy Connect naming method eliminates the need for service name lookup in the `tnsnames.ora` files for TCP/IP environments. With Easy Connect, clients use a connect string for a simple TCP/IP address, consisting of a host name and optional port and service name. If you use this method, then no naming or directory system is required.

See Also: *Oracle Database Net Services Administrator's Guide* for further information about the `sqlnet.ora` file

Part V

Oracle Clusterware and Oracle Real Application Clusters Installation and Configuration Reference Information

Part V provides Oracle Clusterware and Oracle Real Application Clusters (RAC) installation and configuration reference information. The contents of Part V are:

- [Appendix A, "Troubleshooting the Oracle Clusterware and Oracle Real Application Clusters Installation Process"](#)
- [Appendix B, "Using Scripts to Create Oracle Real Application Clusters Databases"](#)
- [Appendix C, "Configuring Raw Devices for Oracle Real Application Clusters"](#)
- [Appendix D, "Converting to Oracle Real Application Clusters from Single-Instance Oracle Databases"](#)
- [Appendix E, "Directory Structure for Oracle Database 10g Oracle Real Application Clusters Environments"](#)
- [Appendix F, "How to Stop Processes in an Existing Oracle Real Application Clusters Database"](#)

Troubleshooting the Oracle Clusterware and Oracle Real Application Clusters Installation Process

This appendix provides troubleshooting information for installing Oracle Clusterware and Oracle Database 10g Real Application Clusters (RAC). The topic in this appendix is:

- [Troubleshooting the Oracle Real Application Clusters Installation](#)

See Also: The Oracle Database 10g Oracle Real Application Clusters documentation set included with the installation media in the Documentation directory:

- *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*

Troubleshooting the Oracle Real Application Clusters Installation

This section contains these topics:

- [General Installation Issues](#)
- [Real Application Clusters Installation Error Messages](#)
- [Performing Cluster Diagnostics During Real Application Clusters Installations](#)

General Installation Issues

The following is a list of examples of types of errors that can occur during installation

An error occurred while trying to get the disks

Cause: There is an entry in `/etc/oratab` pointing to a non-existent Oracle home. The OUI error file should show the following error: "java.io.IOException: /home/oracle/OraHome//bin/kfod: not found" (Oracle*Metalink* bulletin 276454.1)

Action: Remove the entry in `/etc/oratab` pointing to a non-existing Oracle home.

Nodes unavailable for selection from the OUI Node Selection screen

Cause: Oracle Clusterware is either not installed, or the Oracle Clusterware services are not up and running.

Action: Install Oracle Clusterware, or review the status of your Oracle Clusterware. Consider restarting the nodes, as doing so may resolve the problem.

Node *nodename* is unreachable

Cause: Unavailable IP host

Action: Attempt the following:

1. Run the shell command `ifconfig -a`. Compare the output of this command with the contents of the `/etc/hosts` file to ensure that the node IP is listed.
2. Run the shell command `nslookup` to see if the host is reachable.
3. As Oracle, attempt to connect to the node with `ssh` or `rsh`. If you are prompted for a password, then user equivalence is not set up properly. Review the section "[Configuring SSH on Cluster Member Nodes](#)" on page 2-11.

Time stamp is in the future

Cause: One or more nodes has a different clock time than the local node. If this is the case, then you may see output similar to the following:

```
time stamp 2005-04-04 14:49:49 is 106 s in the future
```

Action: Ensure that all member nodes of the cluster have the same clock time

Real Application Clusters Installation Error Messages

Oracle Real Application Clusters Management Tools Error Messages are in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*.

Performing Cluster Diagnostics During Real Application Clusters Installations

If the Oracle Universal Installer (OUI) does not display the Node Selection page, then perform clusterware diagnostics by running the `olsnodes -v` command from the binary directory in your Oracle Clusterware home (`CRS_home/bin`) and analyzing its output. Refer to your clusterware documentation if the detailed output indicates that your clusterware is not running.

In addition, use the following command syntax to check the integrity of the Cluster Manager:

```
cluvfy comp clumgr -n node_list -verbose
```

In the preceding syntax example, the variable `node_list` is the list of nodes in your cluster, separated by commas.

Using Scripts to Create Oracle Real Application Clusters Databases

This chapter describes the steps required to create an Oracle Real Application Clusters (RAC) database using scripts to perform non-interactive installations. The topic in this appendix is:

- [Creating a Database Using Scripts](#)

Note: The scripts generated by DBCA are for reference purposes only. Oracle strongly recommends that you use DBCA to create a database.

See Also: *Oracle Universal Installer and OPatch User's Guide* for detailed information about generating scripts

Creating a Database Using Scripts

To generate scripts to create a Real Application Clusters database, create a database using the scripts, and prepare the database for use, complete the following steps:

1. Start Database Configuration Assistant (DBCA) and select your preferred options to build the RAC database. Note: you must select the Custom Database template on the Database Templates page for DBCA to provide the script generation option.

On the Creation Options page of your DBCA session, deselect Create Database and select Generate Database Creation Scripts before you click **Finish**. You can accept the default destination directory for the scripts, or browse for a different location. In either case, you should note the path name for use in the next step.

See Also: [Chapter 6, "Creating Real Application Clusters Databases with Database Configuration Assistant"](#) for additional information about running a DBCA session.

2. Navigate to the directory, which you noted in Step 1, where DBCA created the scripts, and review the SQL scripts to ensure that they contain the statements to build a database with the characteristics you require. If they do not, then Oracle recommends that you rerun DBCA to create scripts with the desired configuration rather than editing the scripts yourself.
3. On each cluster node you identified during your DBCA session, run the script `sid.sh`, where *sid* is the SID prefix that you entered on the DBCA Database Name page.

4. Set the initialization parameter, `cluster_database`, to the value `TRUE` in your SPFILE by issuing an `ALTER SYSTEM` command, or by uncommenting it in your PFILE for each instance.
5. Configure Net Services to support your new database and instances as described in [Chapter 9, "Understanding the Oracle Real Application Clusters Installed Configuration"](#).
6. Set the `local_listener` and `remote_listener` parameters in your SPFILE by issuing an `ALTER SYSTEM` command, or by uncommenting it in your PFILE for each instance.
7. Run SRVCTL to configure and start database and instance applications as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*.

See Also: *Oracle Universal Installer and OPatch User's Guide* for additional information about creating and using scripts to install Oracle software

Configuring Raw Devices for Oracle Real Application Clusters

This appendix provides additional information about configuring raw devices to deploy Real Application Clusters (RAC) using Database Configuration Assistant (DBCA). You must configure raw devices if you do not use Automatic Storage Management (ASM), or a cluster file system. The topic in this appendix is:

- [Raw Devices Required by DBCA for Non-Cluster Environments](#)

Raw Devices Required by DBCA for Non-Cluster Environments

If you want to use DBCA to create a database on raw storage and not use General Parallel File System (GPFS), then configure the raw devices, as described in this section. These devices are in addition to the Oracle Cluster Registry (OCR) and voting disk required to install Oracle Clusterware. Create these devices before running Oracle Universal Installer (OUI) to install the Oracle Database 10g software. DBCA cannot create a RAC database unless you have properly configured the following devices:

- Four raw devices for four tablespace data files
- At least two raw devices for control files
- One raw device for each instance for its own tablespace for automatic undo management
- At least two raw devices for redo log files for each instance
- One raw device for the server parameter file

Note: Each instance has its own redo log files, but all instances in a cluster share the control files and data files. In addition, each instance's online redo log files must be readable by all other instances to enable recovery.

Planning Your Raw Device Creation Strategy

Before installing the Oracle Database 10g software with Oracle Real Application Clusters, create enough partitions of specific sizes to support your database, and also leave a few spare partitions of the same size for future expansion. For example, if you have space on your shared disk array, then select a limited set of standard partition sizes for your entire database. Partition sizes of 50MB, 100MB, 500MB, and 1GB are suitable for most databases. Also create a few very small and a few very large spare partitions that are, for example, 1MB and perhaps 5GB or greater in size. Based on your plans for using each partition, determine the placement of these spare partitions

by combining different sizes on one disk, or by segmenting each disk into same-sized partitions.

Note: Ensure that there are spare partitions enables you to perform emergency file relocations or additions if a tablespace data file becomes full.

Converting to Oracle Real Application Clusters from Single-Instance Oracle Databases

This chapter describes the procedures for converting from Oracle Database 10g single-instance databases to Real Application Clusters (RAC) databases. The topics in this appendix are:

- [Single-Instance to Cluster-Enabled Conversion Administrative Issues](#)
- [Converting with DBCA](#)
- [Converting with rconfig and Oracle Enterprise Manager](#)
- [Post-Conversion Steps](#)

If you are upgrading from Oracle Parallel Server to RAC or from an earlier version of RAC, then use the Database Upgrade Assistant (DBUA). In other words, the procedures in this chapter assume that your original single-instance database and the target RAC database are the same version of Oracle 10g, and running on the same platform.

Note: You must use clustered ASM instances for RAC databases.

See Also: You must comply with the restrictions of the license you have purchased. To understand the restrictions of your license, please refer to the *Database Licensing Information* manual.

Single-Instance to Cluster-Enabled Conversion Administrative Issues

Note the following administrative considerations before conversion:

- Backup procedures should be available before converting from a single-instance Oracle database to RAC.
- Additional archiving considerations apply in RAC environments. In particular, the archive file format requires a thread number. In addition, the archived logs from all instances of a RAC database are required for media recovery. If you archive to a file and you do not use a cluster file system, then a method of accessing the archive logs from all nodes on which the cluster database has instances is required where file systems are not shared.

Converting with DBCA

You can use Database Configuration Assistant to convert from single-instance Oracle databases to RAC. DBCA automates the configuration of the control file attributes, creates the undo tablespaces and the redo logs, and makes the initialization parameter file entries for cluster-enabled environments. It also configures the Oracle Net Services, Oracle Clusterware resources, and the configuration for RAC database management for use by Oracle Enterprise Manager or the SRVCTL utility.

Before you use DBCA to convert a single-instance database to a RAC database, ensure that the following conditions are met:

- A supported hardware and operating system software configuration
- Shared storage, either Oracle Cluster File System or ASM, is available and accessible from all nodes
- Your application has no design characteristics that preclude its use with cluster database processing

If your platform supports a cluster file system, then you can use it for RAC. You can also convert to RAC and use a non-shared file system. In either case, Oracle strongly recommends that you use Oracle Universal Installer (OUI) to perform an Oracle Database 10g installation that sets up the Oracle home and inventory in an identical location on each of the selected nodes in your cluster.

This section describes the following scenarios:

- [Single Instance on a Non-Cluster Computer to Oracle Database 10g with RAC](#)
- [Single Instance on a Cluster to Oracle Database 10g RAC](#)

Single Instance on a Non-Cluster Computer to Oracle Database 10g with RAC

To convert from a single-instance Oracle database that is on a non-cluster computer to RAC, perform the procedures described under the following headings in the order shown:

- [Back Up the Original Single-Instance Database](#)
- [Perform the Pre-Installation Steps](#)
- [Set Up the Cluster](#)
- [Validate the Cluster](#)
- [Copy the Preconfigured Database Image](#)
- [Install Oracle Database 10g Software with Real Application Clusters](#)

Back Up the Original Single-Instance Database

Use DBCA to create a preconfigured image of your single-instance database by using the following procedure:

1. Navigate to the bin directory in ORACLE_HOME, and start DBCA.
2. At the Welcome page, click **Next**.
3. On the Operations page, select **Manage Templates**, and click **Next**.
4. On the Template Management page, select **Create a database template** and **From an existing database (structure as well as data)**, and click **Next**.

5. On the Source Database page, enter the database name in the **Database instance** field, and click **Next**.
6. On the Template Properties page, enter a name for your template in the **Name** field. Oracle recommends that you use the database name.

By default, the template files are generated in the directory `ORACLE_HOME/assistants/dbca/templates`. If you choose to do so, you can enter a description of the file in the **Description** field, and change the template file location in the **Template data file** field.

When you have completed entries, click **Next**.

7. On the Location of Database Related Files page, select **Maintain the file locations**, so that you can restore the database to the current directory structure, and click **Finish**.

DBCA generates two files: a database structure file (`template_name.dbc`), and a database preconfigured image file (`template_name.dfb`).

Perform the Pre-Installation Steps

Perform the pre-installation steps as documented in [Part II](#) of this book. Then set up shared storage by referring to the "Configure Disk Storage for Oracle Database and Recovery Files" sections in the pre-installation chapters in [Part II](#).

See Also: Storage vendor-specific documentation for setting up the shared disk subsystem and for information about how to mirror and stripe disks

Set Up the Cluster

To use vendor clusterware, form a cluster with the required number of nodes according to your hardware vendor's documentation. When you have configured all of the nodes in your cluster, either with or without vendor clusterware, then install Oracle Clusterware and validate cluster components by referring to the procedures in [Chapter 4, "Installing Oracle Clusterware"](#).

Validate the Cluster

Validate the cluster configuration using the Cluster Verification Utility, as described in [Chapter 5, "Installing Oracle Database 10g with Real Application Clusters"](#).

Copy the Preconfigured Database Image

Copy the preconfigured database image. This includes copying the database structure `*.dbc` file and the database preconfigured image `*.dfb` file that DBCA created in the previous procedure "[Back Up the Original Single-Instance Database](#)" on page D-2 to a temporary location on the node in the cluster from which you plan to run DBCA.

Install Oracle Database 10g Software with Real Application Clusters

1. Run the Oracle Universal Installer (OUI) to perform an Oracle installation with the Oracle 10g Database with RAC.
2. Select Cluster Installation Mode on the Specify Hardware Cluster Installation page of the Oracle Universal Installer (OUI) and select the nodes to include in your RAC database.
3. On the OUI Database Configuration Types page, select the Advanced install type.

After installing the Oracle software, OUI runs post-installation configuration tools, such as the Network Configuration Assistant (NetCA), DBCA, and so on.

4. On the DBCA Template Selection page, use the template that you copied to a temporary location in the ["Copy the Preconfigured Database Image"](#) procedure. Use the browse option to select the template location.
5. If you selected raw storage on the OUI Storage Options page, then on the DBCA File Locations Tab on the Initialization Parameters page, replace the data files, control files, and log files, and so on, with the corresponding raw device files if you have not setup the `DBCA_RAW_CONFIG` environment variable. You must also replace default database files with raw devices on the Storage page.

See Also: [Chapter 6](#) for more details about DBCA

6. After creating the RAC database, DBCA displays the Password Management page on which you must change the passwords for database privileged users who have `SYSDBA` and `SYSOPER` roles. When DBCA exits, the conversion process is complete.

Single Instance on a Cluster to Oracle Database 10g RAC

There are three scenarios in which a single-instance database can exist on a cluster computer:

- Scenario 1: The Oracle home from which the single-instance database is running is cluster-installed. The steps to perform a conversion to RAC in this scenario are described in ["Single Instance on a Cluster Running from a Cluster-Enabled Oracle Home"](#) on page D-4.
- Scenario 2: The Oracle home from which the single-instance database is running is cluster-installed, but the RAC feature is disabled. Refer to ["Single Instance on a Cluster Running from a RAC-Disabled Oracle Home"](#) on page D-7 for instructions on how to convert the database to RAC in this environment.
- Scenario 3: The Oracle home from which the single-instance database is running is not cluster-installed. The procedure to convert the single-instance database to RAC in this scenario is described in ["Single Instance on a Cluster Running from a Single-Instance Installed Oracle Home"](#) on page D-7.

Use the following procedures to convert your single-instance database on a cluster computer to RAC for all of these scenarios.

Single Instance on a Cluster Running from a Cluster-Enabled Oracle Home

Perform the following procedures to convert a single-instance database on a cluster running from a cluster-installed (Oracle Database 10g with RAC) Oracle home.

1. Use DBCA to create a preconfigured image of your single-instance database as described under the heading ["Back Up the Original Single-Instance Database"](#) on page D-2. To perform the conversion manually, shut down the single-instance database.
2. To add nodes to your cluster, add and connect these nodes to the cluster as described under the heading ["Perform the Pre-Installation Steps"](#) on page D-3. Ensure that all of these nodes can access the shared storage. Also extend the Oracle Clusterware home to the new nodes using the procedures for ["Extending Clusterware and Oracle Software to New Nodes"](#) as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*.

3. From the existing Oracle home, extend this home to the new nodes using the procedure "Adding Nodes at the Oracle RAC Database Layer" as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*.
4. From one of the newly added nodes, configure the listeners on the additional nodes using the NetCA. Choose the same port number and protocol that you used on the existing node. If the NetCA displays the existing node in the node list page, then do not select this node, because the listener is already configured on it.
5. Convert the database using one of the following procedures:
 - [Automated Conversion Procedure](#)
 - [Manual Conversion Procedure](#)

Automated Conversion Procedure 1.If you created the preconfigured image of the single instance database as described under the heading "[Back Up the Original Single-Instance Database](#)" on page D-2, then use DBCA to complete the conversion to a RAC database.

2. Start DBCA from the initial node. Select the names of the nodes that you want to include as part of your cluster database. On the Template Selection page, select the preconfigured template that you created in Step 1 on page D-4. Enter the database name and respond to the remaining DBCA prompts.
3. To use raw devices for the cluster database files: When the Initialization Parameters page appears, enter the raw device name for the SPFILE on the File Locations tab. On the Storage page, replace the default database file names with the raw devices for the control files, redo logs, and data files to create the cluster database. Click **Finish**, and create the database.

After creating the RAC database, DBCA displays the Password Management page on which you must change the passwords for the database privileged users who have SYSDBA and SYSOPER roles. When DBCA exits, the conversion process is complete.

Manual Conversion Procedure Because you did not use DBCA to create a preconfigured image of your single-instance database in Step 1 on page D-4, perform the following steps to complete the conversion:

1. Create the OFA directory structure on each of the nodes that you have added.

See Also: "[Directory Structures for Real Application Clusters](#)" on page E-1 for more information about OFA.

2. If you are converting single-instance database files on a file system to raw devices, then copy the database data files, control files, redo logs, and server parameter file to their corresponding raw devices using the `dd` command. Otherwise, continue to the next step.
3. Re-create the control files by running the `CREATE CONTROLFILE SQL` statement with the `REUSE` keyword and specify `MAXINSTANCES` and `MAXLOGFILES`, and so on, as needed for your RAC configuration. The `MAXINSTANCES` recommended default is 32.
4. Shut down the database instance.
5. If your single-instance database was using an SPFILE parameter file, then create a temporary PFILE from the SPFILE using the following SQL statement:

```
CREATE PFILE='pfile_name' from spfile='spfile_name'
```

6. Set the `CLUSTER_DATABASE` parameter to `TRUE`, set the `INSTANCE_NUMBER` parameter to a unique value for each instance, using a `sid.parameter=value` syntax.

If you optimized memory usage on your single-instance database, then adjust the size of the SGA to avoid swapping and paging when you convert to RAC. you should make this adjustment because RAC requires about 350 bytes for each buffer to accommodate the Global Cache Service (GCS). For example, if you have 10,000 buffers, then RAC requires about 350*10,000 bytes more memory. Therefore, adjust the size of the SGA by changing the `DB_CACHE_SIZE` and `DB_nK_CACHE_SIZE` parameters accordingly.

7. Start up the database instance using the PFILE created in step 5.
8. If your single-instance database was using automatic undo management, then create an undo tablespace for each additional instance using the `CREATE UNDO TABLESPACE SQL` statement. If you are using raw devices, then ensure that the data file for the undo tablespace is on the raw device.
9. Create redo threads that have at least two redo logs for each additional instance. If you are using raw devices, then ensure that the redo log files are on raw devices. Enable the new redo threads by using an `ALTER DATABASE SQL` statement. Then shutdown the database instance.
10. Copy the Oracle password file from the initial node, or from the node from which you are working, to the corresponding location on the additional nodes on which the cluster database will have an instance. Make sure that you replace the `ORACLE_SID` name in each password file appropriately for each additional instance.
11. Add `REMOTE_LISTENER=LISTENERS_DB_NAME` and `sid.LOCAL_LISTENER=LISTENER_SID` parameters to the PFILE.
12. Configure the net service entries for the database and instances and address entries for the `LOCAL_LISTENER` for each instance and `REMOTE_LISTENER` in the `tnsnames.ora` file and copy it to all nodes.
13. Create the SPFILE from the PFILE using the procedures under the heading "[Procedures for Migrating to the Server Parameter File](#)" on page 8-3. If you are not using a cluster file system, then ensure that the SPFILE is on a raw device.
14. Create the `$ORACLE_HOME/dbs/initsid.ora` file that contains the following entry:


```
spfile='spfile_path_name'
```

where `spfile_path_name` is the complete path name of the SPFILE.
15. Add the configuration for the RAC database and its instance-to-node mapping using `SRVCTL`.
16. Start the RAC database using `SRVCTL`.

After starting the database with `SRVCTL`, your conversion process is complete and, for example, you can run the following SQL statement to see the statuses of all the instances in your RAC database:

```
select * from v$instance
```


Single Instance on a Cluster Running from a RAC-Disabled Oracle Home

You can install a single instance on a cluster running from a RAC-disabled Oracle home if you performed a one-node cluster (with RAC) installation, but later disabled the RAC feature by unlinking it from the `oracle` binary before creating the single instance database. (However, you can also select the "local", "non-cluster" selection on the Node Selection Page to create a non-RAC-enabled single-instance home on a cluster.) Perform the following procedures to convert this type of single-instance database to a RAC database:

1. Use DBCA to create a preconfigured image of your single-instance database as described under the heading "[Back Up the Original Single-Instance Database](#)" on page D-2. To perform the conversion manually, shut down the single-instance database.
2. Change the directory to the `lib` subdirectory in the `rdbms` directory under the Oracle home.
3. Relink the `oracle` binary by running the following commands:

```
make -f ins_rdbms.mk rac_on
make -f ins_rdbms.mk ioracle
```

4. Continue with Step 2 on page D-4.

Single Instance on a Cluster Running from a Single-Instance Installed Oracle Home

You can only install a single instance on a cluster running from a single-instance installed Oracle home if you selected the local installation option on the OUI Specify Hardware Cluster Installation page during the single-instance Oracle Database 10g installation.

To convert this type of database to a RAC database, perform the procedures described under the following headings:

1. "[Back Up the Original Single-Instance Database](#)" on page D-2.
2. "[Perform the Pre-Installation Steps](#)" on page D-3.
3. "[Set Up the Cluster](#)" on page D-3.
4. "[Install Oracle Database 10g Software with Real Application Clusters](#)". In this step, make sure that you select a new Oracle home other than the one from which the single-instance database was running.

Converting with rconfig and Oracle Enterprise Manager

You can use `rconfig`, or Oracle Enterprise Manager to assist you with the task of converting a single-instance database installation to a RAC database. The first of these, `rconfig`, is a command line utility. Oracle Enterprise Manager Grid Control database administration option, Convert to Cluster Database, provides a GUI conversion tool. The following sections describe how to use these conversion tools:

- [Prerequisites for Converting to RAC Databases](#)
- [Single-Instance to RAC Conversion Scenarios](#)
- [Converting Single-Instance Databases to RAC Using rconfig](#)
- [Example of an rconfig XML Input File](#)
- [Converting Single-Instance Databases to RAC Using Oracle Enterprise Manager](#)
- [Converting Single-Instance ASM to Cluster ASM](#)

Note: Before you start the conversion, as is always true before you start any major change to your database, always back up your existing database.

Prerequisites for Converting to RAC Databases

Before you convert a single-instance database to a RAC database, ensure that the following conditions are met for each cluster node that you intend to make a RAC database node:

- Oracle Clusterware 10g Release 2 (10.2) is installed, configured, and running
- Oracle Real Application Clusters 10g Release 2 (10.2) software is installed
- The Oracle binary is enabled for RAC
- Shared storage, either Oracle Cluster File System or ASM, is available and accessible from all nodes
- User equivalence exists for the oracle user
- If you intend to use Oracle Enterprise Manager, then all Enterprise Manager agents are configured and running, and are configured with cluster and host information

Note: You must use clustered ASM instances for RAC databases. If your single-instance database uses ASM Storage, then before you use `rconfig` to convert the Oracle Database with RAC, convert your ASM installation to a cluster-enabled ASM as described in "[Converting Single-Instance ASM to Cluster ASM](#)" on page D-12.

Single-Instance to RAC Conversion Scenarios

The following is a list of scenarios for converting a single-instance Oracle database to an Oracle Real Application Clusters (RAC) database:

- Converting a single-instance Oracle Database 10g Release 2 (10.2) to an Oracle 10g Release 2 (10.2) RAC database, running out of the *same* Oracle home and using the same data files as the single-instance database

In this scenario, either use the `rconfig` utility, or use the **Convert to RAC** option on the single-instance database target of Oracle Enterprise Manager Grid Control.

- Converting a single-instance Oracle Database version previous to Oracle Database 10g Release 2 (10.2), running out of the same Oracle home and using the same data files as the single-instance database

In this scenario, use OUI and Database Upgrade Assistant (DBUA) to update the single-instance database to Oracle Database 10g Release 2 (10.2). Then use `rconfig` or the Enterprise Manager **Convert to RAC** option, as described in the preceding scenario.

- Converting a single-instance Oracle Database 10g Release 2 (10.2) to an Oracle 10g Release 2 (10.2) RAC database, running out of a *different* Oracle home and using the same data files as the single-instance database.

In this scenario, either use the `rconfig` utility in the source database home (the database that you are converting), or use the **Convert to RAC** option in the

single-instance database target of Oracle Enterprise Manager Grid Control. Provide the file storage location when prompted.

- Converting a single-instance Oracle Database 10g Release 2 (10.2) to an 10g Release 2 (10.2) RAC database, running out of a *different* Oracle home, and where the host where the single-instance database is running is *not* one of the nodes of the RAC database

In this scenario, create a clone image of the single-instance database, and move the clone image to a host that is one of the nodes of the cluster. Then use `rconfig` or the Enterprise Manager **Convert to RAC** option, as described in the preceding scenario.

Converting Single-Instance Databases to RAC Using rconfig

You can use the command line utility `rconfig` to convert a single-instance database to RAC. To use this feature, complete the following steps:

See Also: *Oracle Database Upgrade Guide* for information about upgrading existing Oracle Database installations

1. As the Oracle user, navigate to the directory `$ORACLE_HOME/assistants/rconfig/sampleXMLs`, and open the file `ConvertToRAC.xml` using a text editor, such as `vi`.
2. Review the `ConvertToRAC.xml` file, and modify the parameters as required for your system. The XML sample file contains comment lines that provide instructions for how to configure the file.

When you have completed making changes, save the file with the syntax `filename.xml`. Make a note of the name you select.

3. Navigate to the directory `$ORACLE_HOME/bin`, and use the following syntax to run the command `rconfig`:

```
rconfig input.xml
```

where `input.xml` is the name of the XML input file you configured in step 2.

For example if you create an input XML file called `convert.xml`, then enter the following command

```
$ ./rconfig convert.xml
```

Note: The `Convert verify` option in the `ConvertToRAC.xml` file has three options:

- `Convert verify="YES"`: `rconfig` performs checks to ensure that the prerequisites for single-instance to RAC conversion have been met before it starts conversion
 - `Convert verify="NO"`: `rconfig` does not perform prerequisite checks, and starts conversion
 - `Convert verify="ONLY"`: `rconfig` only performs prerequisite checks; it does not start conversion after completing prerequisite checks
-

Example of an rconfig XML Input File

The following is an example of an XML input file for the rconfig utility. In the example, the XML input file is for converting a single-instance database with ASM to a RAC database with ASM in the same Oracle home.

```
<n:RConfig xsi:schemaLocation="http://www.oracle.com/rconfig">
-
<n:ConvertToRAC>
-
<!--
  Verify does a precheck to ensure all pre-requisites are met, before the
  conversion is attempted. Allowable values are: YES|NO|ONLY
-->
-
<n:Convert verify="YES">
-
<!--
Specify current OracleHome of non-rac database for SourceDBHome
-->
<n:SourceDBHome>/oracle/product/10.2.0/db_1</n:SourceDBHome>
-
<!--
Specify OracleHome where the rac database should be configured. It can be same as
SourceDBHome
-->
<n:TargetDBHome>/oracle/product/10.2.0/db_1</n:TargetDBHome>
-
<!--
Specify SID of non-rac database and credential. User with sysdba role is required
to perform conversion
-->
-
<n:SourceDBInfo SID="sales">
-
<n:Credentials>
<n:User>sys</n:User>
<n>Password>oracle</n>Password>
<n:Role>sysdba</n:Role>
</n:Credentials>
</n:SourceDBInfo>
-
<!--
ASMInfo element is required only if the current non-rac database uses ASM Storage
-->
-
<n:ASMInfo SID="+ASM1">
-
<n:Credentials>
<n:User>sys</n:User>
<n>Password>welcome</n>Password>
<n:Role>sysdba</n:Role>
</n:Credentials>
</n:ASMInfo>
-
<!--
Specify the list of nodes that should have rac instances running. LocalNode should
be the first node in this nodelist.
-->
-
<n:NodeList>
```

```

<n:Node name="node1"/>
<n:Node name="node2"/>
</n:NodeList>
-
<!--
Specify prefix for rac instances. It can be same as the instance name for non-rac
database or different. The instance number will be attached to this prefix.
-->
<n:InstancePrefix>sales</n:InstancePrefix>
-
<!--
Specify port for the listener to be configured for rac database.If port="",
alistener existing on localhost will be used for rac database.The listener will be
extended to all nodes in the nodelist
-->
<n:Listener port="1551"/>
-
<!--
Specify the type of storage to be used by rac database. Allowable values are
CFS|ASM. The non-rac database should have same storage type.
-->
-
<n:SharedStorage type="ASM">
-
<!--
Specify Database Area Location to be configured for rac database.If this field is
left empty, current storage will be used for rac database. For CFS, this field
will have directory path.
-->
<n:TargetDatabaseArea>+ASMDG</n:TargetDatabaseArea>
-
<!--
Specify Flash Recovery Area to be configured for rac database. If this field is
left empty, current recovery area of non-rac database will be configured for rac
database. If current database is not using recovery Area, the resulting rac
database will not have a recovery area.
-->
<n:TargetFlashRecoveryArea>+ASMDG</n:TargetFlashRecoveryArea>
</n:SharedStorage>
</n:Convert>
</n:ConvertToRAC>
</n:RConfig>
    
```

Converting Single-Instance Databases to RAC Using Oracle Enterprise Manager

You can use Oracle Enterprise Manager Grid Control to convert a single-instance database to RAC. To use this feature, complete the following steps:

See Also: *Oracle Database Upgrade Guide* for information about upgrading existing Oracle Database installations

1. Log in to Grid Control. From the Grid Control Home page, click the **Targets** tab.
2. On the Targets page, click the **Databases** secondary tab, and click the link in the Names column of the database that you want to convert to RAC.
3. On the Database Instance Home page, click the **Administration** secondary tab.

4. On the Administration page, in the Database Administration Change Database section, click **Convert to Cluster Database**.
5. Log in as the database user SYS with SYSDBA privileges to the database you want to convert, and click **Next**.
6. On the Convert to Cluster Database: Cluster Credentials page, provide a user name and password for the Oracle user and password of the target database that you want to convert. If the target database is using ASM, then also provide the ASM SYS user and password, and click **Next**.
7. On the Hosts screen, select the host nodes in the cluster that you want to be cluster members in the RAC database installed. When you have completed your selection, click **Next**.
8. On the Convert to Database: Options page, select whether you want to use the existing listener and port number, or specify a new listener and port number for the cluster. Also provide a prefix for cluster database instances on the cluster.
When you have finished entering information, click **Next**, or click **Help** if you need assistance in deciding how to enter information.
9. On the Convert to Cluster Database: Shared Storage page, either select the option to use your existing shared storage area, or select the option to have your database files copied to a new shared storage location. Also, decide if you want to use your existing Flash Recovery area, or if you want to copy your Flash Recovery files to a new Flash Recovery area using Oracle-Managed Files.
When you have finished entering information, click **Next**, or click **Help** if you need assistance in deciding how to enter information.
10. On the Convert to Cluster Database: Review page, review the options you have selected. Click **Submit Job** if you want to proceed to conversion. If you want to change options you have selected, click **Back**. To cancel the conversion, click **Cancel**.
11. On the Confirmation page, click View Job to check the status of the conversion.

Converting Single-Instance ASM to Cluster ASM

To convert a single-instance node using ASM to a RAC node using ASM:

1. Shut down the database instance, the ASM instance, and the listener.
2. Follow the instructions in [Chapter 2](#) and [Chapter 3](#) to configure each node that you want to have as a cluster member.
3. If any cluster member node has had previous versions of Oracle clusterware (Cluster Ready Services or Oracle Clusterware) installed, then ensure that you remove the file `ocr.loc` on any node that has been labeled previously as a cluster node. The file `ocr.loc` is in `/etc/oracle`.
4. log in as the Oracle user, and run DBCA in silent mode to deconfigure ASM. To run DBCA in silent mode, navigate to the directory `$ORACLE_HOME/bin` and use the following command syntax on the local node:

```
dbca -silent -deleteASM
```

You can de-install the single-instance ASM without losing data.

5. Install Oracle Clusterware on all nodes you intend to have as cluster members, following the directions in [Chapter 4](#).

6. Install Cluster ASM using DBCA. At the Node Selection page, select all the cluster member nodes for which you intend to use ASM to manage storage. When the ASM Disk Groups page prompts you to select disk groups, select the existing disk groups you used with the single-instance ASM instance that you deleted in step 4.
7. Start up the single-instance Oracle Database.

Post-Conversion Steps

After completing the conversion, note the following recommendations for RAC environments, as described in the RAC documentation:

- Follow the recommendations for using load balancing and transparent application failover, as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*
- Use locally managed tablespaces instead of dictionary managed tablespaces to reduce contention and manage sequences in RAC as described in *Oracle Real Application Clusters Deployment and Performance Guide*
- Follow the guidelines for configuring an interconnect, for using automatic segment space management and for using SRVCTL to administer multiple instances, as described in *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide*

The buffer cache and shared pool capacity requirements in RAC are slightly greater than the requirements for single-instance Oracle databases. Therefore, you should increase the size of the buffer cache by about 10%, and the size of the shared pool by about 15%.

Directory Structure for Oracle Database 10g Oracle Real Application Clusters Environments

This appendix describes the directory structures for Real Application Clusters (RAC) software environments. The topics in this appendix are:

- [Understanding the Real Application Clusters Directory Structure](#)
- [Directory Structures for Real Application Clusters](#)

Understanding the Real Application Clusters Directory Structure

When you install Oracle Database 10g with RAC, all subdirectories are under a top-level ORACLE_BASE directory. The ORACLE_HOME and admin directories are also located under ORACLE_BASE.

See Also: *Oracle Database Oracle Clusterware and Oracle Real Application Clusters Administration and Deployment Guide* for further information about the \$ORACLE_HOME and /admin directories

Directory Structures for Real Application Clusters

[Table E-1](#) shows the hierarchical directory tree of a sample OFA-compliant database for RAC:

Table E-1 Directory Structure for A Sample OFA-Compliant Environment

Root	Second-Level	Third-Level	Fourth-Level	Description
\$ORACLE_BASE				/u01/app/oracle The default ORACLE_BASE directory.
	ORACLE_HOME			/product/10.2.0 The default name of the Oracle home.
	/admin			Administrative directory.
		/db_unique_name		Database unique name, the same as dbname when database name is eight or fewer characters in length.

Table E-1 (Cont.) Directory Structure for A Sample OFA-Compliant Environment

Root	Second-Level	Third-Level	Fourth-Level	Description
			/bdump /cdump /hdump /pfile /udump	Dump destinations for database server.
<code>\$CRS_home</code>				/u01/crs/oracle/product/10.2.0/app The default name of the Oracle Clusterware home. After you install the software, you must change the permissions of all of the parent directories of the Oracle Clusterware home directory to grant write access only to the root user. Because of this, the Oracle Clusterware home directory must not be a subdirectory of the 10g Release 2 (10.2) Oracle base directory.
		/bin		Subtree for Oracle binaries.
		/network		Subtree for Oracle Net.

See Also: *Oracle Database Administrator's Reference 10g Release 2 (10.2)* for further information about the `$ORACLE_HOME` and `/admin` directories

How to Stop Processes in an Existing Oracle Real Application Clusters Database

This appendix describes how to stop all processes in an Oracle Real Application Clusters (RAC) database, in preparation for adding additional products to an existing database, or in preparation for patch updates. The topics in this appendix are:

- [Back Up the Oracle Real Application Clusters Database](#)
- [Shut Down Oracle Real Application Clusters Databases](#)
- [Stop All Oracle Processes](#)

Back Up the Oracle Real Application Clusters Database

Before you make any changes to the Oracle software, Oracle recommends that you create a backup of the Oracle Database 10g installation.

Shut Down Oracle Real Application Clusters Databases

Shut down any existing Oracle Database instances on each node, with normal or immediate priority.

If Automatic Storage Management (ASM) is running, shut down all databases that use ASM, and then shut down the ASM instance on each node of the cluster.

Note: If you are using Oracle Clusterware or Cluster Ready Services, then you must shut down all Oracle Database instances on all cluster nodes before modifying the Oracle software. If you are performing a patch update, review the instructions in the Patch Set Notes for detailed instructions.

Stop All Oracle Processes

Stop all listener and other processes running in the Oracle home directories where you want to modify the database software.

Note: If you shut down ASM instances, then you must first shut down all database instances that use ASM, even if these databases run from different Oracle homes.

Stopping Oracle Clusterware or Cluster Ready Services Processes

If you are modifying an Oracle Clusterware or Oracle Cluster Ready Services (CRS) installation, shut down the following Oracle Database 10g services.

Note: You must perform these steps in the order listed.

1. Shut down any processes in the Oracle home on each node that might be accessing a database; for example, Oracle Enterprise Manager Database Control.

Note: Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.

2. Shut down all RAC instances on all nodes. To shut down all RAC instances for a database, enter the following command, where *db_name* is the name of the database:

```
$ oracle_home/bin/srvctl stop database -d db_name
```

3. Shut down all ASM instances on all nodes. To shut down an ASM instance, enter the following command, where *node* is the name of the node where the ASM instance is running:

```
$ oracle_home/bin/srvctl stop asm -n node
```

4. Stop all node applications on all nodes. To stop node applications running on a node, enter the following command, where *node* is the name of the node where the applications are running

```
$ oracle_home/bin/srvctl stop nodeapps -n node
```

5. Shut down the Oracle Clusterware or CRS process by entering the following command on all nodes as the root user

```
# /etc/init.d/init.crs stop
```

Note: If the Oracle Clusterware or CRS installation is not on a shared Oracle home, then you can upgrade the Oracle Clusterware or CRS installation one node at a time. To do this, perform the preceding steps only on the first node that you are upgrading, and then follow the instructions on the Installer screen.

Stopping Oracle Database 10g Processes Before Adding Products or Upgrading

This section provides an overview of what needs to be done before adding additional products to Oracle Database 10g Release 2 (10.2). If you are performing a patch upgrade, then refer to the Database Patch Set Notes for the patch for additional instructions.

If node applications are running in the RAC Oracle home, then shut down the following Oracle Database 10g services before modifying the Oracle Database software:

Note: You must perform these steps in the order listed.

1. Shut down any processes in the Oracle home on each node that can access a database; for example, Oracle Enterprise Manager Database Control.

Note: Before you shut down any processes that are monitored by Enterprise Manager Grid Control, set a blackout in Grid Control for the processes that you intend to shut down. This is necessary so that the availability records for these processes indicate that the shutdown was planned downtime, rather than an unplanned system outage.

2. Shut down all RAC instances on all nodes. To shut down all RAC instances for a database, enter the following command, where *db_name* is the name of the database:

```
$ oracle_home/bin/srvctl stop database -d db_name
```

3. Shut down all ASM instances on all nodes. To shut down an ASM instance, enter the following command, where *node* is the name of the node where the ASM instance is running:

```
$ oracle_home/bin/srvctl stop asm -n node
```

4. Stop all node applications on all nodes. To stop node applications running on a node, enter the following command, where *node* is the name of the node where the applications are running:

```
$ oracle_home/bin/srvctl stop nodeapps -n node
```

Index

A

activating volume groups, 3-15, 3-34
Additional Real Application Clusters
 documentation, 1-1
Advanced
 configuration type, 5-4, 5-5
AIX
 character raw device names, 3-22
 checking disk availability for ASM, 3-20
 configuring disks for ASM, 3-19
 configuring new disks, 3-20
 identifying disks for ASM, 3-20
 identifying LVM disks, 3-20
 initializing disks for LVM, 3-20
 raw device sizes, 3-7
APAR
 download location, 2-27
APAR download location, 2-27
API libraries
 for Oracle Clusterware, xxi
architecture
 checking system architecture, 2-21
 Optimal Flexible Architecture (OFA), 5-5
archive logs
 destinations, converting to cluster database, D-1
ASM
 and OFA, xxi
 benefits of, 1-9
 changing owner and permissions of disks
 on AIX, 3-22
 character raw device names on AIX, 3-22
 characteristics of failure groups, 1-9, 3-17
 checking disk availability on AIX, 3-20
 compared to logical volume managers, 1-9
 compared to RAID, 1-9
 configuring disks
 on AIX, 3-19
 database recovery area for, 1-10
 disk groups, 1-9, 3-16
 failure groups, 1-9, 3-16
 examples, 3-18
 identifying, 3-18
 identifying available disks on AIX, 3-20
 identifying disks on AIX, 3-20
 overview, 1-8

 recommendations for disk groups, 1-9, 3-16
 redundancy levels, 1-9
 restrictions on use for OCR or voting disk, 3-15
 space required for preconfigured database, 3-17
ASM only installation, 1-10
Automatic Storage Management
 storage option for data files, 3-2
automatic undo management, 9-3
Available
 service configuration policy, 6-2

B

background process
 crsd, 4-9
 evmd, 4-9
 ocssd, 4-9
 oproc, 4-9
backups
 and converting to cluster database, D-1
base directory
 See Oracle base directory
Bash shell
 default user startup file, 2-18
.bash_profile file, 2-18
Basic
 TAF failover policy, 6-3
Bourne shell
 default user startup file, 2-18

C

C compiler
 requirement, 2-25
 See also Pro*C/C++
C shell
 default user startup file, 2-18
cfgmgr command, 3-12, 3-20, 3-29
character raw device
 device name on AIX, 3-22
chdev command, 3-12, 3-20, 3-29
checking disk availability for raw devices, 3-11, 3-29
checking existence of the nobody user, 2-9
checking maintenance level, 2-25
checking version, 2-25
chmod command, 2-33, 2-34, 3-6, 3-22

- chown command, 2-33, 2-34, 3-6, 3-22
- cluster database
 - installed configuration, 9-2
- cluster file system
 - database recovery area and, 1-10
 - single-instance storage option for data files, 3-2
 - storage option for data files, 3-2
- cluster name
 - requirements for, 4-5
- cluster nodes
 - activating volume groups, 3-15, 3-34
 - importing raw device disk group, 3-14, 3-33
 - private node names, 4-6
 - public node names, 4-5
 - specifying uids and gids, 2-9
 - virtual node names, 4-6
- Cluster Synchronization Service Daemon, xxi, 1-12
- Cluster Synchronization Services, xxi, 1-5, 1-12, 4-4
- Cluster Verification Utility
 - about, xix, 1-2
 - DBCA database creation stage readiness check, 6-3
 - hardware and operating system setup stage verification, 2-28
 - Oracle Clusterware configuration check, 4-1
 - shared storage area check, 3-4
 - user equivalency troubleshooting, 4-2
 - verifying readiness for database installation, 5-1
- clusterware diagnostics, A-2
- components
 - created when using DBCA, 9-2
- configuration types
 - Advanced, 5-4
 - Data Warehouse, 5-4
 - Do not create a starter database, 5-4
 - General Purpose, 5-4
 - Transaction Processing, 5-4
- configuring new disks, 3-12, 3-29
- connection load balancing, 9-4
- control file
 - installed configuration, 9-3
- control files, 1-12
 - described, 9-3
 - raw devices for, 3-23, 3-32
- convert to cluster database
 - administrative considerations, D-1
 - from non-cluster system, D-2
 - from single-instance, D-4
 - from single-instance to Real Application Clusters, D-1
 - post-conversion, D-13
 - reasons not to convert, D-2
 - to Real Application Clusters from single-instance Oracle databases, D-1
- converting
 - from single-instance to Real Application Clusters, B-1, D-11
 - to Real Application Clusters from single-instance Oracle databases, B-1
- corrective service diskette

- See* CSD
- create database
 - using scripts, B-1
- creating
 - Real Application Clusters database
 - with Database Configuration Assistant, 5-5, 6-1, 6-4
 - creating a raw device mapping file, 3-34
 - creating a volume group, 3-11, 3-28
 - creating identical users, 2-10
 - creating logical volumes, 3-32
 - creating raw logical volumes, 3-13, 3-31
 - creating volume groups, 3-12, 3-29
 - cross-node registration, 9-4
- CRS
 - OCR restriction, 3-15
 - raw device for OCR on AIX, 3-7
 - voting disk restriction, 3-15
- CRSD, 4-9
- CSD
 - download location for WebSphere MQ, 2-28
 - requirements, 2-26
- CSS, xxi, 1-5, 1-12, 4-4
 - CCSD, xxi
 - OCCSD, 1-12, 4-4
- CSSD, xxi
- custom database
 - failure groups for ASM, 3-18
 - requirements when using ASM, 1-10, 3-17
- Custom installation type
 - reasons for choosing, 2-4
- CVU
 - See* Cluster Verification Utility

D

- data files
 - creating separate directories for, 3-5
 - setting permissions on data file directories, 3-6
 - single-instance database storage options, 3-2
 - storage options, 3-2
- data loss
 - minimizing with ASM, 1-9, 3-17
- Data Warehouse
 - configuration type, 5-4
- database
 - ASM requirements, 1-10
 - components, created when using DBCA, 9-2
- Database Configuration Assistant
 - ASM Disk Groups page, 6-5
 - components created by, 9-2
 - control files, 9-3
 - creating Real Application Clusters database
 - after installation, 6-4
 - during installation, 5-5, 6-1
 - datafiles, 9-2
 - deleting databases with, 6-6
 - deleting Real Application Clusters databases, 6-6
 - initialization parameter files, 9-4
 - Initialization Parameters page, 6-5

- List of Cluster Databases page, 6-6
- Operations page, 6-6
- raw storage requirements, C-1
- Recovery Configuration page, 6-5
- redo log files, 9-3
- rollback segments, 9-3
- Summary dialog, 6-6
- tablespaces, 9-2
- using, 6-1
- Welcome page, 6-4
- database configuration type
 - selecting, 5-4
- database creation using scripts, B-1
- database recovery area
 - shared storage requirement for, 1-10
- databases
 - ASM requirements, 3-17
- datafiles, 1-12
 - and DBCA, 9-2
 - described, 9-2
 - managing with ASM, 1-8
- dba group
 - and ASM disks on AIX, 3-22
 - and SYSDBA privilege, 2-4
 - creating, 2-7
 - creating on other nodes, 2-9
 - description, 2-4
 - raw device group, 3-14, 3-15, 3-33
- DBCA
 - delete database, 6-6
- DBCA_RAW_CONFIG environment variable, 3-28, 3-35
- dedicated servers, 9-4
- default file mode creation mask
 - setting, 2-18
- de-install Oracle Clusterware software, 5-9
- de-install Oracle Database software, 5-7
- delete database with DBCA, 6-6
- device names
 - on AIX, 3-22
- device numbers
 - identifying major numbers, 3-12, 3-29
- diagnostics, A-2
- directory
 - creating separate data file directories, 3-5
 - Oracle base directory, 2-30
 - Oracle home directory, 2-31
 - Oracle Inventory directory, 2-30
 - oraInventory, 2-30
 - permission for data file directories, 3-6
- directory structure, E-1
- disk devices
 - managing with ASM, 1-8
- disk group
 - ASM, 1-8, 1-9, 3-16
 - recommendations for ASM disk groups, 1-9, 3-16
- disk space
 - checking, 2-20
 - requirements for preconfigured database in ASM, 3-17

- disks
 - changing permissions and owner for ASM on AIX, 3-22
 - checking availability for ASM on AIX, 3-20
 - checking availability for raw devices, 3-11, 3-29
 - configuring for ASM on AIX, 3-19
 - configuring new disks, 3-12, 3-20, 3-29
 - identifying LVM disks, 3-12, 3-29
 - identifying LVM disks on AIX, 3-20
 - raw voting disk on AIX, 3-8
- DISPLAY environment variable
 - setting, 2-18, 2-19
- Do not create a database
 - configuration type, 5-4
- documentation
 - Oracle Clusterware, 1-1
 - Oracle Real Application Clusters Administration and Deployment Guide, 1-2
 - Real Application Clusters, 1-1

E

- Easy Connect, 9-11
- emulator
 - installing from X emulator, 2-4
- env command, 2-35
- environment
 - checking settings, 2-35
 - configuring for oracle user, 2-18
- environment variables
 - DBCA_RAW_CONFIG, 3-28, 3-35
 - DISPLAY, 2-18, 2-19
 - ORACLE_BASE, 2-18, 2-30, 2-33
 - ORACLE_HOME, 2-18, 2-34, 2-36
 - ORACLE_SID, 2-18
 - PATH, 2-18
 - removing from shell startup file, 2-18
 - SHELL, 2-18
 - TEMP and TMPDIR, 2-19, 2-20
 - TNS_ADMIN, 2-34
- error messages
 - Real Application Clusters management tools, A-2
- EVMD, 4-9
- EXAMPLE tablespace
 - raw device for, 3-23, 3-32
- examples
 - ASM failure groups, 3-18
 - Oracle base directories, 2-30
- external jobs
 - UNIX user required for, 2-5
- external redundancy
 - ASM redundancy level, 1-9
- extjob executable
 - UNIX user required for, 2-5

F

- failover
 - and service registration, 9-4
 - of single-instance databases using Oracle

- Clusterware, 3-2
- failure group
 - ASM, 1-9, 3-16
 - characteristics of ASM failure group, 1-9, 3-17
 - examples of ASM failure groups, 3-18
- features, new, xix
- file mode creation mask
 - setting, 2-18
- file system
 - appropriate for Oracle base directory, 2-33
 - storage option for data files, 3-2
 - storage option for single instance data files, 3-2
- files
 - .bash_profile, 2-18
 - control files
 - raw devices for, 3-23, 3-32
 - editing shell startup file, 2-18
 - .login, 2-18
 - oraInst.loc, 2-6, 2-32
 - oratab, 2-32
 - password file
 - raw device for, 3-24, 3-32
 - .profile, 2-18
 - raw device mapping file, 3-34
 - redo log files
 - raw devices for, 3-23, 3-32
 - server parameter file
 - raw devices for, 3-23, 3-32
 - SPFILE
 - raw device for, 3-23, 3-32
- filesets, 2-23
 - checking, 2-25
- Flash Recovery
 - and Oracle-Managed Files, D-12

G

- Gateway
 - See* Oracle Messaging Gateway
- General Parallel File System (GPFS), 3-1, 3-2
 - and Oracle Clusterware, 1-3
 - and the Oracle base directory, 2-30
- General Purpose
 - configuration type, 5-4
- gid
 - identifying existing, 2-10
 - specifying, 2-10
 - specifying on other nodes, 2-9
- GPFS
 - restriction for Oracle base directory on AIX, 2-33, 2-34
- group IDs
 - identifying existing, 2-10
 - specifying, 2-10
 - specifying on other nodes, 2-9
- groups
 - checking for existing oinstall group, 2-6
 - creating identical groups on other nodes, 2-9
 - creating the dba group, 2-7
 - creating the oinstall group, 2-6

- creating the oper group, 2-7
- specifying when creating UNIX users, 2-10
- UNIX OSDBA group (dba), 2-4
- UNIX OSOPER group (oper), 2-5

H

- hardware requirements, 2-19
- high redundancy
 - ASM redundancy level, 1-9
- home directory
 - See* Oracle home directory

I

- IBM WebSphere MQ
 - requirement, 2-25
- id command, 2-9, 2-10
- identifying disks for LVM, 3-11, 3-29
- identifying LVM disks, 3-12, 3-29
- importing raw device disk group, 3-14, 3-33
- importvg command, 3-14, 3-33
- initialization parameter files, 9-4
 - for instances, 8-1
 - listener parameters, 9-5
- initialization parameters
 - DISPATCHERS, 9-4
 - LOCAL_LISTENER, 9-4
 - REMOTE_LISTENER, 9-4, 9-8
- initializing disks for LVM, 3-12, 3-29
- installation
 - directory structure, E-1
 - ldap.ora file, 9-6
 - listener.ora file, 9-5
 - non-interactive, 1-7, B-1
 - of additional products after installation is completed, 6-6
 - overview, 1-7
 - requirements, hardware, 1-2
 - requirements, software, 1-2
 - tnsnames.ora file, 9-7
 - verifying raw devices, 6-4
- installation types
 - and ASM requirements, 1-10, 3-17
- instance
 - instance identifier (SID), 2-18
 - preferences, 6-2
- instances
 - initialization parameter files, 8-1
- instfix command, 2-27

J

- JDK requirements, 2-23

K

- Korn shell
 - default user startup file, 2-18

L

- ldap.ora file, 9-6
 - creating, 9-6
 - default configuration, 9-6
- Lightweight Directory Access Protocol (LDAP), 9-6
- List of Cluster Databases page, 6-6
- listener
 - automatic migration from 10.1 to 10.2, 6-3
 - identifying Oracle home for, 2-36
 - local, 9-4
 - lsnrctl command, 2-37
 - registration, 9-6
 - stopping, 2-36, 2-37
 - stopping existing listener process, 2-35
- listener.ora file, 9-5
 - configuring, 9-5
 - default configuration, 9-5
- listeners
 - listener.ora file, 9-5
- load balancing
 - and service registration, 9-4
- local listener, 9-4
- logical volume manager
 - See LVM
- logical volumes
 - creating, 3-32
- .login file, 2-18
- lsdev command, 3-11, 3-20, 3-29
- lslpp command, 2-25, 2-28
- lsnrctl command, 2-37
- lspv command, 3-12, 3-14, 3-20, 3-29, 3-33

LVM

- compared to ASM, 1-9
- creating a volume group, 3-11, 3-28
- creating raw logical volumes, 3-13, 3-31
- creating volume groups, 3-12, 3-29
- identifying available disks, 3-11, 3-29
- identifying major device numbers, 3-12, 3-29
- identifying volume group devices, 3-12, 3-29
- identifying volume group devices on AIX, 3-20
- initializing disks, 3-12, 3-29
- initializing disks on AIX, 3-20
- recommendations for ASM, 1-9, 3-16

M

- maintenance level
 - checking, 2-25
- major device numbers
 - identifying, 3-12, 3-29
- mapping file
 - for raw devices, 3-34
- mask
 - setting default file mode creation mask, 2-18
- memory requirements, 2-19
- Messaging Gateway
 - See Oracle Messaging Gateway
- MetaLink
 - Oracle patches, 7-1
- migration

- from single-instance, D-2
- mkdir command, 2-33, 2-34, 3-6
- mklnv command, 3-32
- mkvlg command, 3-12, 3-29
- mode
 - setting default file mode creation mask, 2-18
- mount point
 - for Oracle base directory, 2-30
- multiple voting disks, xxii, 1-5

N

- Net naming methods, 9-11
- net service names, 9-7
- network configuration files
 - ldap.ora.ora, 9-6
 - listener.ora, 9-5
 - sqlnet.ora, 9-11
 - tnsnames.ora, 9-7
- network directory, E-2
- Network Information Services
 - See NIS
- new features, xix
- NIS
 - alternative to local users and groups, 2-5
- nobody user
 - checking existence of, 2-9
 - description, 2-5
- node applications, 6-1
- None
 - TAF failover policy, 6-3
- non-interactive installation, 1-7
- normal redundancy
 - ASM redundancy level, 1-9
- Not used
 - service configuration policy, 6-2

O

- OCCSD, 4-4, 4-9
- OCR
 - installed configuration, 9-1
 - mirroring, 3-5
 - raw device for
 - on AIX, 3-7
 - restriction on using ASM for, 3-15
- OCR contents, 9-1
- OCR. See Oracle Cluster Registry
- OCCSSD, 1-12
- OCCSSD. See CSSD
- OFA
 - and ASM, xxi
 - and Oracle Clusterware, xx
 - recommendations for Oracle base directory, 2-30
 - recommended path for Oracle base directory, 2-30
 - recommended path for Oracle home directory, 2-31
 - recommended path for Oracle Inventory directory, 2-30

- oinstall group
 - checking for existing, 2-6
 - creating, 2-6
 - creating on other nodes, 2-9
 - description, 2-5
- olsnodes command, A-2
- oper group
 - and SYSOPER privilege, 2-5
 - creating, 2-7
 - creating on other nodes, 2-9
 - description, 2-5
- operating system
 - checking version, 2-25
- operating system account users
 - requirements, 2-4
- operating system groups
 - requirements, 2-4
- operating system requirements, 2-23
- OPROCD, 4-9
- Optimal Flexible Architecture
 - and ASM, xxi
 - and Oracle Clusterware, xx
 - See* OFA
- Optimal Flexible Architecture (OFA), 5-5
- Oracle base directory
 - and ORACLE_BASE environment variable, 2-30
 - creating, 2-33, 2-34
 - creating new, 2-33
 - description, 2-30
 - determining disk space on, 2-32
 - equivalent directory on Windows, 2-30
 - examples, 2-30
 - GPFS restriction on AIX, 2-33, 2-34
 - identifying appropriate file system, 2-33
 - identifying existing, 2-32
 - mount point for, 2-30
 - recommended path, 2-30
 - relationship with Oracle Software Owner user, 2-30
 - requirement for, 2-30
 - requirement for RAC installations, 2-33, 2-34
 - requirements for existing directory, 2-32
- Oracle Cluster Registry
 - configuration of, 4-6
 - See* OCR
- Oracle Clusterware
 - and OFA, xx
 - and single-instance databases, 3-2
 - API libraries for, xxi
 - documentation, 1-1
 - installing, 4-1
 - installing with Oracle Universal Installer, 4-7
 - raw device for voting disk on AIX, 3-8
- Oracle Database
 - creating data file directories, 3-5
 - data file storage options, 3-2
 - privileged groups, 2-4
 - requirements with ASM, 1-10, 3-17
 - setting ORACLE_SID environment variable, 2-18
 - single instance data file storage options, 3-2
- Oracle Enterprise Manager
 - post-installation configuration, 7-3
 - using to convert single-instance databases to Real Application Clusters, D-11
- Oracle home directory
 - description, 2-31
 - identifying for listener, 2-36
 - recommended path, 2-31
 - requirement for, 2-31
 - requirements, 2-31
 - using to identify Oracle base directory, 2-32
- Oracle home name, 2-31
- Oracle Inventory
 - description, 2-30
 - pointer file, 2-6
- Oracle Inventory directory
 - description, 2-30
 - recommended path, 2-30
- Oracle Inventory group
 - checking for existing, 2-6
 - creating, 2-6
 - creating on other nodes, 2-9
 - description, 2-5
- Oracle Messaging Gateway
 - CSD requirements, 2-26
 - requirements, 2-25
- Oracle Net
 - identifying Oracle home for listener, 2-36
 - lsnrctl command, 2-37
 - stopping existing listener, 2-35
 - stopping listener, 2-36
 - stopping the listener, 2-37
- Oracle Notification Server Configuration Assistant, 4-7
- Oracle Private Interconnect Configuration Assistant, 4-7
- Oracle Software Owner user
 - and ASM disks, 3-22
 - configuring environment for, 2-18
 - creating, 2-7, 2-8
 - creating on other nodes, 2-9
 - description, 2-5
 - determining default shell, 2-18
 - raw device owner, 3-14, 3-15, 3-33
 - relationship with Oracle base directory, 2-30
 - required group membership, 2-5
- Oracle Universal Installer
 - and Oracle Clusterware, 4-7
 - overview of processing, 1-7
 - Welcome page, 4-7, 5-5, 5-9
- oracle user
 - and ASM disks, 3-22
 - configuring environment for, 2-18
 - creating, 2-7, 2-8
 - creating on other nodes, 2-9
 - description, 2-5
 - determining default shell, 2-18
 - raw device owner, 3-14, 3-15, 3-33
 - relationship with Oracle base directory, 2-30
 - required group membership, 2-5

- ORACLE_BASE environment variable, 2-30, 2-33
 - removing from shell startup file, 2-18
 - setting, 2-18
- ORACLE_HOME environment variable
 - removing from shell startup file, 2-18
 - setting, 2-36, 7-3
 - unset, 2-34
- ORACLE_SID environment variable
 - removing from shell startup file, 2-18
 - setting, 2-18, 7-3
- Oracle9 *upgrades*
 - stopping processes, 2-35
- OracleMetalink, 7-1
- oraInst.loc file, 2-32
 - location, 2-6
 - location of, 2-6
- oraInventory
 - creating, 2-6
- oraInventory directory
 - See* Oracle Inventory directory
- oratab file, 9-2
 - format, 2-32
 - location of oratab file, 2-32
- OSDBA group
 - and ASM disks on AIX, 3-22
 - and SYSDBA privilege, 2-4
 - creating, 2-7
 - creating on other nodes, 2-9
 - description, 2-4
 - raw device group, 3-14, 3-15, 3-33
- oslevel command, 2-25
- OSOPER group
 - and SYSOPER privilege, 2-5
 - creating, 2-7
 - creating on other nodes, 2-9
 - description, 2-5
- OUI
 - see* Oracle Universal Installer

P

- parameter file search order, 8-2
- parameters
 - initialization, 8-1
- partition
 - using with ASM, 1-9, 3-16
- partitions
 - creating raw partitions, 3-7, 3-23
 - required sizes for raw devices on AIX, 3-7
- passwd command, 2-8, 2-10
- password file
 - raw device for, 3-24, 3-32
- patches
 - download, 7-1
 - download location, 2-27
 - install, 7-1
 - OracleMetalink, 7-1
- PATH environment variable
 - setting, 2-18
- PC X server

- installing from, 2-4
- permissions
 - for data file directories, 3-6
 - for Oracle base directory, 2-33, 2-34
- physical RAM requirements, 2-19
- post-installation
 - Oracle Enterprise Manager configuration, 7-3
 - patch download and install, 7-1
 - product configuration, 7-2
 - root.sh back up, 7-3
 - user accounts setup, 7-3
- Precompilers
 - requirements, 2-25
- preconfigured database
 - ASM disk space requirements, 3-17
 - requirements when using ASM, 1-10, 3-17
- preconfigured database installation types, 5-4
- Preferred
 - service configuration policy, 6-2
- pre-installation
 - raw device creation, C-1
- privileged groups
 - for Oracle Database, 2-4
- Pro*C/C++
 - PTFs and APARs required, 2-26
 - requirements, 2-25
- process
 - stopping existing, 2-35
 - stopping existing listener process, 2-35
 - stopping listener process, 2-36
- processor
 - checking system architecture, 2-21
- .profile file, 2-18
- ps command, 2-36
- PTF
 - checking, 2-28
 - download location, 2-28
- PTF download location, 2-28

R

- RAC
 - configuring disks for raw devices on AIX, 3-23
 - configuring raw logical volumes, 3-11, 3-28
 - preferred datafile storage mechanisms, 3-15
 - requirements for Oracle base directory, 2-33, 2-34
- RAC high availability extensions
 - configuring services for, 6-2
 - TAF policies for, 6-2
- RAID
 - and mirroring OCR and voting disk, 3-5
 - compared to ASM, 1-9
 - recommended ASM redundancy level, 1-9, 3-16
- RAM requirements, 2-19
- raw device
 - for OCR
 - on AIX, 3-7
 - for password file, 3-24, 3-32
 - for server parameter file, 3-23, 3-32
 - for SPFILE, 3-23, 3-32

- for voting disk
 - on AIX, 3-8
- raw device sizes, 3-14, 3-31
- raw devices
 - activating volume group on cluster nodes, 3-15, 3-34
 - checking availability of disks, 3-11, 3-29
 - creating a raw device mapping file, 3-34
 - creating logical volumes, 3-32
 - creating raw logical volumes, 3-13, 3-31
 - creating raw partitions, 3-7, 3-23
 - Database Configuration Assistant, C-1
 - for control files, 3-23, 3-32
 - for EXAMPLE tablespace, 3-23, 3-32
 - for redo log files, 3-23, 3-32
 - for SYSAUX tablespace, 3-23, 3-31
 - for SYSTEM tablespace, 3-23, 3-31
 - for TEMP tablespace, 3-23, 3-31
 - for UNDOTBS tablespace, 3-23, 3-31
 - for USER tablespace, 3-23, 3-32
 - identifying disks, 3-11, 3-29
 - importing on disk group on cluster nodes, 3-14, 3-33
 - initializing disks for LVM, 3-12, 3-29
 - initializing disks for LVM on AIX, 3-20
 - required sizes, 3-14, 3-31
 - on AIX, 3-7
 - setting up, C-1
 - specifying owner and permissions, 3-14, 3-15, 3-33
 - storage option for data files, 3-2
 - value for DBCA_RAW_CONFIG environment variable, 3-28, 3-35
 - verification, 6-4
- raw storage
 - Database Configuration Assistant requirements, C-1
- RBS tablespace
 - description, 9-3
- Real Application Clusters
 - components, 1-11
 - databases, deleting, 6-6
 - installation requirements, 1-2
 - installed components of, 1-12
 - management tools error messages, A-2
 - overview, 1-1, 6-1, 9-1
 - raw device setup, C-1
- recovery files
 - shared storage requirement for, 1-10
- redo log file
 - installed configuration, 9-3
- redo log files, 1-12
 - described, 9-3
 - raw devices for, 3-23, 3-32
- redundancy level
 - and space requirements for preconfigured database, 3-17
 - for ASM, 1-9
- registration
 - cross-node, 9-4

- requirements
 - hardware, 2-19
- rollback segments
 - described, 9-3
- root user
 - logging in as, 2-3
- root.sh, 4-7
 - back up, 7-3

S

- scripts to create a Real Application Clusters
 - database, B-1
- server parameter file
 - raw device for, 3-23, 3-32
- server parameter files, 1-12, 8-1, 9-4
 - errors, 8-4
- Service Management
 - using, 6-2
- service registration
 - configuring, 9-4
- services, 6-2
- shared configuration file, 9-1
- shared server, 9-4
- shared storage
 - requirement for recovery area, 1-10
- shell
 - determining default shell for oracle user, 2-18
- SHELL environment variable
 - checking value of, 2-18
- shell startup file
 - editing, 2-18
 - removing environment variables, 2-18
- SID
 - setting ORACLE_SID environment variable, 2-18
- silent installation. *See* installation
 - non-interactive
- single-instance databases
 - converting, D-11
- smit command, 2-8, 2-10
- software requirements, 2-23
 - checking software requirements, 2-25
- specifying owner and permissions of raw devices, 3-14, 3-15, 3-33
- SPFILE
 - default creation, 8-1
 - default location, 8-2
 - managing on raw device, 8-2
 - migrating to, 8-3
 - raw device for, 3-23, 3-32
- sqlnet.ora file, 9-11
- startup file
 - for shell, 2-18
- Summary dialog, 6-6
- swap space
 - requirements, 2-19
- SYSAUX tablespace
 - raw device for, 3-23, 3-31
- SYSDBA privilege
 - associated UNIX group, 2-4

- SYSOPER privilege
 - associated UNIX group, 2-5
- system architecture
 - checking, 2-21
- SYSTEM tablespace
 - description, 9-2
 - raw device for, 3-23, 3-31

T

- tablespaces
 - and DBCA, 9-2
 - expanding for large sorts, 9-3
 - RBS, 9-3
 - SYSTEM, 9-2
 - TEMP, 9-3
 - undo tablespaces for automatic undo management, 9-3
 - USERS, 9-2
- TAF failover policies
 - Basic, 6-3
 - None, 6-3
- TEMP environment variable, 2-20
 - setting, 2-19
- TEMP tablespace
 - described, 9-3
 - raw device for, 3-23, 3-31
- temporary directory, 2-20
- temporary disk space
 - checking, 2-20
 - freeing, 2-20
 - requirements, 2-19
- /tmp directory
 - checking space in, 2-20
 - freeing space in, 2-20
- TMPDIR environment variable, 2-20
 - setting, 2-19
- TNS_ADMIN environment variable
 - unset, 2-34
- tnsnames.ora file, 9-7
 - default configuration, 9-7
- Transaction Processing
 - configuration type, 5-4
- Transparent Application Failover (TAF) policies, 6-2
- troubleshooting
 - user equivalency, 4-2

U

- uid
 - identifying existing, 2-10
 - specifying, 2-10
 - specifying on other nodes, 2-9
- umask, 2-35
- umask command, 2-18, 2-35
- undo management, 9-3
- UNDOTBS tablespace
 - raw device for, 3-23, 3-31
- UNIX commands, 2-35
 - cfgmgr, 3-12, 3-20, 3-29

- chdev, 3-12, 3-20, 3-29
- chmod, 2-33, 2-34, 3-6, 3-22
- chown, 2-33, 2-34, 3-6, 3-22
- env, 2-35
- id, 2-9, 2-10
- importvg, 3-14, 3-33
- instfix, 2-27
- lsdev, 3-11, 3-20, 3-29
- lslpp, 2-25, 2-28
- lspv, 3-12, 3-14, 3-20, 3-29, 3-33
- mkdir, 2-33, 2-34, 3-6
- mklv, 3-32
- mkvg, 3-12, 3-29
- oslevel, 2-25
- passwd, 2-8, 2-10
- ps, 2-36
- smit, 2-8, 2-10
- swap, 2-20
- swapon, 2-20
- umask, 2-18
- unset, 2-34
- unsetenv, 2-34
- varyoffvg, 3-14, 3-33
- varyonvg, 3-13, 3-31
- xhost, 2-3
- xterm, 2-4

- UNIX groups
 - checking for existing oinstall group, 2-6
 - creating identical groups on other nodes, 2-9
 - creating the dba group, 2-7
 - creating the oinstall group, 2-6
 - creating the oper group, 2-7
 - oinstall, 2-5
 - OSDBA (dba), 2-4
 - OSOPER (oper), 2-5
 - required for oracle user, 2-5
 - specifying when creating users, 2-10
 - using NIS, 2-5, 2-9
- UNIX users
 - checking existence of the nobody user, 2-9
 - creating identical users on other nodes, 2-9
 - creating the oracle user, 2-7, 2-8
 - nobody, 2-5
 - oracle, 2-5
 - required for external jobs, 2-5
 - specifying groups when creating, 2-10
 - unprivileged user, 2-5
 - using NIS, 2-5, 2-9
- UNIX workstation
 - installing from, 2-3
- unprivileged user
 - nobody user, 2-5
- unset command, 2-34
- unsetenv command, 2-34
- user accounts
 - post-installation setup, 7-3
- user equivalence
 - testing, 4-2
- user IDs
 - identifying existing, 2-10

- specifying, 2-10
- specifying on other nodes, 2-9
- USER tablespace
 - raw device for, 3-23, 3-32
- users
 - checking existence of the nobody user, 2-9
 - creating identical users on other nodes, 2-9
 - creating the oracle user, 2-7, 2-8
 - Oracle Software Owner user (oracle), 2-5
 - specifying UNIX groups when creating, 2-10
 - UNIX nobody user, 2-5
- USERS tablespace
 - described, 9-2

V

- varyoffvg command, 3-14, 3-33
- varyonvg command, 3-13, 3-31
- VIP, 1-4
- virtual IP. *See* VIP
- volume group
 - creating, 3-11, 3-28
- volume groups
 - creating, 3-12, 3-29
- volumes
 - creating logical volumes, 3-32
- voting disk
 - configuration of, 4-6
 - mirroring, 3-5
 - raw device for
 - on AIX, 3-8
 - restriction on using ASM for, 3-15
- voting disks
 - configuring multiple, xxii, 1-5

W

- WebSphere MQ
 - CSD download location, 2-28
 - CSDs required, 2-26
 - requirement, 2-25
- Welcome page
 - Oracle Universal Installer, 4-7, 5-5, 5-9
- Windows
 - analogy for Oracle base directory, 2-30

X

- X emulator
 - installing from, 2-4
- X window system
 - enabling remote hosts, 2-3, 2-4
- xhost command, 2-3
- xterm command, 2-4