



ZFS Administration Guide



Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 817-2271-09
April 2007

Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc. Legato NetWorker is a trademark or registered trademark of Legato Systems, Inc.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2007 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux Etats-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certains composants de ce produit peuvent être dérivées du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. Legato NetWorker is a trademark or registered trademark of Legato Systems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des Etats-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFACON.

Contents

Preface	9
1 ZFS File System (Introduction)	13
What's New in ZFS?	13
Improved <code>zpool status</code> Output	14
New ZFS Property (<code>xattr</code>)	14
ZFS and Solaris iSCSI Improvements	14
Sharing ZFS File System Enhancements	15
ZFS Command History (<code>zpool history</code>)	15
ZFS <code>canmount</code> Property	16
ZFS User Properties	17
Setting Properties When Creating ZFS File Systems	17
Displaying All ZFS File System Information	17
New <code>zfs receive -F</code> Option	17
Recursive ZFS Snapshots	18
Double Parity RAID-Z (<code>raidz2</code>)	18
Hot Spares for ZFS Storage Pool Devices	18
Replacing a ZFS File System With a ZFS Clone (<code>zfs promote</code>)	19
Upgrading ZFS Storage Pools (<code>zpool upgrade</code>)	19
Using ZFS to Clone Non-Global Zones and Other Enhancements	19
ZFS Backup and Restore Commands are Renamed	20
Recovering Destroyed Storage Pools	20
ZFS is Integrated With Fault Manager	20
New <code>zpool clear</code> Command	21
Compact NFSv4 ACL Format	21
File System Monitoring Tool (<code>fsstat</code>)	21
ZFS Web-Based Management	21
What Is ZFS?	22

ZFS Pooled Storage	23
Transactional Semantics	23
Checksums and Self-Healing Data	24
Unparalleled Scalability	24
ZFS Snapshots	24
Simplified Administration	24
ZFS Terminology	25
ZFS Component Naming Requirements	26
2 Getting Started With ZFS	29
ZFS Hardware and Software Requirements and Recommendations	29
Creating a Basic ZFS File System	30
Creating a ZFS Storage Pool	31
▼ How to Identify Storage Requirements for Your ZFS Storage Pool	31
▼ How to Create a ZFS Storage Pool	32
Creating a ZFS File System Hierarchy	32
▼ How to Determine Your ZFS File System Hierarchy	33
▼ How to Create ZFS File Systems	33
3 ZFS and Traditional File System Differences	37
ZFS File System Granularity	37
ZFS Space Accounting	38
Out of Space Behavior	38
Mounting ZFS File Systems	39
Traditional Volume Management	39
New Solaris ACL Model	39
4 Managing ZFS Storage Pools	41
Components of a ZFS Storage Pool	41
Using Disks in a ZFS Storage Pool	41
Using Files in a ZFS Storage Pool	43
Identifying Virtual Devices in a Storage Pool	43
Replication Features of a ZFS Storage Pool	44
Mirrored Storage Pool Configuration	44

RAID-Z Storage Pool Configuration	44
Self-Healing Data in a Redundant Configuration	45
Dynamic Striping in a Storage Pool	45
Creating and Destroying ZFS Storage Pools	46
Creating a ZFS Storage Pool	46
Handling ZFS Storage Pool Creation Errors	48
Destroying ZFS Storage Pools	50
Managing Devices in ZFS Storage Pools	51
Adding Devices to a Storage Pool	52
Attaching and Detaching Devices in a Storage Pool	53
Onlining and Offlining Devices in a Storage Pool	55
Clearing Storage Pool Devices	57
Replacing Devices in a Storage Pool	58
Designating Hot Spares in Your Storage Pool	58
Querying ZFS Storage Pool Status	62
Displaying Basic ZFS Storage Pool Information	62
Viewing ZFS Storage Pool I/O Statistics	64
Determining the Health Status of ZFS Storage Pools	66
Migrating ZFS Storage Pools	68
Preparing for ZFS Storage Pool Migration	69
Exporting a ZFS Storage Pool	69
Determining Available Storage Pools to Import	69
Finding ZFS Storage Pools From Alternate Directories	71
Importing ZFS Storage Pools	72
Recovering Destroyed ZFS Storage Pools	73
Upgrading ZFS Storage Pools	75
5 Managing ZFS File Systems	77
Creating and Destroying ZFS File Systems	78
Creating a ZFS File System	78
Destroying a ZFS File System	79
Renaming a ZFS File System	80
Introducing ZFS Properties	81
ZFS Read-Only Native Properties	86
Settable ZFS Native Properties	87

ZFS User Properties	89
Querying ZFS File System Information	90
Listing Basic ZFS Information	90
Creating Complex ZFS Queries	91
Managing ZFS Properties	92
Setting ZFS Properties	93
Inheriting ZFS Properties	93
Querying ZFS Properties	94
Mounting and Sharing ZFS File Systems	97
Managing ZFS Mount Points	97
Mounting ZFS File Systems	99
Using Temporary Mount Properties	100
Unmounting ZFS File Systems	101
Sharing and Unsharing ZFS File Systems	101
ZFS Quotas and Reservations	103
Setting Quotas on ZFS File Systems	103
Setting Reservations on ZFS File Systems	104
6 Working With ZFS Snapshots and Clones	107
Overview of ZFS Snapshots	107
Creating and Destroying ZFS Snapshots	108
Displaying and Accessing ZFS Snapshots	109
Rolling Back to a ZFS Snapshot	110
Overview of ZFS Clones	111
Creating a ZFS Clone	111
Destroying a ZFS Clone	112
Replacing a ZFS File System With a ZFS Clone	112
Saving and Restoring ZFS Data	113
Saving ZFS Data With Other Backup Products	114
Saving a ZFS Snapshot	114
Restoring a ZFS Snapshot	115
Remote Replication of ZFS Data	116
7 Using ACLs to Protect ZFS Files	117
New Solaris ACL Model	117

Syntax Descriptions for Setting ACLs	118
ACL Inheritance	121
ACL Property Modes	122
Setting ACLs on ZFS Files	123
Setting and Displaying ACLs on ZFS Files in Verbose Format	125
Setting ACL Inheritance on ZFS Files in Verbose Format	131
Setting and Displaying ACLs on ZFS Files in Compact Format	139
8 ZFS Advanced Topics	143
ZFS Volumes	143
Using a ZFS Volume as a Swap or Dump Device	144
Using a ZFS Volume as a Solaris iSCSI Target	144
Using ZFS on a Solaris System With Zones Installed	145
Adding ZFS File Systems to a Non-Global Zone	146
Delegating Datasets to a Non-Global Zone	147
Adding ZFS Volumes to a Non-Global Zone	148
Using ZFS Storage Pools Within a Zone	148
Mangling ZFS Properties Within a Zone	148
Understanding the zoned Property	149
Using ZFS Alternate Root Pools	151
Creating ZFS Alternate Root Pools	151
Importing Alternate Root Pools	151
ZFS Rights Profiles	152
9 ZFS Troubleshooting and Data Recovery	153
ZFS Failure Modes	153
Missing Devices in a ZFS Storage Pool	154
Damaged Devices in a ZFS Storage Pool	154
Corrupted ZFS Data	154
Checking ZFS Data Integrity	155
Data Repair	155
Data Validation	155
Controlling ZFS Data Scrubbing	155
Identifying Problems in ZFS	157
Determining if Problems Exist in a ZFS Storage Pool	158

Reviewing zpool status Output	158
System Reporting of ZFS Error Messages	161
Repairing a Damaged ZFS Configuration	162
Repairing a Missing Device	162
Physically Reattaching the Device	163
Notifying ZFS of Device Availability	164
Repairing a Damaged Device	164
Determining the Type of Device Failure	164
Clearing Transient Errors	165
Replacing a Device in a ZFS Storage Pool	166
Repairing Damaged Data	169
Identifying the Type of Data Corruption	170
Repairing a Corrupted File or Directory	171
Repairing ZFS Storage Pool-Wide Damage	172
Repairing an Unbootable System	173
Index	175

Preface

The *ZFS Administration Guide* provides information about setting up and managing Solaris™ ZFS file systems.

This guide contains information for both SPARC® based and x86 based systems.

Note – This Solaris release supports systems that use the SPARC and x86 families of processor architectures: UltraSPARC®, SPARC64, AMD64, Pentium, and Xeon EM64T. The supported systems appear in the *Solaris 10 Hardware Compatibility List* at <http://www.sun.com/bigadmin/hcl>. This document cites any implementation differences between the platform types.

In this document these x86 terms mean the following:

- “x86” refers to the larger family of 64-bit and 32-bit x86 compatible products.
- “x64” points out specific 64-bit information about AMD64 or EM64T systems.
- “32-bit x86” points out specific 32-bit information about x86 based systems.

For supported systems, see the *Solaris 10 Hardware Compatibility List*.

Who Should Use This Book

This guide is intended for anyone who is interested in setting up and managing Solaris ZFS file systems. Experience using the Solaris Operating System (OS) or another UNIX® version is recommended.

How This Book Is Organized

The following table describes the chapters in this book.

Chapter	Description
Chapter 1	Provides an overview of ZFS and its features and benefits. It also covers some basic concepts and terminology.
Chapter 2	Provides step-by-step instructions on setting up simple ZFS configurations with simple pools and file systems. This chapter also provides the hardware and software required to create ZFS file systems.
Chapter 3	Identifies important features that make ZFS significantly different from traditional file systems. Understanding these key differences will help reduce confusion when using traditional tools to interact with ZFS.
Chapter 4	Provides a detailed description of how to create and administer storage pools.
Chapter 5	Provides detailed information about managing ZFS file systems. Included are such concepts as hierarchical file system layout, property inheritance, and automatic mount point management and share interactions.
Chapter 6	Describes how to create and administer ZFS snapshots and clones.
Chapter 7	Describes how to use access control lists (ACLs) to protect your ZFS files by providing more granular permissions than the standard UNIX permissions.
Chapter 8	Provides information on using emulated volumes, using ZFS on a Solaris system with zones installed, and alternate root pools.
Chapter 9	Describes how to identify ZFS failure modes and how to recover from them. Steps for preventing failures are covered as well.

Related Books

Related information about general Solaris system administration topics can be found in the following books:

- *Solaris System Administration: Basic Administration*
- *Solaris System Administration: Advanced Administration*
- *Solaris System Administration: Devices and File Systems*
- *Solaris System Administration: Security Services*
- *Solaris Volume Manager Administration Guide*

Documentation, Support, and Training

The Sun web site provides information about the following additional resources:

- Documentation (<http://www.sun.com/documentation/>)
- Support (<http://www.sun.com/support/>)
- Training (<http://www.sun.com/training/>)

Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code>
AaBbCc123	What you type, contrasted with onscreen computer output	<code>machine_name% su</code> Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <i>rm filename</i> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . A <i>cache</i> is a copy that is stored locally. Do <i>not</i> save the file. Note: Some emphasized items appear bold online.

Shell Prompts in Command Examples

The following table shows the default UNIX system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE P-2 Shell Prompts

Shell	Prompt
C shell	machine_name%
C shell for superuser	machine_name#
Bourne shell and Korn shell	\$
Bourne shell and Korn shell for superuser	#

ZFS File System (Introduction)

This chapter provides an overview of the ZFS file system and its features and benefits. This chapter also covers some basic terminology used throughout the rest of this book.

The following sections are provided in this chapter:

- “What's New in ZFS?” on page 13
- “What Is ZFS?” on page 22
- “ZFS Terminology” on page 25
- “ZFS Component Naming Requirements” on page 26

What's New in ZFS?

This section summarizes new features in the ZFS file system.

- “Improved `zpool status` Output” on page 14
- “New ZFS Property (`xattr`)” on page 14
- “ZFS and Solaris iSCSI Improvements” on page 14
- “Sharing ZFS File System Enhancements” on page 15
- “ZFS Command History (`zpool history`)” on page 15
- “ZFS `canmount` Property” on page 16
- “ZFS User Properties” on page 17
- “Setting Properties When Creating ZFS File Systems” on page 17
- “Displaying All ZFS File System Information” on page 17
- “New `zfs receive -F` Option” on page 17
- “Recursive ZFS Snapshots” on page 18
- “Double Parity RAID-Z (`raidz2`)” on page 18
- “Hot Spares for ZFS Storage Pool Devices” on page 18
- “Replacing a ZFS File System With a ZFS Clone (`zfs promote`)” on page 19
- “Upgrading ZFS Storage Pools (`zpool upgrade`)” on page 19
- “Using ZFS to Clone Non-Global Zones and Other Enhancements” on page 19
- “ZFS Backup and Restore Commands are Renamed” on page 20

- “Recovering Destroyed Storage Pools” on page 20
- “ZFS is Integrated With Fault Manager” on page 20
- “New `zpool clear` Command” on page 21
- “Compact NFSv4 ACL Format” on page 21
- “File System Monitoring Tool (`fsstat`)” on page 21
- “ZFS Web-Based Management” on page 21

Improved `zpool status` Output

Solaris Express Community Edition, build 57: You can use the `zpool status -v` command to display a list of files with persistent errors. Previously, you had to use the `find -inum` command to identify the filenames from the list of displayed inodes.

For more information about displaying a list of files with persistent errors, see “[Repairing a Corrupted File or Directory](#)” on page 171.

New ZFS Property (`xattr`)

Solaris Express Community Release, build 56: You can use the `xattr` property to disable or enable extended attributes for a specific ZFS file system. The default value is `on`. For a description of ZFS properties, see “[Introducing ZFS Properties](#)” on page 81.

ZFS and Solaris iSCSI Improvements

Solaris Express Community Release, build 54: In this Solaris release, you can create a ZFS volume as a Solaris iSCSI target device by setting the `shareiscsi` property on the ZFS volume. This method is a convenient way to quickly set up a Solaris iSCSI target. For example:

```
# zfs create -V 2g tank/volumes/v2
# zfs set shareiscsi=on tank/volumes/v2
# iscsitadm list target
Target: tank/volumes/v2
    iSCSI Name: iqn.1986-03.com.sun:02:984fe301-c412-ccc1-cc80-cf9a72aa062a
    Connections: 0
```

After the iSCSI target is created, set up the iSCSI initiator. For information about setting up a Solaris iSCSI initiator, see Chapter 14, “Configuring Solaris iSCSI Targets and Initiators (Tasks),” in *System Administration Guide: Devices and File Systems*.

For more information about managing a ZFS volume as an iSCSI target, see “[Using a ZFS Volume as a Solaris iSCSI Target](#)” on page 144.

Sharing ZFS File System Enhancements

Solaris Express Community Release, build 53: In this Solaris release, the process of sharing file systems has been improved. Although modifying system configuration files, such as `/etc/dfs/dfsstab`, is unnecessary for sharing ZFS file systems, you can use the `sharemgr` command to manage ZFS share properties. The `sharemgr` command enables you to set and manage share properties on share groups. ZFS shares are automatically designated in the `zfs` share group.

As in previous releases, you can set the `ZFS sharenfs` property on a ZFS file system to share a ZFS file system. For example:

```
# zfs set sharenfs=on tank/home
```

Or, you can use the new `sharemgr add-share` subcommand to share a ZFS file system in the `zfs` share group. For example:

```
# sharemgr add-share -s tank/data zfs
# sharemgr show -vp zfs
zfs nfs=()
  zfs/tank/data
    /tank/data
    /tank/data/1
    /tank/data/2
    /tank/data/3
```

Then, you can use the `sharemgr` command to manage ZFS shares. The following example shows how to use `sharemgr` to set the `nosuid` property on the shared ZFS file systems. You must preface ZFS share paths with `/zfs` designation.

```
# sharemgr set -P nfs -p nosuid=true zfs/tank/data
# sharemgr show -vp zfs
zfs nfs=()
  zfs/tank/data nfs=(nosuid="true")
    /tank/data
    /tank/data/1
    /tank/data/2
    /tank/data/3
```

For more information, see `sharemgr(1M)`.

ZFS Command History (zpool history)

Solaris Express Community Release, build 51: In this Solaris release, ZFS automatically logs successful `zfs` and `zpool` commands that modify pool state information. For example:

zpool history

History for 'newpool':

```
2006-10-23.08:58:22 zpool create -f newpool c1t2d0
2006-10-23.08:59:02 zpool replace -f newpool c1t2d0 c1t3d0
2006-10-23.08:59:54 zpool attach -f newpool c1t3d0 c1t4d0
```

History for 'tank':

```
2006-10-17.12:50:19 zpool create -f tank mirror c0t9d0 c0t10d0 c0t11d0 c0t12d0
```

This feature enables you or Sun support personnel to identify the *exact* set of ZFS commands that was executed to troubleshoot an error scenario.

You can identify a specific storage pool with the `zpool history` command. For example:

zpool history newpool

History for 'newpool':

```
2006-10-23.08:58:22 zpool create -f newpool c1t2d0
2006-10-23.08:59:02 zpool replace -f newpool c1t2d0 c1t3d0
2006-10-23.08:59:54 zpool attach -f newpool c1t3d0 c1t4d0
2006-10-23.10:38:40 zfs create newpool/user1
2006-10-23.11:29:35 zfs destroy newpool/user1
```

The features of the history log are as follows:

- The log cannot be disabled.
- The log is saved persistently on disk, which means the log is saved across system reboots.
- The log is implemented as a ring buffer. The minimum size is 128 Kbytes. The maximum size is 32 Mbytes.
- For smaller pools, the maximum size is capped at 1% of the pool size, where *size* is determined at pool creation time.
- Requires no administration, which means tuning the size of the log or changing the location of the log is unnecessary.

Currently, the `zpool history` command does not record *user-ID*, *hostname*, or *zone-name*.

For more information about troubleshooting ZFS problems, see [“Identifying Problems in ZFS” on page 157](#).

ZFS canmount Property

Solaris Express Community Release, build 48: The new `canmount` property allows you to specify whether a dataset can be mounted by using the `zfs mount` command. For more information, see [“The `canmount` Property” on page 88](#).

ZFS User Properties

Solaris Express Community Release, build 48: In addition to the standard native properties that can either export internal statistics or control ZFS file system behavior, ZFS supports user properties. User properties have no effect on ZFS behavior, but you can use them to annotate datasets with information that is meaningful in your environment.

For more information, see “ZFS User Properties” on page 89.

Setting Properties When Creating ZFS File Systems

Solaris Express Community Release, build 48: In this Solaris release, you can set properties when you create a file system, in addition to setting properties after the file system is created.

The following examples illustrate equivalent syntax:

```
# zfs create tank/home
# zfs set mountpoint=/export/zfs tank/home
# zfs set sharenfs=on tank/home
# zfs set compression=on tank/home

# zfs create -o mountpoint=/export/zfs -o sharenfs=on -o compression=on tank/home
```

Displaying All ZFS File System Information

Solaris Express Community Release, build 48: In this Solaris release, you can use various forms of the `zfs get` command to display information about all datasets if you do not specify a dataset. In previous releases, all dataset information was not retrievable with the `zfs get` command.

For example:

```
# zfs get -s local all
tank/home          atime          off            local
tank/home/bonwick atime          off            local
tank/home/marks    quota          50G           local
```

New `zfs receive -F` Option

Solaris Express Community Release, build 48: In this Solaris release, you can use the new `-F` option to the `zfs receive` command to force a rollback of the file system to the most recent snapshot before doing the receive. Using this option might be necessary when the file system is modified between the time a rollback occurs and the receive is initiated.

For more information, see [“Restoring a ZFS Snapshot”](#) on page 115.

Recursive ZFS Snapshots

Solaris Express Community Release, build 43: When you use the `zfs snapshot` command to create a file system snapshot, you can use the `-r` option to recursively create snapshots for all descendant file systems. In addition, using the `-r` option recursively destroys all descendant snapshots when a snapshot is destroyed. Recursive ZFS snapshots are created quickly as one atomic operation. The snapshots are created together (all at once) or not created at all. The benefit of atomic snapshots operations is that the snapshot data is always taken at one consistent time, even across descendant file systems.

For more information, see [“Creating and Destroying ZFS Snapshots”](#) on page 108.

Double Parity RAID-Z (raidz2)

Solaris Express Community Release, build 42: A redundant RAID-Z configuration can now have either single- or double-parity, which means that one or two device failures can be sustained respectively, without any data loss. You can specify the `raidz2` keyword for a double-parity RAID-Z configuration. Or, you can specify the `raidz` or `raidz1` keyword for a single-parity RAID-Z configuration.

For more information, see [“Creating a Double-Parity RAID-Z Storage Pool”](#) on page 47 or `zpool(1M)`.

Hot Spares for ZFS Storage Pool Devices

Solaris Express Community Release, build 42: The ZFS hot spares feature enables you to identify disks that could be used to replace a failed or faulted device in one or more storage pools. Designating a device as a *hot spare* means that if an active device in the pool fails, the hot spare automatically replaces the failed device. Or, you can manually replace a device in a storage pool with a hot spare.

For more information, see [“Designating Hot Spares in Your Storage Pool”](#) on page 58 and `zpool(1M)`.

Replacing a ZFS File System With a ZFS Clone (`zfs promote`)

Solaris Express Community Release, build 42: The `zfs promote` command enables you to replace an existing ZFS file system with a clone of that file system. This feature is helpful when you want to run tests on an alternative version of a file system and then, make that alternative version of the file system the active file system.

For more information, see [“Replacing a ZFS File System With a ZFS Clone”](#) on page 112 and `zfs(1M)`.

Upgrading ZFS Storage Pools (`zpool upgrade`)

Solaris Express Community Release, build 39: You can upgrade your storage pools to a newer version to take advantage of the latest features by using the `zpool upgrade` command. In addition, the `zpool status` command has been modified to notify you when your pools are running older versions.

For more information, see [“Upgrading ZFS Storage Pools”](#) on page 75 and `zpool(1M)`.

If you want to use the ZFS Administration console on a system with a pool from a previous Solaris release, make sure you upgrade your pools before using the ZFS Administration console. To see if your pools need to be upgraded, use the `zpool status` command. For information about the ZFS Administration console, see [“ZFS Web-Based Management”](#) on page 21.

Using ZFS to Clone Non-Global Zones and Other Enhancements

Solaris Express Community Release, build 39: When the source `zonepath` and the target `zonepath` both reside on ZFS and are in the same pool, `zoneadm clone` now automatically uses the ZFS clone feature to clone a zone. This enhancement means that `zoneadm clone` will take a ZFS snapshot of the source `zonepath` and set up the target `zonepath`. The snapshot is named `SUNWzoneX`, where X is a unique ID used to distinguish between multiple snapshots. The destination zone's `zonepath` is used to name the ZFS clone. A software inventory is performed so that a snapshot used at a future time can be validated by the system. Note that you can still specify that the ZFS `zonepath` be copied instead of the ZFS clone, if desired.

To clone a source zone multiple times, a new parameter added to `zoneadm` allows you to specify that an existing snapshot should be used. The system validates that the existing snapshot is usable on the target. Additionally, the zone install process now has the capability to detect when a ZFS file system can be created for a zone, and the uninstall process can detect when a ZFS file system in a zone can be destroyed. These steps are then performed automatically by the `zoneadm` command.

Do not use the ZFS snapshot features to clone a zone.

For more information, see *System Administration Guide: Solaris Containers-Resource Management and Solaris Zones*.

ZFS Backup and Restore Commands are Renamed

Solaris Express Community Release, build 38: In this Solaris release, the `zfs backup` and `zfs restore` commands are renamed to `zfs send` and `zfs receive` to more accurately describe their function. The function of these commands is to save and restore ZFS data stream representations.

For more information about these commands, see [“Saving and Restoring ZFS Data”](#) on page 113.

Recovering Destroyed Storage Pools

Solaris Express Community Release, build 37: This release includes the `zpool import -D` command, which enables you to recover pools that were previously destroyed with the `zpool destroy` command.

For more information, see [“Recovering Destroyed ZFS Storage Pools”](#) on page 73.

ZFS is Integrated With Fault Manager

Solaris Express Community Release, build 36: This release includes the integration of a ZFS diagnostic engine that is capable of diagnosing and reporting pool failures and device failures. Checksum, I/O, device, and pool errors associated with pool or device failures are also reported.

The diagnostic engine does not include predictive analysis of checksum and I/O errors, nor does it include proactive actions based on fault analysis.

In the event of the ZFS failure, you might see a message similar to the following from `cmd`:

```
SUNW-MSG-ID: ZFS-8000-D3, TYPE: Fault, VER: 1, SEVERITY: Major
EVENT-TIME: Fri Mar 10 11:09:06 MST 2006
PLATFORM: SUNW,Ultra-60, CSN: -, HOSTNAME: neo
SOURCE: zfs-diagnosis, REV: 1.0
EVENT-ID: b55ee13b-cd74-4dff-8aff-ad575c372ef8
DESC: A ZFS device failed. Refer to http://sun.com/msg/ZFS-8000-D3 for more information.
AUTO-RESPONSE: No automated response will occur.
IMPACT: Fault tolerance of the pool may be compromised.
REC-ACTION: Run 'zpool status -x' and replace the bad device.
```

By reviewing the recommended action, which will be to follow the more specific directions in the `zpool status` command, you will be able to quickly identify and resolve the failure.

For an example of recovering from a reported ZFS problem, see [“Repairing a Missing Device” on page 162](#).

New `zpool clear` Command

Solaris Express Community Release, build 36: This release includes the `zpool clear` command for clearing error counts associated with a device or the pool. Previously, error counts were cleared when a device in a pool was brought online with the `zpool online` command. For more information, see `zpool(1M)` and [“Clearing Storage Pool Devices” on page 57](#).

Compact NFSv4 ACL Format

Solaris Express Community Release, build 34: In this release, three NFSv4 ACL formats are available: verbose, positional, and compact. The new compact and positional ACL formats are available to set and display ACLs. You can use the `chmod` command to set all 3 ACL formats. You can use the `ls -V` command to display compact and positional ACL formats and the `ls -v` command to display verbose ACL formats.

For more information, see [“Setting and Displaying ACLs on ZFS Files in Compact Format” on page 139](#), `chmod(1)`, and `ls(1)`.

File System Monitoring Tool (`fsstat`)

Solaris Express Community Release, build 34: A new file system monitoring tool, `fsstat`, is available to report file system operations. Activity can be reported by mount point or by file system type. The following example shows general ZFS file system activity.

```
$ fsstat zfs
new name name attr attr lookup rddir read read write write
file remov chng get set ops ops ops bytes ops bytes
7.82M 5.92M 2.76M 1.02G 3.32M 5.60G 87.0M 363M 1.86T 20.9M 251G zfs
```

For more information, see `fsstat(1M)`.

ZFS Web-Based Management

Solaris Express Community Release, build 28: A web-based ZFS management tool is available to perform many administrative actions. With this tool, you can perform the following tasks:

- Create a new storage pool.

- Add capacity to an existing pool.
- Move (export) a storage pool to another system.
- Import a previously exported storage pool to make it available on another system.
- View information about storage pools.
- Create a file system.
- Create a volume.
- Take a snapshot of a file system or a volume.
- Roll back a file system to a previous snapshot.

You can access the ZFS Administration console through a secure web browser at the following URL:

```
https://system-name:6789/zfs
```

If you type the appropriate URL and are unable to reach the ZFS Administration console, the server might not be started. To start the server, run the following command:

```
# /usr/sbin/smcwebserver start
```

If you want the server to run automatically when the system boots, run the following command:

```
# /usr/sbin/smcwebserver enable
```

Note – You cannot use the Solaris Management Console (smc) to manage ZFS storage pools or file systems.

You will not be able to manage ZFS file systems remotely with the ZFS Administration console because of a change in a recent Solaris Express Community release, which shutdown some network services automatically. Use the following command to enable these services:

```
# netservices open
```

What Is ZFS?

The ZFS file system is a revolutionary new file system that fundamentally changes the way file systems are administered, with features and benefits not found in any other file system available today. ZFS has been designed to be robust, scalable, and simple to administer.

ZFS Pooled Storage

ZFS uses the concept of *storage pools* to manage physical storage. Historically, file systems were constructed on top of a single physical device. To address multiple devices and provide for data redundancy, the concept of a *volume manager* was introduced to provide the image of a single device so that file systems would not have to be modified to take advantage of multiple devices. This design added another layer of complexity and ultimately prevented certain file system advances, because the file system had no control over the physical placement of data on the virtualized volumes.

ZFS eliminates the volume management altogether. Instead of forcing you to create virtualized volumes, ZFS aggregates devices into a storage pool. The storage pool describes the physical characteristics of the storage (device layout, data redundancy, and so on,) and acts as an arbitrary data store from which file systems can be created. File systems are no longer constrained to individual devices, allowing them to share space with all file systems in the pool. You no longer need to predetermine the size of a file system, as file systems grow automatically within the space allocated to the storage pool. When new storage is added, all file systems within the pool can immediately use the additional space without additional work. In many ways, the storage pool acts as a virtual memory system. When a memory DIMM is added to a system, the operating system doesn't force you to invoke some commands to configure the memory and assign it to individual processes. All processes on the system automatically use the additional memory.

Transactional Semantics

ZFS is a transactional file system, which means that the file system state is always consistent on disk. Traditional file systems overwrite data in place, which means that if the machine loses power, for example, between the time a data block is allocated and when it is linked into a directory, the file system will be left in an inconsistent state. Historically, this problem was solved through the use of the `fsck` command. This command was responsible for going through and verifying file system state, making an attempt to repair any inconsistencies in the process. This problem caused great pain to administrators and was never guaranteed to fix all possible problems. More recently, file systems have introduced the concept of *journaling*. The journaling process records action in a separate journal, which can then be replayed safely if a system crash occurs. This process introduces unnecessary overhead, because the data needs to be written twice, and often results in a new set of problems, such as when the journal can't be replayed properly.

With a transactional file system, data is managed using *copy on write* semantics. Data is never overwritten, and any sequence of operations is either entirely committed or entirely ignored. This mechanism means that the file system can never be corrupted through accidental loss of power or a system crash. So, no need for a `fsck` equivalent exists. While the most recently

written pieces of data might be lost, the file system itself will always be consistent. In addition, synchronous data (written using the `O_DSYNC` flag) is always guaranteed to be written before returning, so it is never lost.

Checksums and Self-Healing Data

With ZFS, all data and metadata is checksummed using a user-selectable algorithm. Traditional file systems that do provide checksumming have performed it on a per-block basis, out of necessity due to the volume management layer and traditional file system design. The traditional design means that certain failure modes, such as writing a complete block to an incorrect location, can result in properly checksummed data that is actually incorrect. ZFS checksums are stored in a way such that these failure modes are detected and can be recovered from gracefully. All checksumming and data recovery is done at the file system layer, and is transparent to applications.

In addition, ZFS provides for self-healing data. ZFS supports storage pools with varying levels of data redundancy, including mirroring and a variation on RAID-5. When a bad data block is detected, ZFS fetches the correct data from another redundant copy, and repairs the bad data, replacing it with the good copy.

Unparalleled Scalability

ZFS has been designed from the ground up to be the most scalable file system, ever. The file system itself is 128-bit, allowing for 256 quadrillion zettabytes of storage. All metadata is allocated dynamically, so no need exists to pre-allocate inodes or otherwise limit the scalability of the file system when it is first created. All the algorithms have been written with scalability in mind. Directories can have up to 2^{48} (256 trillion) entries, and no limit exists on the number of file systems or number of files that can be contained within a file system.

ZFS Snapshots

A *snapshot* is a read-only copy of a file system or volume. Snapshots can be created quickly and easily. Initially, snapshots consume no additional space within the pool.

As data within the active dataset changes, the snapshot consumes space by continuing to reference the old data. As a result, the snapshot prevents the data from being freed back to the pool.

Simplified Administration

Most importantly, ZFS provides a greatly simplified administration model. Through the use of hierarchical file system layout, property inheritance, and automanagement of mount points and NFS share semantics, ZFS makes it easy to create and manage file systems without needing

multiple commands or editing configuration files. You can easily set quotas or reservations, turn compression on or off, or manage mount points for numerous file systems with a single command. Devices can be examined or repaired without having to understand a separate set of volume manager commands. You can take an unlimited number of instantaneous snapshots of file systems. You can backup and restore individual file systems.

ZFS manages file systems through a hierarchy that allows for this simplified management of properties such as quotas, reservations, compression, and mount points. In this model, file systems become the central point of control. File systems themselves are very cheap (equivalent to a new directory), so you are encouraged to create a file system for each user, project, workspace, and so on. This design allows you to define fine-grained management points.

ZFS Terminology

This section describes the basic terminology used throughout this book:

checksum	A 256-bit hash of the data in a file system block. The checksum capability can range from the simple and fast fletcher2 (the default) to cryptographically strong hashes such as SHA256.
clone	A file system whose initial contents are identical to the contents of a snapshot. For information about clones, see “Overview of ZFS Clones” on page 111 .
dataset	A generic name for the following ZFS entities: clones, file systems, snapshots, or volumes. Each dataset is identified by a unique name in the ZFS namespace. Datasets are identified using the following format: <i>pool/path[@snapshot]</i> <i>pool</i> Identifies the name of the storage pool that contains the dataset <i>path</i> Is a slash-delimited path name for the dataset object <i>snapshot</i> Is an optional component that identifies a snapshot of a dataset For more information about datasets, see Chapter 5 .
file system	A dataset that contains a standard POSIX file system. For more information about file systems, see Chapter 5 .
mirror	A virtual device that stores identical copies of data on two or more disks. If any disk in a mirror fails, any other disk in that mirror can provide the same data.

pool	<p>A logical group of devices describing the layout and physical characteristics of the available storage. Space for datasets is allocated from a pool.</p> <p>For more information about storage pools, see Chapter 4.</p>
RAID-Z	<p>A virtual device that stores data and parity on multiple disks, similar to RAID-5. For more information about RAID-Z, see “RAID-Z Storage Pool Configuration” on page 44.</p>
resilvering	<p>The process of transferring data from one device to another device is known as <i>resilvering</i>. For example, if a mirror component is replaced or taken offline, the data from the up-to-date mirror component is copied to the newly restored mirror component. This process is referred to as <i>mirror resynchronization</i> in traditional volume management products.</p> <p>For more information about ZFS resilvering, see “Viewing Resilvering Status” on page 168.</p>
snapshot	<p>A read-only image of a file system or volume at a given point in time.</p> <p>For more information about snapshots, see “Overview of ZFS Snapshots” on page 107.</p>
virtual device	<p>A logical device in a pool, which can be a physical device, a file, or a collection of devices.</p> <p>For more information about virtual devices, see “Identifying Virtual Devices in a Storage Pool” on page 43.</p>
volume	<p>A dataset used to emulate a physical device. For example, you can create an emulated volume as a swap device.</p> <p>For more information about emulated volumes, see “ZFS Volumes” on page 143.</p>

ZFS Component Naming Requirements

Each ZFS component must be named according to the following rules:

- Empty components are not allowed.
- Each component can only contain alphanumeric characters in addition to the following four special characters:
 - Underscore (`_`)
 - Hyphen (`-`)
 - Colon (`:`)
 - Period (`.`)

- Pool names must begin with a letter, except that the beginning sequence `c[0-9]` is not allowed. In addition, pool names that begin with `mirror`, `raidz`, or `spare` are not allowed as these names are reserved.
- Dataset names must begin with an alphanumeric character.

Getting Started With ZFS

This chapter provides step-by-step instructions on setting up simple ZFS configurations. By the end of this chapter, you should have a basic idea of how the ZFS commands work, and should be able to create simple pools and file systems. This chapter is not designed to be a comprehensive overview and refers to later chapters for more detailed information.

The following sections are provided in this chapter:

- “ZFS Hardware and Software Requirements and Recommendations” on page 29
- “Creating a Basic ZFS File System” on page 30
- “Creating a ZFS Storage Pool” on page 31
- “Creating a ZFS File System Hierarchy” on page 32

ZFS Hardware and Software Requirements and Recommendations

Make sure you review the following hardware and software requirements and recommendations before attempting to use the ZFS software:

- A SPARC™ or x86 system that is running the Solaris™ Nevada release, build 27 or later.
- The minimum disk size is 128 Mbytes. The minimum amount of disk space required for a storage pool is approximately 64 Mbytes.
- Currently, the minimum amount of memory recommended to install a Solaris system is 512 Mbytes. However, for good ZFS performance, at least one Gbyte or more of memory is recommended.
- If you create a mirrored disk configuration, multiple controllers are recommended.

Creating a Basic ZFS File System

ZFS administration has been designed with simplicity in mind. Among the goals of the ZFS design is to reduce the number of commands needed to create a usable file system. When you create a new pool, a new ZFS file system is created and mounted automatically.

The following example illustrates how to create a non-redundant storage pool named `tank` and a ZFS file system name `tank` in one command. Assume that the whole disk `/dev/dsk/c1t0d0` is available for use.

```
# zpool create tank c1t0d0
```

Note – This command creates a non-redundant pool. A non-redundant pool configuration is not recommended for production environments even if the single storage object is presented from a hardware RAID array or from a software volume manager. ZFS can only detect errors in these configurations. ZFS can corrects error in pool configurations with redundant data. For more information, about redundant ZFS pool configurations, see [“Replication Features of a ZFS Storage Pool” on page 44](#).

The new ZFS file system, `tank`, can use as much of the disk space on `c1t0d0` as needed, and is automatically mounted at `/tank`.

```
# mkfile 100m /tank/foo
# df -h /tank
```

Filesystem	size	used	avail	capacity	Mounted on
tank	80G	100M	80G	1%	/tank

Within a pool, you will probably want to create additional file systems. File systems provide points of administration that allow you to manage different sets of data within the same pool.

The following example illustrates how to create a file system named `fs` in the storage pool `tank`. Assume that the whole disk `/dev/dsk/c1t0d0` is available for use.

```
# zpool create tank mirror c1t0d0 c2t0d0
# zfs create tank/fs
```

The new ZFS file system, `tank/fs`, can use as much of the disk space on `c1t0d0` as needed, and is automatically mounted at `/tank/fs`.

```
# mkfile 100m /tank/fs/foo
# df -h /tank/fs
```

Filesystem	size	used	avail	capacity	Mounted on
tank/fs	80G	100M	80G	1%	/tank/fs

In most cases, you will probably want to create and organize a hierarchy of file systems that matches your organizational needs. For more information about creating a hierarchy of ZFS file systems, see [“Creating a ZFS File System Hierarchy” on page 32](#).

Creating a ZFS Storage Pool

The previous example illustrates the simplicity of ZFS. The remainder of this chapter demonstrates a more complete example similar to what you would encounter in your environment. The first tasks are to identify your storage requirements and create a storage pool. The pool describes the physical characteristics of the storage and must be created before any file systems are created.

▼ How to Identify Storage Requirements for Your ZFS Storage Pool

1 Determine available devices.

Before creating a storage pool, you must determine which devices will store your data. These devices must be disks of at least 128 Mbytes in size, and they must not be in use by other parts of the operating system. The devices can be individual slices on a preformatted disk, or they can be entire disks that ZFS formats as a single large slice.

For the storage example used in [“How to Create a ZFS Storage Pool” on page 32](#), assume that the whole disks `/dev/dsk/c1t0d0` and `/dev/dsk/c1t1d0` are available for use.

For more information about disks and how they are used and labeled, see [“Using Disks in a ZFS Storage Pool” on page 41](#).

2 Choose data replication.

ZFS supports multiple types of data replication, which determines what types of hardware failures the pool can withstand. ZFS supports nonredundant (striped) configurations, as well as mirroring and RAID-Z (a variation on RAID-5).

For the storage example used in [“How to Create a ZFS Storage Pool” on page 32](#), basic mirroring of two available disks is used.

For more information about ZFS replication features, see [“Replication Features of a ZFS Storage Pool” on page 44](#).

▼ How to Create a ZFS Storage Pool

1 Become root or assume an equivalent role with the appropriate ZFS rights profile.

For more information about the ZFS rights profiles, see [“ZFS Rights Profiles”](#) on page 152.

2 Pick a pool name.

The pool name is used to identify the storage pool when you are using the `zpool` or `zfs` commands. Most systems require only a single pool, so you can pick any name that you prefer, provided it satisfies the naming requirements outlined in [“ZFS Component Naming Requirements”](#) on page 26.

3 Create the pool.

For example, create a mirrored pool that is named `tank`.

```
# zpool create tank mirror c1t0d0 c1t1d0
```

If one or more devices contains another file system or is otherwise in use, the command cannot create the pool.

For more information about creating storage pools, see [“Creating a ZFS Storage Pool”](#) on page 46.

For more information about how device usage is determined, see [“Detecting in Use Devices”](#) on page 48.

4 View the results.

You can determine if your pool was successfully created by using the `zpool list` command.

```
# zpool list
NAME                SIZE  USED  AVAIL  CAP  HEALTH  ALROOT
tank                 80G   137K   80G    0%  ONLINE  -
```

For more information about viewing pool status, see [“Querying ZFS Storage Pool Status”](#) on page 62.

Creating a ZFS File System Hierarchy

After creating a storage pool to store your data, you can create your file system hierarchy. Hierarchies are simple yet powerful mechanisms for organizing information. They are also very familiar to anyone who has used a file system.

ZFS allows file systems to be organized into arbitrary hierarchies, where each file system has only a single parent. The root of the hierarchy is always the pool name. ZFS leverages this hierarchy by supporting property inheritance so that common properties can be set quickly and easily on entire trees of file systems.

▼ How to Determine Your ZFS File System Hierarchy

1 Pick the file system granularity.

ZFS file systems are the central point of administration. They are lightweight and can be created easily. A good model to use is a file system per user or project, as this model allows properties, snapshots, and backups to be controlled on a per-user or per-project basis.

Two ZFS file systems, `bonwick` and `billm`, are created in “[How to Create ZFS File Systems](#)” on [page 33](#).

For more information on managing file systems, see [Chapter 5](#).

2 Group similar file systems.

ZFS allows file systems to be organized into hierarchies so that similar file systems can be grouped. This model provides a central point of administration for controlling properties and administering file systems. Similar file systems should be created under a common name.

For the example in “[How to Create ZFS File Systems](#)” on [page 33](#), the two file systems are placed under a file system named `home`.

3 Choose the file system properties.

Most file system characteristics are controlled by using simple properties. These properties control a variety of behavior, including where the file systems are mounted, how they are shared, if they use compression, and if any quotas are in effect.

For the example in “[How to Create ZFS File Systems](#)” on [page 33](#), all home directories are mounted at `/export/zfs/user`, are shared by using NFS, and with compression enabled. In addition, a quota of 10 Gbytes on `bonwick` is enforced.

For more information about properties, see “[Introducing ZFS Properties](#)” on [page 81](#).

▼ How to Create ZFS File Systems

1 Become root or assume an equivalent role with the appropriate ZFS rights profile.

For more information about the ZFS rights profiles, see “[ZFS Rights Profiles](#)” on [page 152](#).

2 Create the desired hierarchy.

In this example, a file system that acts as a container for individual file systems is created.

```
# zfs create tank/home
```

Next, individual file systems are grouped under the `home` file system in the pool `tank`.

3 Set the inherited properties.

After the file system hierarchy is established, set up any properties that should be shared among all users:

```
# zfs set mountpoint=/export/zfs tank/home
# zfs set sharenfs=on tank/home
# zfs set compression=on tank/home
# zfs get compression tank/home
NAME                PROPERTY           VALUE              SOURCE
tank/home           compression        on                 local
```

A new feature is available that enables you to set file system properties when the file system is created. For example:

```
# zfs create -o mountpoint=/export/zfs -o sharenfs=on -o compression=on tank/home
```

For more information about properties and property inheritance, see [“Introducing ZFS Properties” on page 81](#).

4 Create the individual file systems.

Note that the file systems could have been created and then the properties could have been changed at the home level. All properties can be changed dynamically while file systems are in use.

```
# zfs create tank/home/bonwick
# zfs create tank/home/billm
```

These file systems inherit their property settings from their parent, so they are automatically mounted at `/export/zfs/user` and are NFS shared. You do not need to edit the `/etc/vfstab` or `/etc/dfs/dfstab` file.

For more information about creating file systems, see [“Creating a ZFS File System” on page 78](#).

For more information about mounting and sharing file systems, see [“Mounting and Sharing ZFS File Systems” on page 97](#).

5 Set the file system-specific properties.

In this example, user `bonwick` is assigned a quota of 10 Gbytes. This property places a limit on the amount of space he can consume, regardless of how much space is available in the pool.

```
# zfs set quota=10G tank/home/bonwick
```

6 View the results.

View available file system information by using the `zfs list` command:

```
# zfs list
NAME                USED  AVAIL  REFER  MOUNTPOINT
tank                92.0K 67.0G  9.5K   /tank
tank/home           24.0K 67.0G   8K    /export/zfs
tank/home/billm      8K    67.0G   8K    /export/zfs/billm
```

```
tank/home/bonwick      8K  10.0G      8K  /export/zfs/bonwick
```

Note that the user `bonwick` only has 10 Gbytes of space available, while the user `billm` can use the full pool (67 Gbytes).

For more information about viewing file system status, see [“Querying ZFS File System Information” on page 90](#).

For more information about how space is used and calculated, see [“ZFS Space Accounting” on page 38](#).

ZFS and Traditional File System Differences

This chapter discusses some significant differences between ZFS and traditional file systems. Understanding these key differences can help reduce confusion when using traditional tools to interact with ZFS.

The following sections are provided in this chapter:

- “ZFS File System Granularity” on page 37
- “ZFS Space Accounting” on page 38
- “Out of Space Behavior” on page 38
- “Mounting ZFS File Systems” on page 39
- “Traditional Volume Management” on page 39
- “New Solaris ACL Model” on page 39

ZFS File System Granularity

Historically, file systems have been constrained to one device so that the file systems themselves have been constrained to the size of the device. Creating and re-creating traditional file systems because of size constraints are time-consuming and sometimes difficult. Traditional volume management products helped manage this process.

Because ZFS file systems are not constrained to specific devices, they can be created easily and quickly, similar to the way directories are created. ZFS file systems grow automatically within the space allocated to the storage pool.

Instead of creating one file system, such as `/export/home`, to manage many user subdirectories, you can create one file system per user. In addition, ZFS provides a file system hierarchy so that you can easily set up and manage many file systems by applying properties that can be inherited by file systems contained within the hierarchy.

For an example of creating a file system hierarchy, see “[Creating a ZFS File System Hierarchy](#)” on page 32.

ZFS Space Accounting

ZFS is based on a concept of pooled storage. Unlike typical file systems, which are mapped to physical storage, all ZFS file systems in a pool share the available storage in the pool. So, the available space reported by utilities such as `df` might change even when the file system is inactive, as other file systems in the pool consume or release space. Note that the maximum file system size can be limited by using quotas. For information about quotas, see [“Setting Quotas on ZFS File Systems” on page 103](#). Space can be guaranteed to a file system by using reservations. For information about reservations, see [“Setting Reservations on ZFS File Systems” on page 104](#). This model is very similar to the NFS model, where multiple directories are mounted from the same file system (consider `/home`).

All metadata in ZFS is allocated dynamically. Most other file systems pre-allocate much of their metadata. As a result, an immediate space cost at file system creation for this metadata is required. This behavior also means that the total number of files supported by the file systems is predetermined. Because ZFS allocates its metadata as it needs it, no initial space cost is required, and the number of files is limited only by the available space. The output from the `df -g` command must be interpreted differently for ZFS than other file systems. The `total files` reported is only an estimate based on the amount of storage that is available in the pool.

ZFS is a transactional file system. Most file system modifications are bundled into transaction groups and committed to disk asynchronously. Until these modifications are committed to disk, they are termed *pending changes*. The amount of space used, available, and referenced by a file or file system does not consider pending changes. Pending changes are generally accounted for within a few seconds. Even committing a change to disk by using `fsync(3c)` or `O_SYNC` does not necessarily guarantee that the space usage information is updated immediately.

Out of Space Behavior

File system snapshots are inexpensive and easy to create in ZFS. Most likely, snapshots will be common in most ZFS environments. For information about ZFS snapshots, see [Chapter 6](#).

The presence of snapshots can cause some unexpected behavior when you attempt to free space. Typically, given appropriate permissions, you can remove a file from a full file system, and this action results in more space becoming available in the file system. However, if the file to be removed exists in a snapshot of the file system, then no space is gained from the file deletion. The blocks used by the file continue to be referenced from the snapshot.

As a result, the file deletion can consume more disk space, because a new version of the directory needs to be created to reflect the new state of the namespace. This behavior means that you can get an unexpected `ENOSPC` or `EDQUOT` when attempting to remove a file.

Mounting ZFS File Systems

ZFS is designed to reduce complexity and ease administration. For example, with existing file systems you must edit the `/etc/vfstab` file every time you add a new file system. ZFS has eliminated this requirement by automatically mounting and unmounting file systems according to the properties of the dataset. You do not need to manage ZFS entries in the `/etc/vfstab` file.

For more information about mounting and sharing ZFS file systems, see [“Mounting and Sharing ZFS File Systems” on page 97](#).

Traditional Volume Management

As described in [“ZFS Pooled Storage” on page 23](#), ZFS eliminates the need for a separate volume manager. ZFS operates on raw devices, so it is possible to create a storage pool comprised of logical volumes, either software or hardware. This configuration is not recommended, as ZFS works best when it uses raw physical devices. Using logical volumes might sacrifice performance, reliability, or both, and should be avoided.

New Solaris ACL Model

Previous versions of the Solaris OS supported an ACL implementation that was primarily based on the POSIX ACL draft specification. The POSIX-draft based ACLs are used to protect UFS files. A new ACL model that is based on the NFSv4 specification is used to protect ZFS files.

The main differences of the new Solaris ACL model are as follows:

- Based on the NFSv4 specification and are similar to NT-style ACLs.
- Much more granular set of access privileges.
- Set and displayed with the `chmod` and `ls` commands rather than the `setfacl` and `getfacl` commands.
- Richer inheritance semantics for designating how access privileges are applied from directory to subdirectories, and so on.

For more information about using ACLs with ZFS files, see [Chapter 7](#).

Managing ZFS Storage Pools

This chapter describes how to create and administer ZFS storage pools.

The following sections are provided in this chapter:

- “Components of a ZFS Storage Pool” on page 41
- “Creating and Destroying ZFS Storage Pools” on page 46
- “Managing Devices in ZFS Storage Pools” on page 51
- “Querying ZFS Storage Pool Status” on page 62
- “Migrating ZFS Storage Pools” on page 68
- “Upgrading ZFS Storage Pools” on page 75

Components of a ZFS Storage Pool

The following sections provide detailed information about the following storage pool components:

- “Using Disks in a ZFS Storage Pool” on page 41
- “Using Files in a ZFS Storage Pool” on page 43
- “Identifying Virtual Devices in a Storage Pool” on page 43

Using Disks in a ZFS Storage Pool

The most basic element of a storage pool is a piece of physical storage. Physical storage can be any block device of at least 128 Mbytes in size. Typically, this device is a hard drive that is visible to the system in the `/dev/dsk` directory.

A storage device can be a whole disk (`c1t0d0`) or an individual slice (`c0t0d0s7`). The recommended mode of operation is to use an entire disk, in which case the disk does not need to be specially formatted. ZFS formats the disk using an EFI label to contain a single, large slice. When used in this way, the partition table that is displayed by the `format` command appears similar to the following:

Current partition table (original):

Total disk sectors available: 71670953 + 16384 (reserved sectors)

Part	Tag	Flag	First Sector	Size	Last Sector
0	usr	wm	34	34.18GB	71670953
1	unassigned	wm	0	0	0
2	unassigned	wm	0	0	0
3	unassigned	wm	0	0	0
4	unassigned	wm	0	0	0
5	unassigned	wm	0	0	0
6	unassigned	wm	0	0	0
7	unassigned	wm	0	0	0
8	reserved	wm	71670954	8.00MB	71687337

To use whole disks, the disks must be named using the standard Solaris convention, such as `/dev/dsk/cXtXdXsX`. Some third-party drivers use a different naming convention or place disks in a location other than the `/dev/dsk` directory. To use these disks, you must manually label the disk and provide a slice to ZFS.

ZFS applies an EFI label when you create a storage pool with whole disks. Disks can be labeled with a traditional Solaris VTOC label when you create a storage pool with a disk slice.

Slices should only be used under the following conditions:

- The device name is nonstandard.
- A single disk is shared between ZFS and another file system, such as UFS.
- A disk is used as a swap or a dump device.

Disks can be specified by using either the full path, such as `/dev/dsk/c1t0d0`, or a shorthand name that consists of the device name within the `/dev/dsk` directory, such as `c1t0d0`. For example, the following are valid disk names:

- `c1t0d0`
- `/dev/dsk/c1t0d0`
- `c0t0d6s2`
- `/dev/foo/disk`

Using whole physical disks is the simplest way to create ZFS storage pools. ZFS configurations become progressively more complex, from management, reliability, and performance perspectives, when you build pools from disk slices, LUNs in hardware RAID arrays, or volumes presented by software-based volume managers. The following considerations might help you determine how to configure ZFS with other hardware or software storage solutions:

- If you construct ZFS configurations on top of LUNs from hardware RAID arrays, you need to understand the relationship between ZFS redundancy features and the redundancy features offered by the array. Certain configurations might provide adequate redundancy and performance, but other configurations might not.

- You can construct logical devices for ZFS using volumes presented by software-based volume managers, such as Solaris™ Volume Manager (SVM) or Veritas Volume Manager (VxVM). However, these configurations are not recommended. While ZFS functions properly on such devices, less-than-optimal performance might be the result.

For additional information about storage pool recommendations, see the ZFS best practices site:

http://www.solarisinternals.com/wiki/index.php/ZFS_Best_Practices_Guide

Disks are identified both by their path and by their device ID, if available. This method allows devices to be reconfigured on a system without having to update any ZFS state. If a disk is switched between controller 1 and controller 2, ZFS uses the device ID to detect that the disk has moved and should now be accessed using controller 2. The device ID is unique to the drive's firmware. While unlikely, some firmware updates have been known to change device IDs. If this situation happens, ZFS can still access the device by path and update the stored device ID automatically. If you inadvertently change both the path and the ID of the device, then export and re-import the pool in order to use it.

Using Files in a ZFS Storage Pool

ZFS also allows you to use UFS files as virtual devices in your storage pool. This feature is aimed primarily at testing and enabling simple experimentation, not for production use. The reason is that **any use of files relies on the underlying file system for consistency**. If you create a ZFS pool backed by files on a UFS file system, then you are implicitly relying on UFS to guarantee correctness and synchronous semantics.

However, files can be quite useful when you are first trying out ZFS or experimenting with more complicated layouts when not enough physical devices are present. All files must be specified as complete paths and must be at least 128 Mbytes in size. If a file is moved or renamed, the pool must be exported and re-imported in order to use it, as no device ID is associated with files by which they can be located.

Identifying Virtual Devices in a Storage Pool

Each storage pool is comprised of one or more virtual devices. A *virtual device* is an internal representation of the storage pool that describes the layout of physical storage and its fault characteristics. As such, a virtual device represents the disk devices or files that are used to create the storage pool.

Two top-level virtual devices provide data redundancy: mirror and RAID-Z virtual devices. These virtual devices consist of disks, disk slices, or files.

Disks, disk slices, or files that are used in pools outside of mirrors and RAID-Z virtual devices, function as top-level virtual devices themselves.

Storage pools typically contain multiple top-level virtual devices. ZFS dynamically stripes data among all of the top-level virtual devices in a pool.

Replication Features of a ZFS Storage Pool

ZFS provides data redundancy, as well as self-healing properties, in a mirrored and a RAID-Z configuration.

- [“Mirrored Storage Pool Configuration” on page 44](#)
- [“RAID-Z Storage Pool Configuration” on page 44](#)
- [“Self-Healing Data in a Redundant Configuration” on page 45](#)
- [“Dynamic Striping in a Storage Pool” on page 45](#)

Mirrored Storage Pool Configuration

A mirrored storage pool configuration requires at least two disks, preferably on separate controllers. Many disks can be used in a mirrored configuration. In addition, you can create more than one mirror in each pool. Conceptually, a simple mirrored configuration would look similar to the following:

```
mirror c1t0d0 c2t0d0
```

Conceptually, a more complex mirrored configuration would look similar to the following:

```
mirror c1t0d0 c2t0d0 c3t0d0 mirror c4t0d0 c5t0d0 c6t0d0
```

For information about creating a mirrored storage pool, see [“Creating a Mirrored Storage Pool” on page 47](#).

RAID-Z Storage Pool Configuration

In addition to a mirrored storage pool configuration, ZFS provides a RAID-Z configuration with either single or double parity fault tolerance. Single-parity RAID-Z is similar to RAID-5. Double-parity RAID-Z is similar to RAID-6.

All traditional RAID-5-like algorithms (RAID-4, RAID-5, RAID-6, RDP, and EVEN-ODD, for example) suffer from a problem known as the “RAID-5 write hole.” If only part of a RAID-5 stripe is written, and power is lost before all blocks have made it to disk, the parity will remain out of sync with the data, and therefore useless, forever (unless a subsequent full-stripe write overwrites it). In RAID-Z, ZFS uses variable-width RAID stripes so that all writes are full-stripe writes. This design is only possible because ZFS integrates file system and device management in such a way that the file system's metadata has enough information about the underlying data redundancy model to handle variable-width RAID stripes. RAID-Z is the world's first software-only solution to the RAID-5 write hole.

A RAID-Z configuration with N disks of size X with P parity disks can hold approximately $(N-P)*X$ bytes and can withstand one device failing before data integrity is compromised. You need at least two disks for a single-parity RAID-Z configuration and at least three disks for a double-parity RAID-Z configuration. For example, if you have three disks in a single-parity RAID-Z configuration, parity data occupies space equal to one of the three disks. Otherwise, no special hardware is required to create a RAID-Z configuration.

Conceptually, a RAID-Z configuration with three disks would look similar to the following:

```
raidz c1t0d0 c2t0d0 c3t0d0
```

A more complex conceptual RAID-Z configuration would look similar to the following:

```
raidz c1t0d0 c2t0d0 c3t0d0 c4t0d0 c5t0d0 c6t0d0 c7t0d0 raidz c8t0d0 c9t0d0 c10t0d0 c11t0d0
c12t0d0 c13t0d0 c14t0d0
```

If you are creating a RAID-Z configuration with many disks, as in this example, a RAID-Z configuration with 14 disks is better split into a two 7-disk groupings. RAID-Z configurations with single-digit groupings of disks should perform better.

For information about creating a RAID-Z storage pool, see “Creating a Single-Parity RAID-Z Storage Pool” on page 47 or “Creating a Double-Parity RAID-Z Storage Pool” on page 47.

For more information about choosing between a mirrored configuration or a RAID-Z configuration based on performance and space considerations, see the following blog:

http://blogs.sun.com/roller/page/roch?entry=when_to_and_not_to

For additional information on RAIDZ storage pool recommendations, see the ZFS best practices site:

http://www.solarisinternals.com/wiki/index.php/ZFS_Best_Practices_Guide

Self-Healing Data in a Redundant Configuration

ZFS provides for self-healing data in a mirrored or RAID-Z configuration.

When a bad data block is detected, not only does ZFS fetch the correct data from another redundant copy, but it also repairs the bad data by replacing it with the good copy.

Dynamic Striping in a Storage Pool

For each virtual device that is added to the pool, ZFS dynamically stripes data across all available devices. The decision about where to place data is done at write time, so no fixed width stripes are created at allocation time.

When virtual devices are added to a pool, ZFS gradually allocates data to the new device in order to maintain performance and space allocation policies. Each virtual device can also be a mirror or a RAID-Z device that contains other disk devices or files. This configuration allows for flexibility in controlling the fault characteristics of your pool. For example, you could create the following configurations out of 4 disks:

- Four disks using dynamic striping
- One four-way RAID-Z configuration
- Two two-way mirrors using dynamic striping

While ZFS supports combining different types of virtual devices within the same pool, this practice is not recommended. For example, you can create a pool with a two-way mirror and a three-way RAID-Z configuration. However, your fault tolerance is as good as your worst virtual device, RAID-Z in this case. The recommended practice is to use top-level virtual devices of the same type with the same redundancy level in each device.

Creating and Destroying ZFS Storage Pools

The following sections describe different scenarios for creating and destroying ZFS storage pools.

- [“Creating a ZFS Storage Pool” on page 46](#)
- [“Handling ZFS Storage Pool Creation Errors” on page 48](#)
- [“Destroying ZFS Storage Pools” on page 50](#)

By design, creating and destroying pools is fast and easy. However, be cautious when doing these operations. Although checks are performed to prevent using devices known to be in use in a new pool, ZFS cannot always know when a device is already in use. Destroying a pool is even easier. Use `zpool destroy` with caution. This is a simple command with significant consequences. .

Creating a ZFS Storage Pool

To create a storage pool, use the `zpool create` command. This command takes a pool name and any number of virtual devices as arguments. The pool name must satisfy the naming conventions outlined in [“ZFS Component Naming Requirements” on page 26](#).

Creating a Basic Storage Pool

The following command creates a new pool named `tank` that consists of the disks `c1t0d0` and `c1t1d0`:

```
# zpool create tank c1t0d0 c1t1d0
```

These whole disks are found in the `/dev/dsk` directory and are labelled appropriately by ZFS to contain a single, large slice. Data is dynamically striped across both disks.

Creating a Mirrored Storage Pool

To create a mirrored pool, use the `mirror` keyword, followed by any number of storage devices that will comprise the mirror. Multiple mirrors can be specified by repeating the `mirror` keyword on the command line. The following command creates a pool with two, two-way mirrors:

```
# zpool create tank mirror c1d0 c2d0 mirror c3d0 c4d0
```

The second `mirror` keyword indicates that a new top-level virtual device is being specified. Data is dynamically striped across both mirrors, with data being redundant between each disk appropriately.

Creating a Single-Parity RAID-Z Storage Pool

Creating a single-parity RAID-Z pool is identical to creating a mirrored pool, except that the `raidz` or `raidz1` keyword is used instead of `mirror`. The following example shows how to create a pool with a single RAID-Z device that consists of five disks:

```
# zpool create tank raidz c1t0d0 c2t0d0 c3t0d0 c4t0d0 /dev/dsk/c5t0d0
```

This example demonstrates that disks can be specified by using their full paths. The `/dev/dsk/c5t0d0` device is identical to the `c5t0d0` device.

A similar configuration could be created with disk slices. For example:

```
# zpool create tank raidz c1t0d0s0 c2t0d0s0 c3t0d0s0 c4t0d0s0 c5t0d0s0
```

However, the disks must be preformatted to have an appropriately sized slice zero.

For more information about a RAID-Z configuration, see [“RAID-Z Storage Pool Configuration” on page 44](#).

Creating a Double-Parity RAID-Z Storage Pool

You can create a double-parity RAID-Z configuration by using the `raidz2` keyword when the pool is created. For example:

```
# zpool create tank raidz2 c1t0d0 c2t0d0 c3t0d0
# zpool status -v tank
  pool: tank
  state: ONLINE
  scrub: none requested
config:
```

NAME	STATE	READ	WRITE	CKSUM
tank	ONLINE	0	0	0

```

raidz2      ONLINE      0      0      0
c1t0d0     ONLINE      0      0      0
c2t0d0     ONLINE      0      0      0
c3t0d0     ONLINE      0      0      0

```

errors: No known data errors

Handling ZFS Storage Pool Creation Errors

Pool creation errors can occur for many reasons. Some of these reasons are obvious, such as when a specified device doesn't exist, while other reasons are more subtle.

Detecting in Use Devices

Before formatting a device, ZFS first determines if the disk is in use by ZFS or some other part of the operating system. If the disk is in use, you might see errors such as the following:

```

# zpool create tank c1t0d0 c1t1d0
invalid vdev specification
use '-f' to override the following errors:
/dev/dsk/c1t0d0s0 is currently mounted on /. Please see umount(1M).
/dev/dsk/c1t0d0s1 is currently mounted on swap. Please see swap(1M).
/dev/dsk/c1t1d0s0 is part of active ZFS pool zeepool. Please see zpool(1M).

```

Some of these errors can be overridden by using the `-f` option, but most errors cannot. The following uses cannot be overridden by using the `-f` option, and you must manually correct them:

Mounted file system	The disk or one of its slices contains a file system that is currently mounted. To correct this error, use the <code>umount</code> command.
File system in <code>/etc/vfstab</code>	The disk contains a file system that is listed in the <code>/etc/vfstab</code> file, but the file system is not currently mounted. To correct this error, remove or comment out the line in the <code>/etc/vfstab</code> file.
Dedicated dump device	The disk is in use as the dedicated dump device for the system. To correct this error, use the <code>dumpadm</code> command.
Part of a ZFS pool	The disk or file is part of an active ZFS storage pool. To correct this error, use the <code>zpool</code> command to destroy the pool.

The following in-use checks serve as helpful warnings and can be overridden by using the `-f` option to create the pool:

Contains a file system	The disk contains a known file system, though it is not mounted and doesn't appear to be in use.
Part of volume	The disk is part of an SVM volume.

Live upgrade	The disk is in use as an alternate boot environment for Solaris Live Upgrade.
Part of exported ZFS pool	The disk is part of a storage pool that has been exported or manually removed from a system. In the latter case, the pool is reported as potentially active, as the disk might or might not be a network-attached drive in use by another system. Be cautious when overriding a potentially active pool.

The following example demonstrates how the `-f` option is used:

```
# zpool create tank c1t0d0
invalid vdev specification
use '-f' to override the following errors:
/dev/dsk/c1t0d0s0 contains a ufs filesystem.
# zpool create -f tank c1t0d0
```

Ideally, correct the errors rather than use the `-f` option.

Mismatched Replication Levels

Creating pools with virtual devices of different replication levels is not recommended. The `zpool` command tries to prevent you from accidentally creating a pool with mismatched levels of redundancy. If you try to create a pool with such a configuration, you see errors similar to the following:

```
# zpool create tank c1t0d0 mirror c2t0d0 c3t0d0
invalid vdev specification
use '-f' to override the following errors:
mismatched replication level: both disk and mirror vdevs are present
# zpool create tank mirror c1t0d0 c2t0d0 mirror c3t0d0 c4t0d0 c5t0d0
invalid vdev specification
use '-f' to override the following errors:
mismatched replication level: 2-way mirror and 3-way mirror vdevs are present
```

You can override these errors with the `-f` option, though this practice is not recommended. The command also warns you about creating a mirrored or RAID-Z pool using devices of different sizes. While this configuration is allowed, mismatched levels of redundancy result in unused space on the larger device, and requires the `-f` option to override the warning.

Doing a Dry Run of Storage Pool Creation

Because creating a pool can fail unexpectedly in different ways, and because formatting disks is such a potentially harmful action, the `zpool create` command has an additional option, `-n`, which simulates creating the pool without actually writing data to disk. This option performs

the device in-use checking and replication level validation, and reports any errors in the process. If no errors are found, you see output similar to the following:

```
# zpool create -n tank mirror c1t0d0 c1t1d0
would create 'tank' with the following layout:
```

```
    tank
      mirror
        c1t0d0
        c1t1d0
```

Some errors cannot be detected without actually creating the pool. The most common example is specifying the same device twice in the same configuration. This error cannot be reliably detected without writing the data itself, so the `create -n` command can report success and yet fail to create the pool when run for real.

Default Mount Point for Storage Pools

When a pool is created, the default mount point for the root dataset is `/pool-name`. This directory must either not exist or be empty. If the directory does not exist, it is automatically created. If the directory is empty, the root dataset is mounted on top of the existing directory. To create a pool with a different default mount point, use the `-m` option of the `zpool create` command:

```
# zpool create home c1t0d0
default mountpoint '/home' exists and is not empty
use '-m' option to specify a different default
# zpool create -m /export/zfs home c1t0d0
```

```
# zpool create home c1t0d0
default mountpoint '/home' exists and is not empty
use '-m' option to provide a different default
# zpool create -m /export/zfs home c1t0d0
```

This command creates a new pool `home` and the home dataset with a mount point of `/export/zfs`.

For more information about mount points, see [“Managing ZFS Mount Points” on page 97](#).

Destroying ZFS Storage Pools

Pools are destroyed by using the `zpool destroy` command. This command destroys the pool even if it contains mounted datasets.

```
# zpool destroy tank
```



Caution – Be very careful when you destroy a pool. Make sure you are destroying the right pool and you always have copies of your data. If you accidentally destroy the wrong pool, you can attempt to recover the pool. For more information, see [“Recovering Destroyed ZFS Storage Pools” on page 73](#).

Destroying a Pool With Faulted Devices

The act of destroying a pool requires that data be written to disk to indicate that the pool is no longer valid. This state information prevents the devices from showing up as a potential pool when you perform an import. If one or more devices are unavailable, the pool can still be destroyed. However, the necessary state information won't be written to these damaged devices.

These devices, when suitably repaired, are reported as *potentially active* when you create a new pool, and appear as valid devices when you search for pools to import. If a pool has enough faulted devices such that the pool itself is faulted (meaning that a top-level virtual device is faulted), then the command prints a warning and cannot complete without the `-f` option. This option is necessary because the pool cannot be opened, so whether data is stored there or not is unknown. For example:

```
# zpool destroy tank
cannot destroy 'tank': pool is faulted
use '-f' to force destruction anyway
# zpool destroy -f tank
```

For more information about pool and device health, see [“Determining the Health Status of ZFS Storage Pools” on page 66](#).

For more information about importing pools, see [“Importing ZFS Storage Pools” on page 72](#).

Managing Devices in ZFS Storage Pools

Most of the basic information regarding devices is covered in [“Components of a ZFS Storage Pool” on page 41](#). Once a pool has been created, you can perform several tasks to manage the physical devices within the pool.

- [“Adding Devices to a Storage Pool” on page 52](#)
- [“Attaching and Detaching Devices in a Storage Pool” on page 53](#)
- [“Onlining and Offlining Devices in a Storage Pool” on page 55](#)
- [“Clearing Storage Pool Devices” on page 57](#)
- [“Replacing Devices in a Storage Pool” on page 58](#)
- [“Designating Hot Spares in Your Storage Pool” on page 58](#)

Adding Devices to a Storage Pool

You can dynamically add space to a pool by adding a new top-level virtual device. This space is immediately available to all datasets within the pool. To add a new virtual device to a pool, use the `zpool add` command. For example:

```
# zpool add zeepool mirror c2t1d0 c2t2d0
```

The format of the virtual devices is the same as for the `zpool create` command, and the same rules apply. Devices are checked to determine if they are in use, and the command cannot change the level of redundancy without the `-f` option. The command also supports the `-n` option so that you can perform a dry run. For example:

```
# zpool add -n zeepool mirror c3t1d0 c3t2d0
would update 'zeepool' to the following configuration:
zeepool
  mirror
    c1t0d0
    c1t1d0
  mirror
    c2t1d0
    c2t2d0
  mirror
    c3t1d0
    c3t2d0
```

This command syntax would add mirrored devices `c3t1d0` and `c3t2d0` to `zeepool`'s existing configuration.

For more information about how virtual device validation is done, see [“Detecting in Use Devices” on page 48](#).

EXAMPLE 4-1 Adding Disks to a RAID-Z Configuration

Additional disks can be added similarly to a RAID-Z configuration. The following example shows how to convert a storage pool with one RAID-Z device comprised of 3 disks to a storage pool with two RAID-Z devices comprised of 3 disks.

```
# zpool status
pool: rpool
state: ONLINE
scrub: none requested
config:
NAME          STATE      READ WRITE CKSUM
rpool        ONLINE    0    0    0
raidz1       ONLINE    0    0    0
```

EXAMPLE 4-1 Adding Disks to a RAID-Z Configuration *(Continued)*

```

c1t2d0  ONLINE      0      0      0
c1t3d0  ONLINE      0      0      0
c1t4d0  ONLINE      0      0      0

```

errors: No known data errors

```
# zpool add rpool raidz c2t2d0 c2t3d0 c2t4d0
```

```
# zpool status
```

```
pool: rpool
```

```
state: ONLINE
```

```
scrub: none requested
```

```
config:
```

NAME	STATE	READ	WRITE	CKSUM
rpool	ONLINE	0	0	0
raidz1	ONLINE	0	0	0
c1t2d0	ONLINE	0	0	0
c1t3d0	ONLINE	0	0	0
c1t4d0	ONLINE	0	0	0
raidz1	ONLINE	0	0	0
c1t2d0	ONLINE	0	0	0
c1t3d0	ONLINE	0	0	0
c1t4d0	ONLINE	0	0	0

errors: No known data errors

Attaching and Detaching Devices in a Storage Pool

In addition to the `zpool add` command, you can use the `zpool attach` command to add a new device to an existing mirrored or non-mirrored device.

EXAMPLE 4-2 Converting a Two-Way Mirrored Storage Pool to a Three-way Mirrored Storage Pool

In this example, `zeepool` is an existing two-way mirror that is transformed to a three-way mirror by attaching `c2t1d0`, the new device, to the existing device, `c1t1d0`.

```
# zpool status
```

```
pool: zeepool
```

```
state: ONLINE
```

```
scrub: none requested
```

```
config:
```

NAME	STATE	READ	WRITE	CKSUM
zeepool	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c0t1d0	ONLINE	0	0	0
c1t1d0	ONLINE	0	0	0

EXAMPLE 4-2 Converting a Two-Way Mirrored Storage Pool to a Three-way Mirrored Storage Pool
 (Continued)

```

errors: No known data errors
# zpool attach zeepool c1t1d0 c2t1d0
# zpool status
  pool: zeepool
  state: ONLINE
  scrub: resilver completed with 0 errors on Fri Jan 12 14:47:36 2007
config:

```

NAME	STATE	READ	WRITE	CKSUM
zeepool	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c0t1d0	ONLINE	0	0	0
c1t1d0	ONLINE	0	0	0
c2t1d0	ONLINE	0	0	0

If the existing device is part of a two-way mirror, attaching the new device, creates a three-way mirror, and so on. In either case, the new device begins to resilver immediately.

EXAMPLE 4-3 Converting a Non-Redundant ZFS Storage Pool to a Mirrored ZFS Storage Pool

In addition, you can convert a non-redundant storage pool into a redundant storage pool by using the `zpool attach` command. For example:

```

# zpool create tank c0t1d0
# zpool status
  pool: tank
  state: ONLINE
  scrub: none requested
config:

```

NAME	STATE	READ	WRITE	CKSUM
tank	ONLINE	0	0	0
c0t1d0	ONLINE	0	0	0

```

errors: No known data errors
# zpool attach tank c0t1d0 c1t1d0
# zpool status
  pool: tank
  state: ONLINE
  scrub: resilver completed with 0 errors on Fri Jan 12 14:55:48 2007
config:

```

NAME	STATE	READ	WRITE	CKSUM
tank	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c0t1d0	ONLINE	0	0	0

EXAMPLE 4-3 Converting a Non-Redundant ZFS Storage Pool to a Mirrored ZFS Storage Pool
(Continued)

```
c1t1d0 ONLINE 0 0 0
```

You can use the `zpool detach` command to detach a device from a mirrored storage pool. For example:

```
# zpool detach zeepool c2t1d0
```

However, this operation is refused if there are no other valid replicas of the data. For example:

```
# zpool detach newpool c1t2d0
cannot detach c1t2d0: only applicable to mirror and replacing vdevs
```

Onlining and Offlining Devices in a Storage Pool

ZFS allows individual devices to be taken offline or brought online. When hardware is unreliable or not functioning properly, ZFS continues to read or write data to the device, assuming the condition is only temporary. If the condition is not temporary, it is possible to instruct ZFS to ignore the device by bringing it offline. ZFS does not send any requests to an offlined device.

Note – Devices do not need to be taken offline in order to replace them.

You can use the `offline` command when you need to temporarily disconnect storage. For example, if you need to physically disconnect an array from one set of Fibre Channel switches and connect the array to a different set, you could take the LUNs offline from the array that was used in ZFS storage pools. After the array was reconnected and operational on the new set of switches, you could then bring the same LUNs online. Data that had been added to the storage pools while the LUNs were offline would resilver to the LUNs after they were brought back online.

This scenario is possible assuming that the systems in question see the storage once it is attached to the new switches, possibly through different controllers than before, and your pools are set up as RAID-Z or mirrored configurations.

Taking a Device Offline

You can take a device offline by using the `zpool offline` command. The device can be specified by path or by short name, if the device is a disk. For example:

```
# zpool offline tank c1t0d0  
bringing device c1t0d0 offline
```

Keep the following points in mind when taking a device offline:

- You cannot take a pool offline to the point where it becomes faulted. For example, you cannot take offline two devices out of a RAID-Z configuration, nor can you take offline a top-level virtual device.

```
# zpool offline tank c1t0d0  
cannot offline c1t0d0: no valid replicas
```

- By default, the offline state is persistent. The device remains offline when the system is rebooted.

To temporarily take a device offline, use the `zpool offline -t` option. For example:

```
# zpool offline -t tank c1t0d0  
bringing device 'c1t0d0' offline
```

When the system is rebooted, this device is automatically returned to the ONLINE state.

- When a device is taken offline, it is not detached from the storage pool. If you attempt to use the offlined device in another pool, even after the original pool is destroyed, you will see a message similar to the following:

```
device is part of exported or potentially active ZFS pool. Please see zpool(1M)
```

If you want to use the offlined device in another storage pool after destroying the original storage pool, first bring the device back online, then destroy the original storage pool.

Another way to use a device from another storage pool if you want to keep the original storage pool is to replace the existing device in the original storage pool with another comparable device. For information about replacing devices, see [“Replacing Devices in a Storage Pool” on page 58](#).

Offlined devices show up in the OFFLINE state when you query pool status. For information about querying pool status, see [“Querying ZFS Storage Pool Status” on page 62](#).

For more information on device health, see [“Determining the Health Status of ZFS Storage Pools” on page 66](#).

Bringing a Device Online

Once a device is taken offline, it can be restored by using the `zpool online` command:

```
# zpool online tank c1t0d0  
bringing device c1t0d0 online
```


When a device is brought online, any data that has been written to the pool is resynchronized to the newly available device. Note that you cannot use device onlining to replace a disk. If you offline a device, replace the drive, and try to bring it online, it remains in the faulted state.

If you attempt to online a faulted device, a message similar to the following is displayed from `cmd`:

```
# zpool online tank c1t0d0
Bringing device c1t0d0 online
#
SUNW-MSG-ID: ZFS-8000-D3, TYPE: Fault, VER: 1, SEVERITY: Major
EVENT-TIME: Thu Aug 31 11:13:59 MDT 2006
PLATFORM: SUNW,Ultra-60, CSN: -, HOSTNAME: neo
SOURCE: zfs-diagnosis, REV: 1.0
EVENT-ID: e11d8245-d76a-e152-80c6-e63763ed7e4f
DESC: A ZFS device failed. Refer to http://sun.com/msg/ZFS-8000-D3 for more information.
AUTO-RESPONSE: No automated response will occur.
IMPACT: Fault tolerance of the pool may be compromised.
REC-ACTION: Run 'zpool status -x' and replace the bad device.
```

For more information on replacing a faulted device, see [“Repairing a Missing Device” on page 162](#).

Clearing Storage Pool Devices

If a device is taken offline due to a failure that causes errors to be listed in the `zpool status` output, you can clear the error counts with the `zpool clear` command.

If specified with no arguments, this command clears all device errors within the pool. For example:

```
# zpool clear tank
```

If one or more devices are specified, this command only clear errors associated with the specified devices. For example:

```
# zpool clear tank c1t0d0
```

For more information on clearing `zpool` errors, see [“Clearing Transient Errors” on page 165](#).

Replacing Devices in a Storage Pool

You can replace a device in a storage pool by using the `zpool replace` command.

```
# zpool replace tank c1t1d0 c1t2d0
```

In this example, the previous device, `c1t1d0`, is replaced by `c1t2d0`.

The replacement device must be greater than or equal to the minimum size of all the devices in a mirror or RAID-Z configuration. If the replacement device is larger, the pool size in an unmirrored or non RAID-Z configuration is increased when the replacement is complete.

For more information about replacing devices, see [“Repairing a Missing Device” on page 162](#) and [“Repairing a Damaged Device” on page 164](#).

Designating Hot Spares in Your Storage Pool

The hot spares feature enables you to identify disks that could be used to replace a failed or faulted device in one or more storage pools. Designating a device as a *hot spare* means that the device is not an active device in a pool, but if an active device in the pool fails, the hot spare automatically replaces the failed device.

Devices can be designated as hot spares in the following ways:

- When the pool is created with the `zpool create` command
- After the pool is created with the `zpool add` command
- Hot spare devices can be shared between multiple pools

Designate devices as hot spares when the pool is created. For example:

```
# zpool create zeepool mirror c1t1d0 c2t1d0 spare c1t2d0 c2t2d0
# zpool status zeepool
pool: zeepool
state: ONLINE
scrub: none requested
config:
```

NAME	STATE	READ	WRITE	CKSUM
zeepool	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c1t1d0	ONLINE	0	0	0
c2t1d0	ONLINE	0	0	0
spares				
c1t2d0	AVAIL			
c2t2d0	AVAIL			

Designate hot spares by adding them to a pool after the pool is created. For example:

```
# zpool add -f zeepool spare c1t3d0 c2t3d0
# zpool status zeepool
pool: zeepool
state: ONLINE
scrub: none requested
config:

    NAME            STATE             READ WRITE CKSUM
    zeepool          ONLINE            0     0     0
      mirror         ONLINE            0     0     0
        c1t1d0       ONLINE            0     0     0
        c2t1d0       ONLINE            0     0     0
    spares
      c1t3d0         AVAIL
      c2t3d0         AVAIL
```

Multiple pools can share devices that are designated as hot spares. For example:

```
# zpool create zeepool mirror c1t1d0 c2t1d0 spare c1t2d0 c2t2d0
# zpool create tank raidz c3t1d0 c4t1d0 spare c1t2d0 c2t2d0
```

Hot spares can be removed from a storage pool by using the `zpool remove` command. For example:

```
# zpool remove zeepool c1t2d0
# zpool status zeepool
pool: zeepool
state: ONLINE
scrub: none requested
config:

    NAME            STATE             READ WRITE CKSUM
    zeepool          ONLINE            0     0     0
      mirror         ONLINE            0     0     0
        c1t1d0       ONLINE            0     0     0
        c2t1d0       ONLINE            0     0     0
    spares
      c1t3d0         AVAIL
```

A hot spare cannot be removed if it is currently used by the storage pool.

Currently, the `zpool remove` command can only be used to remove hot spares.

Activating and Deactivating Hot Spares in Your Storage Pool

Hot spares are activated in the following ways:

- Manually replacement – Replace a failed device in a storage pool with a hot spare by using the `zpool replace` command.
- Automatic replacement – When a fault is received, an FMA agent examines the pool to see if it has any available hot spares. If so, it replaces the faulted device with an available spare.

If a hot spare that is currently in use fails, the agent detaches the spare and thereby cancels the replacement. The agent then attempts to replace the device with another hot spare, if one is available. This feature is currently limited by the fact that the ZFS diagnosis engine only emits faults when a device disappears from the system.

Currently, no automated response is available to bring the original device back online. You must explicitly take one of the actions described in the example below. A future enhancement will allow ZFS to subscribe to hotplug events and automatically replace the affected device when it is replaced on the system.

Manually replace a device with a hot spare by using the `zpool replace` command. For example:

```
# zpool replace zeepool c2t1d0 c2t3d0
# zpool status zeepool
pool: zeepool
state: ONLINE
scrub: resilver completed with 0 errors on Fri Jun  2 13:44:40 2006
config:
```

NAME	STATE	READ	WRITE	CKSUM
zeepool	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c1t2d0	ONLINE	0	0	0
spare	ONLINE	0	0	0
c2t1d0	ONLINE	0	0	0
c2t3d0	ONLINE	0	0	0
spares				
c1t3d0	AVAIL			
c2t3d0	INUSE	currently	in use	

```
errors: No known data errors
```

A faulted device is automatically replaced if a hot spare is available. For example:

```
# zpool status -x
pool: zeepool
state: DEGRADED
status: One or more devices could not be opened. Sufficient replicas exist for
the pool to continue functioning in a degraded state.
```

action: Attach the missing device and online it using 'zpool online'.
 see: <http://www.sun.com/msg/ZFS-8000-D3>
 scrub: resilver completed with 0 errors on Fri Jun 2 13:56:49 2006
 config:

NAME	STATE	READ	WRITE	CKSUM	
zeepool	DEGRADED	0	0	0	
mirror	DEGRADED	0	0	0	
c1t2d0	ONLINE	0	0	0	
spare	DEGRADED	0	0	0	
c2t1d0	UNAVAIL	0	0	0	cannot open
c2t3d0	ONLINE	0	0	0	
spares					
c1t3d0	AVAIL				
c2t3d0	INUSE		currently in use		

errors: No known data errors

Currently, three ways to deactivate hot spares are available:

- Canceling the hot spare by removing it from the storage pool
- Replacing the original device with a hot spare
- Permanently swapping in the hot spare

After the faulted device is replaced, use the `zpool detach` command to return the hot spare back to the spare set. For example:

```
# zpool detach zeepool c2t3d0
# zpool status zeepool
pool: zeepool
state: ONLINE
scrub: resilver completed with 0 errors on Fri Jun 2 13:58:35 2006
config:
```

NAME	STATE	READ	WRITE	CKSUM	
zeepool	ONLINE	0	0	0	
mirror	ONLINE	0	0	0	
c1t2e0	ONLINE	0	0	0	
c2t1d0	ONLINE	0	0	0	
spares					
c1t3d0	AVAIL				
c2t3d0	AVAIL				

errors: No known data errors

Querying ZFS Storage Pool Status

The `zpool list` command provides a number of ways to request information regarding pool status. The information available generally falls into three categories: basic usage information, I/O statistics, and health status. All three types of storage pool information are covered in this section.

- [“Displaying Basic ZFS Storage Pool Information” on page 62](#)
- [“Viewing ZFS Storage Pool I/O Statistics” on page 64](#)
- [“Determining the Health Status of ZFS Storage Pools” on page 66](#)

Displaying Basic ZFS Storage Pool Information

You can use the `zpool list` command to display basic information about pools.

Listing Information About All Storage Pools

With no arguments, the command displays all the fields for all pools on the system. For example:

```
# zpool list
NAME                SIZE    USED    AVAIL    CAP  HEALTH    ALTROOT
tank                80.0G  22.3G   47.7G   28%  ONLINE    -
dozer               1.2T   384G    816G   32%  ONLINE    -
```

This output displays the following information:

NAME	The name of the pool.
SIZE	The total size of the pool, equal to the sum of the size of all top-level virtual devices.
USED	The amount of space allocated by all datasets and internal metadata. Note that this amount is different from the amount of space as reported at the file system level. For more information about determining available file system space, see “ZFS Space Accounting” on page 38 .
AVAILABLE	The amount of unallocated space in the pool.
CAPACITY (CAP)	The amount of space used, expressed as a percentage of total space.
HEALTH	The current health status of the pool. For more information about pool health, see “Determining the Health Status of ZFS Storage Pools” on page 66 .

ALROOT The alternate root of the pool, if any.

For more information about alternate root pools, see [“Using ZFS Alternate Root Pools” on page 151](#).

You can also gather statistics for a specific pool by specifying the pool name. For example:

```
# zpool list tank
NAME                SIZE    USED    AVAIL    CAP    HEALTH    ALROOT
tank                80.0G   22.3G   47.7G   28%    ONLINE    -
```

Listing Specific Storage Pool Statistics

Specific statistics can be requested by using the `-o` option. This option allows for custom reports or a quick way to list pertinent information. For example, to list only the name and size of each pool, you use the following syntax:

```
# zpool list -o name,size
NAME                SIZE
tank                80.0G
dozer               1.2T
```

The column names correspond to the properties that are listed in [“Listing Information About All Storage Pools” on page 62](#).

Scripting ZFS Storage Pool Output

The default output for the `zpool list` command is designed for readability, and is not easy to use as part of a shell script. To aid programmatic uses of the command, the `-H` option can be used to suppress the column headings and separate fields by tabs, rather than by spaces. For example, to request a simple list of all pool names on the system:

```
# zpool list -Ho name
tank
dozer
```

Here is another example:

```
# zpool list -H -o name,size
tank  80.0G
dozer 1.2T
```

Viewing ZFS Storage Pool I/O Statistics

To request I/O statistics for a pool or specific virtual devices, use the `zpool iostat` command. Similar to the `iostat` command, this command can display a static snapshot of all I/O activity so far, as well as updated statistics for every specified interval. The following statistics are reported:

USED CAPACITY	The amount of data currently stored in the pool or device. This figure differs from the amount of space available to actual file systems by a small amount due to internal implementation details.
	For more information about the difference between pool space and dataset space, see “ZFS Space Accounting” on page 38 .
AVAILABLE CAPACITY	The amount of space available in the pool or device. As with the used statistic, this amount differs from the amount of space available to datasets by a small margin.
READ OPERATIONS	The number of read I/O operations sent to the pool or device, including metadata requests.
WRITE OPERATIONS	The number of write I/O operations sent to the pool or device.
READ BANDWIDTH	The bandwidth of all read operations (including metadata), expressed as units per second.
WRITE BANDWIDTH	The bandwidth of all write operations, expressed as units per second.

Listing Pool-Wide Statistics

With no options, the `zpool iostat` command displays the accumulated statistics since boot for all pools on the system. For example:

```
# zpool iostat
          capacity      operations      bandwidth
pool      used avail  read write  read write
-----
tank      100G 20.0G  1.2M  102K  1.2M  3.45K
dozer     12.3G 67.7G  132K  15.2K 32.1K  1.20K
```

Because these statistics are cumulative since boot, bandwidth might appear low if the pool is relatively idle. You can request a more accurate view of current bandwidth usage by specifying an interval. For example:

```
# zpool iostat tank 2
          capacity      operations      bandwidth
pool      used avail  read write  read write
-----
```



```
tank      100G  20.0G  1.2M  102K  1.2M  3.45K
tank      100G  20.0G   134    0  1.34K    0
tank      100G  20.0G   94   342  1.06K  4.1M
```

In this example, the command displays usage statistics only for the pool `tank` every two seconds until you type `Ctrl-C`. Alternately, you can specify an additional count parameter, which causes the command to terminate after the specified number of iterations. For example, `zpool iostat 2 3` would print a summary every two seconds for three iterations, for a total of six seconds. If there is a single pool, then the statistics are displayed on consecutive lines. If more than one pool exists, then an additional dashed line delineates each iteration to provide visual separation.

Listing Virtual Device Statistics

In addition to pool-wide I/O statistics, the `zpool iostat` command can display statistics for specific virtual devices. This command can be used to identify abnormally slow devices, or simply to observe the distribution of I/O generated by ZFS. To request the complete virtual device layout as well as all I/O statistics, use the `zpool iostat -v` command. For example:

```
# zpool iostat -v
          capacity      operations      bandwidth
tank      used  avail  read  write  read  write
-----  -
mirror    20.4G  59.6G    0    22    0  6.00K
  c1t0d0      -    -     1   295  11.2K  148K
  c1t1d0      -    -     1   299  11.2K  148K
-----  -
total     24.5K  149M    0    22    0  6.00K
```

Note two important things when viewing I/O statistics on a virtual device basis.

- First, space usage is only available for top-level virtual devices. The way in which space is allocated among mirror and RAID-Z virtual devices is particular to the implementation and not easily expressed as a single number.
- Second, the numbers might not add up exactly as you would expect them to. In particular, operations across RAID-Z and mirrored devices will not be exactly equal. This difference is particularly noticeable immediately after a pool is created, as a significant amount of I/O is done directly to the disks as part of pool creation that is not accounted for at the mirror level. Over time, these numbers should gradually equalize, although broken, unresponsive, or offlined devices can affect this symmetry as well.

You can use the same set of options (interval and count) when examining virtual device statistics.

Determining the Health Status of ZFS Storage Pools

ZFS provides an integrated method of examining pool and device health. The health of a pool is determined from the state of all its devices. This state information is displayed by using the `zpool status` command. In addition, potential pool and device failures are reported by `fmfd` and are displayed on the system console and the `/var/adm/messages` file. This section describes how to determine pool and device health. This chapter does not document how to repair or recover from unhealthy pools. For more information on troubleshooting and data recovery, see [Chapter 9](#).

Each device can fall into one of the following states:

ONLINE	The device is in normal working order. While some transient errors might still occur, the device is otherwise in working order.
DEGRADED	The virtual device has experienced failure but is still able to function. This state is most common when a mirror or RAID-Z device has lost one or more constituent devices. The fault tolerance of the pool might be compromised, as a subsequent fault in another device might be unrecoverable.
FAULTED	The virtual device is completely inaccessible. This status typically indicates total failure of the device, such that ZFS is incapable of sending or receiving data from it. If a top-level virtual device is in this state, then the pool is completely inaccessible.
OFFLINE	The virtual device has been explicitly taken offline by the administrator.
UNAVAILABLE	The device or virtual device cannot be opened. In some cases, pools with UNAVAILABLE devices appear in DEGRADED mode. If a top-level virtual device is unavailable, then nothing in the pool can be accessed.

The health of a pool is determined from the health of all its top-level virtual devices. If all virtual devices are ONLINE, then the pool is also ONLINE. If any one of the virtual devices is DEGRADED or UNAVAILABLE, then the pool is also DEGRADED. If a top-level virtual device is FAULTED or OFFLINE, then the pool is also FAULTED. A pool in the faulted state is completely inaccessible. No data can be recovered until the necessary devices are attached or repaired. A pool in the degraded state continues to run, but you might not achieve the same level of data redundancy or data throughput than if the pool were online.

Basic Storage Pool Health Status

The simplest way to request a quick overview of pool health status is to use the `zpool status` command:

```
# zpool status -x
all pools are healthy
```

Specific pools can be examined by specifying a pool name to the command. Any pool that is not in the ONLINE state should be investigated for potential problems, as described in the next section.

Detailed Health Status

You can request a more detailed health summary by using the `-v` option. For example:

```
# zpool status -v tank
pool: tank
state: DEGRADED
status: One or more devices could not be opened. Sufficient replicas exist
       for the pool to continue functioning in a degraded state.
action: Attach the missing device and online it using 'zpool online'.
       see: http://www.sun.com/msg/ZFS-8000-2Q
       scrub: none requested
config:

      NAME                STATE      READ WRITE CKSUM
      tank                DEGRADED   0     0     0
      mirror              DEGRADED   0     0     0
      c1t0d0              FAULTED    0     0     0  cannot open
      c1t1d0              ONLINE     0     0     0
errors: No known data errors
```

This output displays a complete description of why the pool is in its current state, including a readable description of the problem and a link to a knowledge article for more information. Each knowledge article provides up-to-date information on the best way to recover from your current problem. Using the detailed configuration information, you should be able to determine which device is damaged and how to repair the pool.

In the above example, the faulted device should be replaced. After the device is replaced, use the `zpool online` command to bring the device back online. For example:

```
# zpool online tank c1t0d0
Bringing device c1t0d0 online
# zpool status -x
all pools are healthy
```

If a pool has an offlined device, the command output identifies the problem pool. For example:

```
# zpool status -x
pool: tank
state: DEGRADED
status: One or more devices has been taken offline by the administrator.
       Sufficient replicas exist for the pool to continue functioning in a
       degraded state.
```

```

action: Online the device using 'zpool online' or replace the device with
        'zpool replace'.
scrub: none requested
config:

```

NAME	STATE	READ	WRITE	CKSUM
tank	DEGRADED	0	0	0
mirror	DEGRADED	0	0	0
c1t0d0	ONLINE	0	0	0
c1t1d0	OFFLINE	0	0	0

```

errors: No known data errors

```

The READ and WRITE columns provides a count of I/O errors seen on the device, while the CKSUM column provides a count of uncorrectable checksum errors that occurred on the device. Both of these error counts likely indicate potential device failure, and some corrective action is needed. If non-zero errors are reported for a top-level virtual device, portions of your data might have become inaccessible. The errors count identifies any known data errors.

In the example output above, the offlined device is not causing data errors.

For more information about diagnosing and repairing faulted pools and data, see [Chapter 9](#).

Migrating ZFS Storage Pools

Occasionally, you might need to move a storage pool between machines. To do so, the storage devices must be disconnected from the original machine and reconnected to the destination machine. This task can be accomplished by physically recabling the devices, or by using multiported devices such as the devices on a SAN. ZFS enables you to export the pool from one machine and import it on the destination machine, even if the machines are of different endianness. For information about replicating or migrating file systems between different storage pools, which might reside on different machines, see [“Saving and Restoring ZFS Data” on page 113](#).

- [“Preparing for ZFS Storage Pool Migration” on page 69](#)
- [“Exporting a ZFS Storage Pool” on page 69](#)
- [“Determining Available Storage Pools to Import” on page 69](#)
- [“Finding ZFS Storage Pools From Alternate Directories” on page 71](#)
- [“Importing ZFS Storage Pools” on page 72](#)
- [“Recovering Destroyed ZFS Storage Pools” on page 73](#)
- [“Upgrading ZFS Storage Pools” on page 75](#)

Preparing for ZFS Storage Pool Migration

Storage pools should be explicitly exported to indicate that they are ready to be migrated. This operation flushes any unwritten data to disk, writes data to the disk indicating that the export was done, and removes all knowledge of the pool from the system.

If you do not explicitly export the pool, but instead remove the disks manually, you can still import the resulting pool on another system. However, you might lose the last few seconds of data transactions, and the pool will appear faulted on the original machine because the devices are no longer present. By default, the destination machine refuses to import a pool that has not been explicitly exported. This condition is necessary to prevent accidentally importing an active pool that consists of network attached storage that is still in use on another system.

Exporting a ZFS Storage Pool

To export a pool, use the `zpool export` command. For example:

```
# zpool export tank
```

Once this command is executed, the pool `tank` is no longer visible on the system. The command attempts to unmount any mounted file systems within the pool before continuing. If any of the file systems fail to unmount, you can forcefully unmount them by using the `-f` option. For example:

```
# zpool export tank
cannot unmount '/export/home/eschrock': Device busy
# zpool export -f tank
```

If devices are unavailable at the time of export, the disks cannot be specified as cleanly exported. If one of these devices is later attached to a system without any of the working devices, it appears as “potentially active.” If emulated volumes are in use in the pool, the pool cannot be exported, even with the `-f` option. To export a pool with an emulated volume, first make sure that all consumers of the volume are no longer active.

For more information about emulated volumes, see “ZFS Volumes” on page 143.

Determining Available Storage Pools to Import

Once the pool has been removed from the system (either through export or by forcefully removing the devices), attach the devices to the target system. Although ZFS can handle some situations in which only a portion of the devices is available, all devices within the pool must be moved between the systems. The devices do not necessarily have to be attached under the same

device name. ZFS detects any moved or renamed devices, and adjusts the configuration appropriately. To discover available pools, run the `zpool import` command with no options. For example:

```
# zpool import
pool: tank
  id: 3778921145927357706
  state: ONLINE
action: The pool can be imported using its name or numeric identifier.
config:

    tank          ONLINE
      mirror      ONLINE
        c1t0d0    ONLINE
        c1t1d0    ONLINE
```

In this example, the pool `tank` is available to be imported on the target system. Each pool is identified by a name as well as a unique numeric identifier. If multiple pools available to import have the same name, you can use the numeric identifier to distinguish between them.

Similar to the `zpool status` command, the `zpool import` command refers to a knowledge article available on the web with the most up-to-date information regarding repair procedures for a problem that is preventing a pool from being imported. In this case, the user can force the pool to be imported. However, importing a pool that is currently in use by another system over a storage network can result in data corruption and panics as both systems attempt to write to the same storage. If some devices in the pool are not available but enough redundancy is available to have a usable pool, the pool appears in the `DEGRADED` state. For example:

```
# zpool import
pool: tank
  id: 3778921145927357706
  state: DEGRADED
status: One or more devices are missing from the system.
action: The pool can be imported despite missing or damaged devices. The
       fault tolerance of the pool may be compromised if imported.
  see: http://www.sun.com/msg/ZFS-8000-2Q
config:

    tank          DEGRADED
      mirror      DEGRADED
        c1t0d0    UNAVAIL  cannot open
        c1t1d0    ONLINE
```

In this example, the first disk is damaged or missing, though you can still import the pool because the mirrored data is still accessible. If too many faulted or missing devices are present, the pool cannot be imported. For example:

```
# zpool import
pool: dozer
  id: 12090808386336829175
  state: FAULTED
action: The pool cannot be imported. Attach the missing
        devices and try again.
  see: http://www.sun.com/msg/ZFS-8000-6X
config:
  raidz          FAULTED
    c1t0d0      ONLINE
    c1t1d0      FAULTED
    c1t2d0      ONLINE
    c1t3d0      FAULTED
```

In this example, two disks are missing from a RAID-Z virtual device, which means that sufficient redundant data is not available to reconstruct the pool. In some cases, not enough devices are present to determine the complete configuration. In this case, ZFS doesn't know what other devices were part of the pool, though ZFS does report as much information as possible about the situation. For example:

```
# zpool import
pool: dozer
  id: 12090808386336829175
  state: FAULTED
status: One or more devices are missing from the system.
action: The pool cannot be imported. Attach the missing
        devices and try again.
  see: http://www.sun.com/msg/ZFS-8000-6X
config:
  dozer          FAULTED  missing device
    raidz        ONLINE
      c1t0d0     ONLINE
      c1t1d0     ONLINE
      c1t2d0     ONLINE
      c1t3d0     ONLINE
  Additional devices are known to be part of this pool, though their
  exact configuration cannot be determined.
```

Finding ZFS Storage Pools From Alternate Directories

By default, the `zpool import` command only searches devices within the `/dev/dsk` directory. If devices exist in another directory, or you are using pools backed by files, you must use the `-d` option to search different directories. For example:

```
# zpool create dozer mirror /file/a /file/b
# zpool export dozer
# zpool import -d /file
  pool: dozer
    id: 10952414725867935582
  state: ONLINE
  action: The pool can be imported using its name or numeric identifier.
  config:

    dozer      ONLINE
      mirror   ONLINE
        /file/a ONLINE
        /file/b ONLINE
# zpool import -d /file dozer
```

If devices exist in multiple directories, you can specify multiple `-d` options.

Importing ZFS Storage Pools

Once a pool has been identified for import, you can import it by specifying the name of the pool or its numeric identifier as an argument to the `zpool import` command. For example:

```
# zpool import tank
```

If multiple available pools have the same name, you can specify which pool to import using the numeric identifier. For example:

```
# zpool import
  pool: dozer
    id: 2704475622193776801
  state: ONLINE
  action: The pool can be imported using its name or numeric identifier.
  config:

    dozer      ONLINE
      c1t9d0    ONLINE

  pool: dozer
    id: 6223921996155991199
  state: ONLINE
  action: The pool can be imported using its name or numeric identifier.
  config:

    dozer      ONLINE
      c1t8d0    ONLINE
# zpool import dozer
```



```
cannot import 'dozer': more than one matching pool
import by numeric ID instead
# zpool import 6223921996155991199
```

If the pool name conflicts with an existing pool name, you can import the pool under a different name. For example:

```
# zpool import dozer zeepool
```

This command imports the exported pool `dozer` using the new name `zeepool`. If the pool was not cleanly exported, ZFS requires the `-f` flag to prevent users from accidentally importing a pool that is still in use on another system. For example:

```
# zpool import dozer
cannot import 'dozer': pool may be in use on another system
use '-f' to import anyway
# zpool import -f dozer
```

Pools can also be imported under an alternate root by using the `-R` option. For more information on alternate root pools, see [“Using ZFS Alternate Root Pools” on page 151](#).

Recovering Destroyed ZFS Storage Pools

You can use the `zpool import -D` command to recover a storage pool that has been destroyed. For example:

```
# zpool destroy tank
# zpool import -D
pool: tank
  id: 3778921145927357706
  state: ONLINE (DESTROYED)
action: The pool can be imported using its name or numeric identifier. The
       pool was destroyed, but can be imported using the '-Df' flags.
config:

      tank      ONLINE
      mirror    ONLINE
           c1t0d0  ONLINE
           c1t1d0  ONLINE
```

In the above `zpool import` output, you can identify this pool as the destroyed pool because of the following state information:

```
state: ONLINE (DESTROYED)
```

To recover the destroyed pool, issue the `zpool import -D` command again with the pool to be recovered and the `-f` option. For example:

```
# zpool import -Df tank
# zpool status tank
  pool: tank
  state: ONLINE
  scrub: none requested
  config:
```

NAME	STATE	READ	WRITE	CKSUM
tank	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c1t0d0	ONLINE	0	0	0
c1t1d0	ONLINE	0	0	0

```
errors: No known data errors
```

If one of the devices in the destroyed pool is faulted or unavailable, you might be able to recover the destroyed pool anyway. In this scenario, import the degraded pool and then attempt to fix the device failure. For example:

```
# zpool destroy dozer
# zpool import -D
  pool: dozer
  id:
  state: DEGRADED (DESTROYED)
  status: One or more devices are missing from the system.
  action: The pool can be imported despite missing or damaged devices. The
         fault tolerance of the pool may be compromised if imported. The
         pool was destroyed, but can be imported using the '-Df' flags.
         see: http://www.sun.com/msg/ZFS-8000-2Q
  config:
```

dozer	DEGRADED	
raidz	ONLINE	
c1t0d0	ONLINE	
c1t1d0	ONLINE	
c1t2d0	UNAVAIL	cannot open
c1t3d0	ONLINE	

```
# zpool import -Df dozer
# zpool status -x
  pool: dozer
  state: DEGRADED
  status: One or more devices could not be opened. Sufficient replicas exist for
         the pool to continue functioning in a degraded state.
  action: Attach the missing device and online it using 'zpool online'.
```

```

see: http://www.sun.com/msg/ZFS-8000-D3
scrub: resilver completed with 0 errors on Fri Mar 17 16:11:35 2006
config:

```

NAME	STATE	READ	WRITE	CKSUM	
dozer	DEGRADED	0	0	0	
raidz	ONLINE	0	0	0	
c1t0d0	ONLINE	0	0	0	
c1t1d0	ONLINE	0	0	0	
c1t2d0	UNAVAIL	0	0	0	cannot open
c1t3d0	ONLINE	0	0	0	

```

errors: No known data errors
# zpool online dozer c1t2d0
Bringing device c1t2d0 online
# zpool status -x
all pools are healthy

```

Upgrading ZFS Storage Pools

If you have ZFS storage pools from a previous Solaris release, such as the Solaris 10 6/06 release, you can upgrade your pools with the `zpool upgrade` command to take advantage of the pool features in the Solaris 10 11/06 release. In addition, the `zpool status` command has been modified to notify you when your pools are running older versions. For example:

```

# zpool status
pool: test
state: ONLINE
status: The pool is formatted using an older on-disk format. The pool can
still be used, but some features are unavailable.
action: Upgrade the pool using 'zpool upgrade'. Once this is done, the
pool will no longer be accessible on older software versions.
scrub: none requested
config:

```

NAME	STATE	READ	WRITE	CKSUM
test	ONLINE	0	0	0
c1t27d0	ONLINE	0	0	0

```

errors: No known data errors

```

You can use the following syntax to identify additional information about a particular version and supported releases.

```
# zpool upgrade -v
```

This system is currently running ZFS version 3.

The following versions are supported:

```
VER  DESCRIPTION
```

```
---  -----
```

- 1 Initial ZFS version
- 2 Ditto blocks (replicated metadata)
- 3 Hot spares and double parity RAID-Z

For more information on a particular version, including supported releases, see:

<http://www.opensolaris.org/os/community/zfs/version/N>

Where 'N' is the version number.

Then, you can run the `zpool upgrade` command to upgrade your pools. For example:

```
# zpool upgrade -a
```

Note – If you upgrade your pools to the latest version, they will not be accessible on systems that run older ZFS versions.

Managing ZFS File Systems

This chapter provides detailed information about managing Solaris™ ZFS file systems. Concepts such as hierarchical file system layout, property inheritance, and automatic mount point management and share interactions are included in this chapter.

A ZFS file system is a lightweight POSIX file system that is built on top of a storage pool. File systems can be dynamically created and destroyed without requiring you to allocate or format any underlying space. Because file systems are so lightweight and because they are the central point of administration in ZFS, you are likely to create many of them.

ZFS file systems are administered by using the `zfs` command. The `zfs` command provides a set of subcommands that perform specific operations on file systems. This chapter describes these subcommands in detail. Snapshots, volumes, and clones are also managed by using this command, but these features are only covered briefly in this chapter. For detailed information about snapshots and clones, see [Chapter 6](#). For detailed information about emulated volumes, see “ZFS Volumes” on page 143.

Note – The term *dataset* is used in this chapter as a generic term to refer to a file system, snapshot, clone, or volume.

The following sections are provided in this chapter:

- “Creating and Destroying ZFS File Systems” on page 78
- “Introducing ZFS Properties” on page 81
- “Querying ZFS File System Information” on page 90
- “Managing ZFS Properties” on page 92
- “Mounting and Sharing ZFS File Systems” on page 97
- “ZFS Quotas and Reservations” on page 103
- “Saving and Restoring ZFS Data” on page 113

Creating and Destroying ZFS File Systems

ZFS file systems can be created and destroyed by using the `zfs create` and `zfs destroy` commands.

- “Creating a ZFS File System” on page 78
- “Destroying a ZFS File System” on page 79
- “Renaming a ZFS File System” on page 80

Creating a ZFS File System

ZFS file systems are created by using the `zfs create` command. The `create` subcommand takes a single argument: the name of the file system to create. The file system name is specified as a path name starting from the name of the pool:

```
pool-name/[filesystem-name/]filesystem-name
```

The pool name and initial file system names in the path identify the location in the hierarchy where the new file system will be created. All the intermediate file system names must already exist in the pool. The last name in the path identifies the name of the file system to be created. The file system name must satisfy the naming conventions defined in “[ZFS Component Naming Requirements](#)” on page 26.

In the following example, a file system named `bonwick` is created in the `tank/home` file system.

```
# zfs create tank/home/bonwick
```

ZFS automatically mounts the newly created file system if it is created successfully. By default, file systems are mounted as `/dataset`, using the path provided for the file system name in the `create` subcommand. In this example, the newly created `bonwick` file system is at `/tank/home/bonwick`. For more information about automanaged mount points, see “[Managing ZFS Mount Points](#)” on page 97.

For more information about the `zfs create` command, see `zfs(1M)`.

A new feature is available that enables you to set file system properties when the file system is created.

In the following example, a mount point of `/export/zfs` is specified and is created for the `tank/home` file system.

```
# zfs create -o mountpoint=/export/zfs tank/home
```

For more information about file system properties, see “[Introducing ZFS Properties](#)” on page 81.

Destroying a ZFS File System

To destroy a ZFS file system, use the `zfs destroy` command. The destroyed file system is automatically unmounted and unshared. For more information about automatically managed mounts or automatically managed shares, see [“Automatic Mount Points” on page 98](#).

In the following example, the `tabriz` file system is destroyed.

```
# zfs destroy tank/home/tabriz
```



Caution – No confirmation prompt appears with the `destroy` subcommand. Use it with extreme caution.

If the file system to be destroyed is busy and so cannot be unmounted, the `zfs destroy` command fails. To destroy an active file system, use the `-f` option. Use this option with caution as it can unmount, unshare, and destroy active file systems, causing unexpected application behavior.

```
# zfs destroy tank/home/ahrens
cannot unmount 'tank/home/ahrens': Device busy
```

```
# zfs destroy -f tank/home/ahrens
```

The `zfs destroy` command also fails if a file system has children. To recursively destroy a file system and all its descendants, use the `-r` option. Note that a recursive destroy also destroys snapshots so use this option with caution.

```
# zfs destroy tank/ws
cannot destroy 'tank/ws': filesystem has children
use '-r' to destroy the following datasets:
tank/ws/billm
tank/ws/bonwick
tank/ws/maybee
```

```
# zfs destroy -r tank/ws
```

If the file system to be destroyed has indirect dependents, even the recursive destroy command described above fails. To force the destruction of *all* dependents, including cloned file systems outside the target hierarchy, the `-R` option must be used. Use extreme caution with this option.

```
# zfs destroy -r tank/home/schrock
cannot destroy 'tank/home/schrock': filesystem has dependent clones
use '-R' to destroy the following datasets:
tank/clones/schrock-clone
```

```
# zfs destroy -R tank/home/schrock
```



Caution – No confirmation prompt appears with the `-f`, `-r`, or `-R` options so use these options carefully.

For more information about snapshots and clones, see [Chapter 6](#).

Renaming a ZFS File System

File systems can be renamed by using the `zfs rename` command. Using the `rename` subcommand can perform the following operations:

- Change the name of a file system
- Relocate the file system to a new location within the ZFS hierarchy
- Change the name of a file system and relocate it with the ZFS hierarchy

The following example uses the `rename` subcommand to do a simple rename of a file system:

```
# zfs rename tank/home/kustarz tank/home/kustarz_old
```

This example renames the `kustarz` file system to `kustarz_old`.

The following example shows how to use `zfs rename` to relocate a file system.

```
# zfs rename tank/home/maybee tank/ws/maybee
```

In this example, the `maybee` file system is relocated from `tank/home` to `tank/ws`. When you relocate a file system through `rename`, the new location must be within the same pool and it must have enough space to hold this new file system. If the new location does not have enough space, possibly because it has reached its quota, the `rename` will fail.

For more information about quotas, see [“ZFS Quotas and Reservations” on page 103](#).

The `rename` operation attempts an unmount/remount sequence for the file system and any descendant file systems. The `rename` fails if the operation is unable to unmount an active file system. If this problem occurs, you will need to force unmount the file system.

For information about renaming snapshots, see [“Renaming ZFS Snapshots” on page 109](#).

Introducing ZFS Properties

Properties are the main mechanism that you use to control the behavior of file systems, volumes, snapshots, and clones. Unless stated otherwise, the properties defined in the section apply to all the dataset types.

- “ZFS Read-Only Native Properties” on page 86
- “Settable ZFS Native Properties” on page 87
- “ZFS User Properties” on page 89

Properties are divided into two types, native properties and user defined properties. Native properties either export internal statistics or control ZFS file system behavior. In addition, native properties are either settable or read-only. User properties have no effect on ZFS file system behavior, but you can use them to annotate datasets in a way that is meaningful in your environment. For more information on user properties, see “ZFS User Properties” on page 89.

Most settable properties are also inheritable. An inheritable property is a property that, when set on a parent, is propagated down to all of its descendants.

All inheritable properties have an associated source. The source indicates how a property was obtained. The source of a property can have the following values:

<code>local</code>	A <code>local</code> source indicates that the property was explicitly set on the dataset by using the <code>zfs set</code> command as described in “Setting ZFS Properties” on page 93.
<code>inherited from <i>dataset-name</i></code>	A value of <code>inherited from <i>dataset-name</i></code> means that the property was inherited from the named ancestor.
<code>default</code>	A value of <code>default</code> means that the property setting was not inherited or set locally. This source is a result of no ancestor having the property as source <code>local</code> .

The following table identifies both read-only and settable native ZFS file system properties. Read-only native properties are identified as such. All other native properties listed in this table are settable. For information about user properties, see “ZFS User Properties” on page 89.

TABLE 5-1 ZFS Native Property Descriptions

Property Name	Type	Default Value	Description
<code>aclinherit</code>	String	<code>secure</code>	Controls how ACL entries are inherited when files and directories are created. The values are <code>discard</code> , <code>noallow</code> , <code>secure</code> , and <code>passthrough</code> . For a description of these values, see “ACL Property Modes” on page 122.

TABLE 5-1 ZFS Native Property Descriptions (Continued)

Property Name	Type	Default Value	Description
<code>aclmode</code>	String	<code>groupmask</code>	Controls how an ACL entry is modified during a <code>chmod</code> operation. The values are <code>discard</code> , <code>groupmask</code> , and <code>passthrough</code> . For a description of these values, see “ ACL Property Modes ” on page 122.
<code>atime</code>	Boolean	<code>on</code>	Controls whether the access time for files is updated when they are read. Turning this property off avoids producing write traffic when reading files and can result in significant performance gains, though it might confuse mailers and other similar utilities.
<code>available</code>	Number	N/A	<p>Read-only property that identifies the amount of space available to the dataset and all its children, assuming no other activity in the pool. Because space is shared within a pool, available space can be limited by various factors including physical pool size, quotas, reservations, or other datasets within the pool.</p> <p>This property can also be referenced by its shortened column name, <code>avail</code>.</p> <p>For more information about space accounting, see “ZFS Space Accounting” on page 38.</p>
<code>canmount</code>	Boolean	<code>on</code>	Controls whether the given file system can be mounted with the <code>zfs mount</code> command. This property can be set on any file system and the property itself is not inheritable. However, when this property is set, a mountpoint can be inherited to descendant file systems, but the file system itself is never mounted. For more information, see “ The canmount Property ” on page 88
<code>checksum</code>	String	<code>on</code>	Controls the checksum used to verify data integrity. The default value is <code>on</code> , which automatically selects an appropriate algorithm, currently <code>fletcher2</code> . The values are <code>on</code> , <code>off</code> , <code>fletcher2</code> , <code>fletcher4</code> , and <code>sha256</code> . A value of <code>off</code> disables integrity checking on user data. A value of <code>off</code> is not recommended.
<code>compression</code>	String	<code>off</code>	<p>Controls the compression algorithm used for this dataset. Currently, only one algorithm, <code>lzjb</code>, exists. Enabling compression on a file system with existing data only compresses new data. Existing data remains uncompressed.</p> <p>This property can also be referred to by its shortened column name, <code>compress</code>.</p>

TABLE 5-1 ZFS Native Property Descriptions (Continued)

Property Name	Type	Default Value	Description
<code>compressratio</code>	Number	N/A	<p>Read-only property that identifies the compression ratio achieved for this dataset, expressed as a multiplier. Compression can be turned on by running <code>zfs set compression=on dataset</code>.</p> <p>Calculated from the logical size of all files and the amount of referenced physical data. Includes explicit savings through the use of the <code>compression</code> property.</p>
<code>creation</code>	Number	N/A	Read-only property that identifies the date and time that this dataset was created.
<code>devices</code>	Boolean	on	Controls the ability to open device files in the file system..
<code>exec</code>	Boolean	on	Controls whether programs within this file system are allowed to be executed. Also, when set to <code>off</code> , <code>mmap(2)</code> calls with <code>PROT_EXEC</code> are disallowed.
<code>mounted</code>	boolean	N/A	Read-only property that indicates whether this file system, clone, or snapshot is currently mounted. This property does not apply to volumes. Value can be either <code>yes</code> or <code>no</code> .
<code>mountpoint</code>	String	N/A	<p>Controls the mount point used for this file system. When the <code>mountpoint</code> property is changed for a file system, the file system and any children that inherit the mount point are unmounted. If the new value is <code>legacy</code>, then they remain unmounted. Otherwise, they are automatically remounted in the new location if the property was previously <code>legacy</code> or <code>none</code>, or if they were mounted before the property was changed. In addition, any shared file systems are unshared and shared in the new location.</p> <p>For more information about using this property, see “Managing ZFS Mount Points” on page 97.</p>
<code>origin</code>	String	N/A	<p>Read-only property for cloned file systems or volumes that identifies the snapshot from which the clone was created. The origin cannot be destroyed (even with the <code>-r</code> or <code>-f</code> options) as long as a clone exists.</p> <p>Non-cloned file systems have an origin of <code>none</code>.</p>

TABLE 5-1 ZFS Native Property Descriptions (Continued)

Property Name	Type	Default Value	Description
quota	Number (or none)	none	<p>Limits the amount of space a dataset and its descendants can consume. This property enforces a hard limit on the amount of space used, including all space consumed by descendants, including file systems and snapshots. Setting a quota on a descendant of a dataset that already has a quota does not override the ancestor's quota, but rather imposes an additional limit. Quotas cannot be set on volumes, as the <code>volsize</code> property acts as an implicit quota.</p> <p>For information about setting quotas, see “Setting Quotas on ZFS File Systems” on page 103.</p>
readonly	Boolean	off	<p>Controls whether this dataset can be modified. When set to on, no modifications can be made to the dataset.</p> <p>This property can also be referred to by its shortened column name, <code>rdonly</code>.</p>
recordsize	Number	128K	<p>Specifies a suggested block size for files in the file system.</p> <p>This property can also be referred to by its shortened column name, <code>recsize</code>. For a detailed description, see “The recordsize Property” on page 88.</p>
referenced	Number	N/A	<p>Read-only property that identifies the amount of data accessible by this dataset, which might or might not be shared with other datasets in the pool.</p> <p>When a snapshot or clone is created, it initially references the same amount of space as the file system or snapshot it was created from, because its contents are identical.</p> <p>This property can also be referred to by its shortened column name, <code>refer</code>.</p>
reservation	Number (or none)	none	<p>The minimum amount of space guaranteed to a dataset and its descendants. When the amount of space used is below this value, the dataset is treated as if it were using the amount of space specified by its reservation. Reservations are accounted for in the parent datasets' space used, and count against the parent datasets' quotas and reservations.</p> <p>This property can also be referred to by its shortened column name, <code>reserv</code>.</p> <p>For more information, see “Setting Reservations on ZFS File Systems” on page 104.</p>

TABLE 5-1 ZFS Native Property Descriptions (Continued)

Property Name	Type	Default Value	Description
sharenfs	String	off	Controls whether the file system is available over NFS, and what options are used. If set to on, the <code>zfs share</code> command is invoked with no options. Otherwise, the <code>zfs share</code> command is invoked with options equivalent to the contents of this property. If set to off, the file system is managed by using the legacy <code>share</code> and <code>unshare</code> commands and the <code>dfstab</code> file. For more information on sharing ZFS file systems, see “Sharing and Unsharing ZFS File Systems” on page 101 .
setuid	Boolean	on	Controls whether the <code>setuid</code> bit is honored in the file system.
snapdir	String	hidden	Controls whether the <code>.zfs</code> directory is hidden or visible in the root of the file system. For more information on using snapshots, see “Overview of ZFS Snapshots” on page 107 .
type	String	N/A	Read-only property that identifies the dataset type as <code>filesystem</code> (file system or clone), <code>volume</code> , or <code>snapshot</code> .
used	Number	N/A	Read-only property that identifies the amount of space consumed by the dataset and all its descendants. For a detailed description, see “The used Property” on page 86 .
volsize	Number	N/A	For volumes, specifies the logical size of the volume. For a detailed description, see “The volsize Property” on page 88 .
volblocksize	Number	8 Kbytes	For volumes, specifies the block size of the volume. The block size cannot be changed once the volume has been written, so set the block size at volume creation time. The default block size for volumes is 8 Kbytes. Any power of 2 from 512 bytes to 128 Kbytes is valid. This property can also be referred to by its shortened column name, <code>volblock</code> .
zoned	Boolean	N/A	Indicates whether this dataset has been added to a non-global zone. If this property is set, then the mount point is not honored in the global zone, and ZFS cannot mount such a file system when requested. When a zone is first installed, this property is set for any added file systems. For more information about using ZFS with zones installed, see “Using ZFS on a Solaris System With Zones Installed” on page 145 .
xattr	Boolean	on	Indicates whether extended attributes are enabled or disabled for this file system. The default value is on.

ZFS Read-Only Native Properties

Read-only native properties are properties that can be retrieved but cannot be set. Read-only native properties are not inherited. Some native properties are specific to a particular type of dataset. In such cases, the particular dataset type is mentioned in the description in [Table 5–1](#).

The read-only native properties are listed here and are described in [Table 5–1](#).

- `available`
- `creation`
- `mounted`
- `origin`
- `compressratio`
- `referenced`
- `type`
- `used`

For detailed information, see “[The used Property](#)” on page 86.

For more information on space accounting, including the used, referenced, and available properties, see “[ZFS Space Accounting](#)” on page 38.

The used Property

The amount of space consumed by this dataset and all its descendants. This value is checked against the dataset's quota and reservation. The space used does not include the dataset's reservation, but does consider the reservation of any descendant datasets. The amount of space that a dataset consumes from its parent, as well as the amount of space that is freed if the dataset is recursively destroyed, is the greater of its space used and its reservation.

When snapshots are created, their space is initially shared between the snapshot and the file system, and possibly with previous snapshots. As the file system changes, space that was previously shared becomes unique to the snapshot, and counted in the snapshot's space used. Additionally, deleting snapshots can increase the amount of space unique to (and used by) other snapshots. For more information about snapshots and space issues, see “[Out of Space Behavior](#)” on page 38.

The amount of space used, available, or referenced does not take into account pending changes. Pending changes are generally accounted for within a few seconds. Committing a change to a disk using `fsync(3c)` or `O_SYNC` does not necessarily guarantee that the space usage information will be updated immediately.

Settable ZFS Native Properties

Settable native properties are properties whose values can be both retrieved and set. Settable native properties are set by using the `zfs set` command, as described in “[Setting ZFS Properties](#)” on page 93 or by using the `zfs create` command as described in “[Creating a ZFS File System](#)” on page 78. With the exceptions of quotas and reservations, settable native properties are inherited. For more information about quotas and reservations, see “[ZFS Quotas and Reservations](#)” on page 103.

Some settable native properties are specific to a particular type of dataset. In such cases, the particular dataset type is mentioned in the description in [Table 5–1](#). If not specifically mentioned, a property applies to all dataset types: file systems, volumes, clones, and snapshots.

The settable properties are listed here and are described in [Table 5–1](#).

- `aclinherit`
For a detailed description, see “[ACL Property Modes](#)” on page 122.
- `aclmode`
For a detailed description, see “[ACL Property Modes](#)” on page 122.
- `atime`
- `canmount`
- `checksum`
- `compression`
- `devices`
- `exec`
- `mountpoint`
- `quota`
- `readonly`
- `recordsize`
For a detailed description, see “[The recordsize Property](#)” on page 88.
- `reservation`
- `sharenfs`
- `setuid`
- `snapdir`
- `volsize`
For a detailed description, see “[The volsize Property](#)” on page 88.
- `volblocksize`
- `zoned`

The canmount Property

If this property is set to no, the file system cannot be mounted by using the `zfs mount` or `zfs mount -a` commands. This property is similar to setting the `mountpoint` property to none, except that the dataset still has a normal `mountpoint` property that can be inherited. For example, you can set this property to no, establish inheritable properties for descendant file systems, but the file system itself is never mounted nor is it accessible to users. In this case, the parent file system with this property set to no is serving as a *container* so that you can set attributes on the container, but the container itself is never accessible.

In the following example, `userpool` is created and the `canmount` property is set to off. Mount points for descendant user file systems are set to one common mount point, `/export/home`. Properties that are set on the parent file system are inherited by descendant file systems, but the parent file system itself is never mounted.

```
# zpool create userpool mirror c0t5d0 c1t6d0
# zfs set canmount=off userpool
# zfs set mountpoint=/export/home userpool
# zfs set compression=on userpool
# zfs create userpool/user1
# zfs create userpool/user2
# zfs list -r userpool
```

NAME	USED	AVAIL	REFER	MOUNTPOINT
userpool	140K	8.24G	24.5K	/export/home
userpool/user1	24.5K	8.24G	24.5K	/export/home/user1
userpool/user2	24.5K	8.24G	24.5K	/export/home/user2

The recordsize Property

Specifies a suggested block size for files in the file system.

This property is designed solely for use with database workloads that access files in fixed-size records. ZFS automatically adjust block sizes according to internal algorithms optimized for typical access patterns. For databases that create very large files but access the files in small random chunks, these algorithms may be suboptimal. Specifying a `recordsize` greater than or equal to the record size of the database can result in significant performance gains. Use of this property for general purpose file systems is strongly discouraged, and may adversely affect performance. The size specified must be a power of two greater than or equal to 512 and less than or equal to 128 Kbytes. Changing the file system's `recordsize` only affects files created afterward. Existing files are unaffected.

This property can also be referred to by its shortened column name, `recsize`.

The volsize Property

The logical size of the volume. By default, creating a volume establishes a reservation for the same amount. Any changes to `volsize` are reflected in an equivalent change to the reservation. These checks are used to prevent unexpected behavior for users. A volume that contains less

space than it claims is available can result in undefined behavior or data corruption, depending on how the volume is used. These effects can also occur when the volume size is changed while it is in use, particularly when you shrink the size. Extreme care should be used when adjusting the volume size.

Though not recommended, you can create a sparse volume by specifying the `-s` flag to `zfs create -V`, or by changing the reservation once the volume has been created. A *sparse volume* is defined as a volume where the reservation is not equal to the volume size. For a sparse volume, changes to `volsize` are not reflected in the reservation.

For more information about using volumes, see [“ZFS Volumes” on page 143](#).

ZFS User Properties

In addition to the standard native properties, ZFS supports arbitrary user properties. User properties have no effect on ZFS behavior, but you can use them to annotate datasets with information that is meaningful in your environment.

User property names must conform to the following characteristics:

- Contain a colon (':') character to distinguish them from native properties.
- Contain lowercase letters, numbers, and the following punctuation characters: '!', '+', ',', '_', '.'
- Maximum user property name is 256 characters.

The expected convention is that the property name is divided into the following two components but this namespace is not enforced by ZFS:

module:property

When making programmatic use of user properties, use a reversed DNS domain name for the *module* component of property names to reduce the chance that two independently-developed packages will use the same property name for different purposes. Property names that begin with "com.sun." are reserved for use by Sun Microsystems.

The values of user properties have the following characteristics:

- Arbitrary strings that are always inherited and are never validated.
- Maximum user property value is 1024 characters.

For example:

```
# zfs set dept:users=finance userpool/user1
# zfs set dept:users=general userpool/user2
# zfs set dept:users=itops userpool/user3
```

All of the commands that operate on properties, such as `zfs list`, `zfs get`, `zfs set`, and so on, can be used to manipulate both native properties and user properties.

For example:

```
zfs get -r dept:users userpool
NAME          PROPERTY  VALUE      SOURCE
userpool      dept:users all        local
userpool/user1 dept:users finance   local
userpool/user2 dept:users general  local
userpool/user3 dept:users itops    local
```

To clear a user property, use the `zfs inherit` command. For example:

```
# zfs inherit -r dept:users userpool
```

If the property is not defined in any parent dataset, it is removed entirely.

Querying ZFS File System Information

The `zfs list` command provides an extensible mechanism for viewing and querying dataset information. Both basic and complex queries are explained in this section.

Listing Basic ZFS Information

You can list basic dataset information by using the `zfs list` command with no options. This command displays the names of all datasets on the system including their used, available, referenced, and mountpoint properties. For more information about these properties, see [“Introducing ZFS Properties” on page 81](#).

For example:

```
# zfs list
NAME          USED  AVAIL  REFER  MOUNTPOINT
pool          476K  16.5G  21K    /pool
pool/clone    18K   16.5G  18K    /pool/clone
pool/home     296K  16.5G  19K    /pool/home
pool/home/marks 277K  16.5G  277K   /pool/home/marks
pool/home/marks@snap 0      -      277K   -
pool/test     18K   16.5G  18K    /test
```

You can also use this command to display specific datasets by providing the dataset name on the command line. Additionally, use the `-r` option to recursively display all descendants of that dataset. For example:

```
# zfs list -r pool/home/marks
NAME          USED  AVAIL  REFER  MOUNTPOINT
pool/home/marks 277K  16.5G  277K   /pool/home/marks
pool/home/marks@snap 0      -      277K   -
```

You use `zfs list` command with absolute pathnames for datasets, snapshots, and volumes. For example:

```
# zfs list /pool/home/marks
NAME                USED  AVAIL  REFER  MOUNTPOINT
pool/home/marks     277K  16.5G  277K   /pool/home/marks
```

The following example shows how to display `tank/home/chua` and all of its descendant datasets.

```
# zfs list -r tank/home/chua
NAME                USED  AVAIL  REFER  MOUNTPOINT
tank/home/chua      26.0K  4.81G  10.0K   /tank/home/chua
tank/home/chua/projects  16K  4.81G   9.0K   /tank/home/chua/projects
tank/home/chua/projects/fs1  8K  4.81G   8K   /tank/home/chua/projects/fs1
tank/home/chua/projects/fs2  8K  4.81G   8K   /tank/home/chua/projects/fs2
```

For additional information about the `zfs list` command, see `zfs(1M)`.

Creating Complex ZFS Queries

The `zfs list` output can be customized by using of the `-o`, `-f`, and `-H` options.

You can customize property value output by using the `-o` option and a comma-separated list of desired properties. Supply any dataset property as a valid value. For a list of all supported dataset properties, see [“Introducing ZFS Properties” on page 81](#). In addition to the properties defined there, the `-o` option list can also contain the literal name to indicate that the output should include the name of the dataset.

The following example uses `zfs list` to display the dataset name, along with the `sharenfs` and `mountpoint` properties.

```
# zfs list -o name,sharenfs,mountpoint
NAME                SHARENFS  MOUNTPOINT
tank                off        /tank
tank/home           on         /tank/home
tank/home/ahrens   on         /tank/home/ahrens
tank/home/bonwick  on         /tank/home/bonwick
tank/home/chua     on         /tank/home/chua
tank/home/eschrock on         legacy
tank/home/moore    on         /tank/home/moore
tank/home/tabriz   ro         /tank/home/tabriz
```

You can use the `-t` option to specify the types of datasets to display. The valid types are described in the following table.

TABLE 5-2 Types of ZFS Datasets

Type	Description
filesystem	File systems and clones
volume	Volumes
snapshot	Snapshots

The `-t` options takes a comma-separated list of the types of datasets to be displayed. The following example uses the `-t` and `-o` options simultaneously to show the name and used property for all file systems:

```
# zfs list -t filesystem -o name,used
NAME                USED
pool                 476K
pool/clone           18K
pool/home            296K
pool/home/marks     277K
pool/test            18K
```

You can use the `-H` option to omit the `zfs list` header from the generated output. With the `-H` option, all white space is output as tabs. This option can be useful when you need parseable output, for example, when scripting. The following example shows the output generated from using the `zfs list` command with the `-H` option:

```
# zfs list -H -o name
pool
pool/clone
pool/home
pool/home/marks
pool/home/marks@snap
pool/test
```

Managing ZFS Properties

Dataset properties are managed through the `zfs` command's `set`, `inherit`, and `get` subcommands.

- [“Setting ZFS Properties” on page 93](#)
- [“Inheriting ZFS Properties” on page 93](#)
- [“Querying ZFS Properties” on page 94](#)

Setting ZFS Properties

You can use the `zfs set` command to modify any settable dataset property. Or, you can use the `zfs create` command to set properties when the dataset is created. For a list of settable dataset properties, see [“Settable ZFS Native Properties” on page 87](#). The `zfs set` command takes a property/value sequence in the format of `property=value` and a dataset name.

The following example sets the `atime` property to `off` for `tank/home`. Only one property can be set or modified during each `zfs set` invocation.

```
# zfs set atime=off tank/home
```

In addition, any file system property can be set when the file system is created. For example:

```
# zfs create -o atime=off tank/home
```

You can specify numeric properties by using the following easy to understand suffixes (in order of magnitude): `BKMGTP EZ`. Any of these suffixes can be followed by an optional `b`, indicating bytes, with the exception of the `B` suffix, which already indicates bytes. The following four invocations of `zfs set` are equivalent numeric expressions indicating that the quota property be set to the value of 50 Gbytes on the `tank/home/marks` file system:

```
# zfs set quota=50G tank/home/marks
# zfs set quota=50g tank/home/marks
# zfs set quota=50GB tank/home/marks
# zfs set quota=50gb tank/home/marks
```

Values of non-numeric properties are case-sensitive and must be lowercase, with the exception of `mountpoint` and `sharenfs`. The values of these properties can have mixed upper and lower case letters.

For more information about the `zfs set` command, see `zfs(1M)`.

Inheriting ZFS Properties

All settable properties, with the exception of quotas and reservations, inherit their value from their parent, unless a quota or reservation is explicitly set on the child. If no ancestor has an explicit value set for an inherited property, the default value for the property is used. You can use the `zfs inherit` command to clear a property setting, thus causing the setting to be inherited from the parent.

The following example uses the `zfs set` command to turn on compression for the `tank/home/bonwick` file system. Then, `zfs inherit` is used to unset the `compression` property, thus causing the property to inherit the default setting of `off`. Because neither `home` nor `tank` have the `compression` property set locally, the default value is used. If both had `compression on`, the value set in the most immediate ancestor would be used (`home` in this example).

```
# zfs set compression=on tank/home/bonwick
# zfs get -r compression tank
NAME          PROPERTY    VALUE          SOURCE
tank          compression off            default
tank/home     compression off            default
tank/home/bonwick compression on          local
# zfs inherit compression tank/home/bonwick
# zfs get -r compression tank
NAME          PROPERTY    VALUE          SOURCE
tank          compression off            default
tank/home     compression off            default
tank/home/bonwick compression off            default
```

The `inherit` subcommand is applied recursively when the `-r` option is specified. In the following example, the command causes the value for the `compression` property to be inherited by `tank/home` and any descendants it might have.

```
# zfs inherit -r compression tank/home
```

Note – Be aware that the use of the `-r` option clears the current property setting for all descendant datasets.

For more information about the `zfs` command, see `zfs(1M)`.

Querying ZFS Properties

The simplest way to query property values is by using the `zfs list` command. For more information, see [“Listing Basic ZFS Information” on page 90](#). However, for complicated queries and for scripting, use the `zfs get` command to provide more detailed information in a customized format.

You can use the `zfs get` command to retrieve any dataset property. The following example shows how to retrieve a single property on a dataset:

```
# zfs get checksum tank/ws
NAME          PROPERTY    VALUE          SOURCE
tank/ws       checksum    on             default
```

The fourth column, `SOURCE`, indicates where this property value has been set from. The following table defines the meaning of the possible source values.

TABLE 5-3 Possible SOURCE Values (zfs get)

Source Value	Description
default	This property was never explicitly set for this dataset or any of its ancestors. The default value for this property is being used.
inherited from <i>dataset-name</i>	This property value is being inherited from the parent as specified by <i>dataset-name</i> .
local	This property value was explicitly set for this dataset by using <code>zfs set</code> .
temporary	This property value was set by using the <code>zfs mount -o</code> option and is only valid for the lifetime of the mount. For more information about temporary mount point properties, see “Using Temporary Mount Properties” on page 100 .
-(none)	This property is a read-only property. Its value is generated by ZFS.

You can use the special keyword `all` to retrieve all dataset properties. The following example uses the `all` keyword to retrieve all existing dataset properties:

```
# zfs get all tank
NAME PROPERTY          VALUE                SOURCE
tank  type                filesystem           -
tank  creation            Wed Jan 10 12:18 2007 -
tank  used                144K                -
tank  available           134G                -
tank  referenced          25.5K               -
tank  compressratio      1.00x               -
tank  mounted             yes                 -
tank  quota               none                default
tank  reservation         none                default
tank  recordsize          128K                default
tank  mountpoint          /tank               default
tank  sharenfs            off                 default
tank  shareiscsi          off                 default
tank  checksum            on                  default
tank  compression         off                 default
tank  atime               on                  default
tank  devices             on                  default
tank  exec                on                  default
tank  setuid              on                  default
tank  readonly           off                 default
tank  zoned               off                 default
tank  snapdir             hidden              default
tank  aclmode             groupmask           default
tank  aclinherit          secure              default
tank  canmount            on                  default
tank  xattr              on                  default
```

The `-s` option to `zfs get` enables you to specify, by source value, the type of properties to display. This option takes a comma-separated list indicating the desired source types. Only properties with the specified source type are displayed. The valid source types are `local`, `default`, `inherited`, `temporary`, and `none`. The following example shows all properties that have been locally set on `pool`.

```
# zfs get -s local all pool
NAME          PROPERTY    VALUE      SOURCE
pool          compression on         local
```

Any of the above options can be combined with the `-r` option to recursively display the specified properties on all children of the specified dataset. In the following example, all temporary properties on all datasets within `tank` are recursively displayed:

```
# zfs get -r -s temporary all tank
NAME          PROPERTY    VALUE      SOURCE
tank/home     atime       off        temporary
tank/home/bonwick atime      off        temporary
tank/home/marks atime       off        temporary
```

A recent feature enables you to make queries with the `zfs get` command without specifying a target file system, which means it operates on all pools or file systems. For example:

```
# zfs get -s local all
tank/home     atime       off        local
tank/home/bonwick atime      off        local
tank/home/marks quota       50G       local
```

For more information about the `zfs get` command, see `zfs(1M)`.

Querying ZFS Properties for Scripting

The `zfs get` command supports the `-H` and `-o` options, which are designed for scripting. The `-H` option indicates that any header information should be omitted and that all white space should come in the form of tab. Uniform white space allows for easily parseable data. You can use the `-o` option to customize the output. This option takes a comma-separated list of values to be output. All properties defined in “[Introducing ZFS Properties](#)” on page 81, along with the literals `name`, `value`, `property` and `source` can be supplied in the `-o` list.

The following example shows how to retrieve a single value by using the `-H` and `-o` options of `zfs get`.

```
# zfs get -H -o value compression tank/home
on
```

The `-p` option reports numeric values as their exact values. For example, 1 Mbyte would be reported as 1000000. This option can be used as follows:


```
# zfs get -H -o value -p used tank/home
182983742
```

You can use the `-r` option along with any of the above options to recursively retrieve the requested values for all descendants. The following example uses the `-r`, `-o`, and `-H` options to retrieve the dataset name and the value of the used property for `export/home` and its descendants, while omitting any header output:

```
# zfs get -H -o name,value -r used export/home
export/home      5.57G
export/home/marks 1.43G
export/home/maybee 2.15G
```

Mounting and Sharing ZFS File Systems

This section describes how mount points and shared file systems are managed in ZFS.

- [“Managing ZFS Mount Points” on page 97](#)
- [“Mounting ZFS File Systems” on page 99](#)
- [“Using Temporary Mount Properties” on page 100](#)
- [“Unmounting ZFS File Systems” on page 101](#)
- [“Sharing and Unsharing ZFS File Systems” on page 101](#)

Managing ZFS Mount Points

By default, all ZFS file systems are mounted by ZFS at boot by using SMF's `svc://system/filesystem/local` service. File systems are mounted under `/path`, where `path` is the name of the file system.

You can override the default mount point by setting the `mountpoint` property to a specific path by using the `zfs set` command. ZFS automatically creates this mount point, if needed, and automatically mounts this file system when the `zfs mount -a` command is invoked, without requiring you to edit the `/etc/vfstab` file.

The `mountpoint` property is inherited. For example, if `pool/home` has `mountpoint` set to `/export/stuff`, then `pool/home/user` inherits `/export/stuff/user` for its `mountpoint` property.

The `mountpoint` property can be set to `none` to prevent the file system from being mounted. In addition, the `canmount` property is available for determining whether a file system can be mounted. For more information about the `canmount` property, see [“The `canmount` Property” on page 88](#).

If desired, file systems can also be explicitly managed through legacy mount interfaces by setting the `mountpoint` property to `legacy` by using `zfs set`. Doing so prevents ZFS from

automatically mounting and managing this file system. Legacy tools including the mount and umount commands, and the `/etc/vfstab` file must be used instead. For more information about legacy mounts, see [“Legacy Mount Points” on page 99](#).

When changing mount point management strategies, the following behaviors apply:

- Automatic mount point behavior
- Legacy mount point behavior

Automatic Mount Points

- When changing from legacy or none, ZFS automatically mounts the file system.
- If ZFS is currently managing the file system but it is currently unmounted, and the `mountpoint` property is changed, the file system remains unmounted.

You can also set the default mount point for the root dataset at creation time by using `zpool create`'s `-m` option. For more information about creating pools, see [“Creating a ZFS Storage Pool” on page 46](#).

Any dataset whose `mountpoint` property is not `legacy` is managed by ZFS. In the following example, a dataset is created whose mount point is automatically managed by ZFS.

```
# zfs create pool/filesystem
# zfs get mountpoint pool/filesystem
NAME          PROPERTY      VALUE          SOURCE
pool/filesystem mountpoint    /pool/filesystem default
# zfs get mounted pool/filesystem
NAME          PROPERTY      VALUE          SOURCE
pool/filesystem mounted       yes            -
```

You can also explicitly set the `mountpoint` property as shown in the following example:

```
# zfs set mountpoint=/mnt pool/filesystem
# zfs get mountpoint pool/filesystem
NAME          PROPERTY      VALUE          SOURCE
pool/filesystem mountpoint    /mnt          local
# zfs get mounted pool/filesystem
NAME          PROPERTY      VALUE          SOURCE
pool/filesystem mounted       yes            -
```

When the `mountpoint` property is changed, the file system is automatically unmounted from the old mount point and remounted to the new mount point. Mount point directories are created as needed. If ZFS is unable to unmount a file system due to it being active, an error is reported and a forced manual unmount is necessary.

Legacy Mount Points

You can manage ZFS file systems with legacy tools by setting the `mountpoint` property to `legacy`. Legacy file systems must be managed through the `mount` and `umount` commands and the `/etc/vfstab` file. ZFS does not automatically mount legacy file systems on boot, and the ZFS `mount` and `umount` command do not operate on datasets of this type. The following examples show how to set up and manage a ZFS dataset in legacy mode:

```
# zfs set mountpoint=legacy tank/home/eschrock
# mount -F zfs tank/home/eschrock /mnt
```

In particular, if you have set up separate ZFS `/usr` or `/var` file systems, you must indicate that they are legacy file systems. In addition, you must mount them by creating entries in the `/etc/vfstab` file. Otherwise, the `system/filesystem/local` service enters maintenance mode when the system boots.

To automatically mount a legacy file system on boot, you must add an entry to the `/etc/vfstab` file. The following example shows what the entry in the `/etc/vfstab` file might look like:

```
#device      device      mount      FS      fsck      mount      mount
#to mount    to fsck     point      type    pass     at boot   options
#
tank/home/eschrock -      /mnt       zfs      -        yes      -
```

Note that the `device to fsck` and `fsck pass` entries are set to `-`. This syntax is because the `fsck` command is not applicable to ZFS file systems. For more information regarding data integrity and the lack of need for `fsck` in ZFS, see [“Transactional Semantics” on page 23](#).

Mounting ZFS File Systems

ZFS automatically mounts file systems when file systems are created or when the system boots. Use of the `zfs mount` command is necessary only when changing mount options or explicitly mounting or unmounting file systems.

The `zfs mount` command with no arguments shows all currently mounted file systems that are managed by ZFS. Legacy managed mount points are not displayed. For example:

```
# zfs mount
tank                /tank
tank/home           /tank/home
tank/home/bonwick   /tank/home/bonwick
tank/ws             /tank/ws
```

You can use the `-a` option to mount all ZFS managed file systems. Legacy managed file systems are not mounted. For example:

```
# zfs mount -a
```

By default, ZFS does not allow mounting on top of a nonempty directory. To force a mount on top of a nonempty directory, you must use the `-O` option. For example:

```
# zfs mount tank/home/lalt
cannot mount '/export/home/lalt': directory is not empty
use legacy mountpoint to allow this behavior, or use the -O flag
# zfs mount -O tank/home/lalt
```

Legacy mount points must be managed through legacy tools. An attempt to use ZFS tools results in an error. For example:

```
# zfs mount pool/home/billm
cannot mount 'pool/home/billm': legacy mountpoint
use mount(1M) to mount this filesystem
# mount -F zfs tank/home/billm
```

When a file system is mounted, it uses a set of mount options based on the property values associated with the dataset. The correlation between properties and mount options is as follows:

Property	Mount Options
devices	devices/nodevices
exec	exec/noexec
readonly	ro/rw
setuid	setuid/nosetuid

The mount option `nosuid` is an alias for `nodevices`, `nosetuid`.

Using Temporary Mount Properties

If any of the above options are set explicitly by using the `-o` option with the `zfs mount` command, the associated property value is temporarily overridden. These property values are reported as `temporary` by the `zfs get` command and revert back to their original settings when the file system is unmounted. If a property value is changed while the dataset is mounted, the change takes effect immediately, overriding any temporary setting.

In the following example, the read-only mount option is temporarily set on the `tank/home/perrin` file system:

```
# zfs mount -o ro tank/home/perrin
```

In this example, the file system is assumed to be unmounted. To temporarily change a property on a file system that is currently mounted, you must use the special `remount` option. In the following example, the `atime` property is temporarily changed to `off` for a file system that is currently mounted:

```
# zfs mount -o remount,noatime tank/home/perrin
# zfs get atime tank/home/perrin
NAME          PROPERTY    VALUE      SOURCE
tank/home/perrin atime      off        temporary
```

For more information about the `zfs mount` command, see `zfs(1M)`.

Unmounting ZFS File Systems

You can unmount file systems by using the `zfs unmount` subcommand. The `unmount` command can take either the mount point or the file system name as arguments.

In the following example, a file system is unmounted by file system name:

```
# zfs unmount tank/home/tabriz
```

In the following example, the file system is unmounted by mount point:

```
# zfs unmount /export/home/tabriz
```

The `unmount` command fails if the file system is active or busy. To forcefully unmount a file system, you can use the `-f` option. Be cautious when forcefully unmounting a file system, if its contents are actively being used. Unpredictable application behavior can result.

```
# zfs unmount tank/home/eschrock
cannot unmount '/export/home/eschrock': Device busy
# zfs unmount -f tank/home/eschrock
```

To provide for backwards compatibility, the legacy `umount` command can be used to unmount ZFS file systems. For example:

```
# umount /export/home/bob
```

For more information about the `zfs unmount` command, see `zfs(1M)`.

Sharing and Unsharing ZFS File Systems

Similar to mount points, ZFS can automatically share file systems by using the `sharenfs` property. Using this method, you do not have to modify the `/etc/dfs/dfstab` file when a new

file system is added. The `sharenfs` property is a comma-separated list of options to pass to the `share` command. The special value `on` is an alias for the default share options, which are `read/write` permissions for anyone. The special value `off` indicates that the file system is not managed by ZFS and can be shared through traditional means, such as the `/etc/dfs/dfstab` file. All file systems whose `sharenfs` property is not `off` are shared during boot.

Controlling Share Semantics

By default, all file systems are unshared. To share a new file system, use `zfs set` syntax similar to the following:

```
# zfs set sharenfs=on tank/home/eschrock
```

The property is inherited, and file systems are automatically shared on creation if their inherited property is not `off`. For example:

```
# zfs set sharenfs=on tank/home
# zfs create tank/home/bricker
# zfs create tank/home/tabriz
# zfs set sharenfs=ro tank/home/tabriz
```

Both `tank/home/bricker` and `tank/home/tabriz` are initially shared writable because they inherit the `sharenfs` property from `tank/home`. Once the property is set to `ro` (readonly), `tank/home/tabriz` is shared read-only regardless of the `sharenfs` property that is set for `tank/home`.

Unsharing ZFS File Systems

While most file systems are automatically shared and unshared during boot, creation, and destruction, file systems sometimes need to be explicitly unshared. To do so, use the `zfs unshare` command. For example:

```
# zfs unshare tank/home/tabriz
```

This command unshares the `tank/home/tabriz` file system. To unshare all ZFS file systems on the system, you need to use the `-a` option.

```
# zfs unshare -a
```

Sharing ZFS File Systems

Most of the time the automatic behavior of ZFS, sharing on boot and creation, is sufficient for normal operation. If, for some reason, you unshare a file system, you can share it again by using the `zfs share` command. For example:

```
# zfs share tank/home/tabriz
```

You can also share all ZFS file systems on the system by using the `-a` option.

```
# zfs share -a
```

Legacy Share Behavior

If the `sharenfs` property is `off`, then ZFS does not attempt to share or unshare the file system at any time. This setting enables you to administer through traditional means such as the `/etc/dfs/dfstab` file.

Unlike the traditional `mount` command, the traditional `share` and `unshare` commands can still function on ZFS file systems. As a result, you can manually share a file system with options that are different from the settings of the `sharenfs` property. This administrative model is discouraged. Choose to either manage NFS shares completely through ZFS or completely through the `/etc/dfs/dfstab` file. The ZFS administrative model is designed to be simpler and less work than the traditional model. However, in some cases, you might still want to control file system sharing behavior through the familiar model.

ZFS Quotas and Reservations

ZFS supports quotas and reservations at the file system level. You can use the `quota` property to set a limit on the amount of space a file system can use. In addition, you can use the `reservation` property to guarantee that some amount of space is available to a file system. Both properties apply to the dataset they are set on and all descendants of that dataset.

That is, if a quota is set on the `tank/home` dataset, the total amount of space used by `tank/home` *and all of its descendants* cannot exceed the quota. Similarly, if `tank/home` is given a reservation, `tank/home` *and all of its descendants* draw from that reservation. The amount of space used by a dataset and all of its descendants is reported by the `used` property.

Setting Quotas on ZFS File Systems

ZFS quotas can be set and displayed by using the `zfs set` and `zfs get` commands. In the following example, a quota of 10 Gbytes is set on `tank/home/bonwick`.

```
# zfs set quota=10G tank/home/bonwick
# zfs get quota tank/home/bonwick
NAME                PROPERTY    VALUE          SOURCE
tank/home/bonwick  quota      10.0G         local
```

ZFS quotas also impact the output of the `zfs list` and `df` commands. For example:

```
# zfs list
NAME                                USED  AVAIL  REFER  MOUNTPOINT
tank/home                          16.5K 33.5G  8.50K  /export/home
tank/home/bonwick                   15.0K 10.0G  8.50K  /export/home/bonwick
tank/home/bonwick/ws                 6.50K 10.0G  8.50K  /export/home/bonwick/ws
# df -h /export/home/bonwick
Filesystem      size  used  avail  capacity  Mounted on
tank/home/bonwick  10G   8K   10G    1%      /export/home/bonwick
```

Note that although tank/home has 33.5 Gbytes of space available, tank/home/bonwick and tank/home/bonwick/ws only have 10 Gbytes of space available, due to the quota on tank/home/bonwick.

You cannot set a quota to an amount less than is currently being used by a dataset. For example:

```
# zfs set quota=10K tank/home/bonwick
cannot set quota for 'tank/home/bonwick': size is less than current used or reserved space
```

Setting Reservations on ZFS File Systems

A ZFS *reservation* is an allocation of space from the pool that is guaranteed to be available to a dataset. As such, you cannot reserve space for a dataset if that space is not currently available in the pool. The total amount of all outstanding unconsumed reservations cannot exceed the amount of unused space in the pool. ZFS reservations can be set and displayed by using the `zfs set` and `zfs get` commands. For example:

```
# zfs set reservation=5G tank/home/moore
# zfs get reservation tank/home/moore
NAME                PROPERTY      VALUE                SOURCE
tank/home/moore     reservation   5.00G                local
```

ZFS reservations can affect the output of the `zfs list` command. For example:

```
# zfs list
NAME                                USED  AVAIL  REFER  MOUNTPOINT
tank/home                          5.00G 33.5G  8.50K  /export/home
tank/home/moore                    15.0K 10.0G  8.50K  /export/home/moore
```

Note that tank/home is using 5 Gbytes of space, although the total amount of space referred to by tank/home and its descendants is much less than 5 Gbytes. The used space reflects the space reserved for tank/home/moore. Reservations are considered in the used space of the parent dataset and do count against its quota, reservation, or both.


```
# zfs set quota=5G pool/filesystem
# zfs set reservation=10G pool/filesystem/user1
cannot set reservation for 'pool/filesystem/user1': size is greater than
available space
```

A dataset can use more space than its reservation, as long as space is available in the pool that is unreserved and the dataset's current usage is below its quota. A dataset cannot consume space that has been reserved for another dataset.

Reservations are not cumulative. That is, a second invocation of `zfs set` to set a reservation does not add its reservation to the existing reservation. Rather, the second reservation replaces the first reservation.

```
# zfs set reservation=10G tank/home/moore
# zfs set reservation=5G tank/home/moore
# zfs get reservation tank/home/moore
```

NAME	PROPERTY	VALUE	SOURCE
tank/home/moore	reservation	5.00G	local

Working With ZFS Snapshots and Clones

This chapter describes how to create and manage ZFS snapshots and clones. Information about saving snapshots is also provided in this chapter.

The following sections are provided in this chapter:

- “Overview of ZFS Snapshots” on page 107
- “Creating and Destroying ZFS Snapshots” on page 108
- “Displaying and Accessing ZFS Snapshots” on page 109
- “Rolling Back to a ZFS Snapshot” on page 110
- “Overview of ZFS Clones” on page 111
- “Creating a ZFS Clone” on page 111
- “Destroying a ZFS Clone” on page 112
- “Saving and Restoring ZFS Data” on page 113

Overview of ZFS Snapshots

A *snapshot* is a read-only copy of a file system or volume. Snapshots can be created almost instantly, and initially consume no additional disk space within the pool. However, as data within the active dataset changes, the snapshot consumes disk space by continuing to reference the old data and so prevents the space from being freed.

ZFS snapshots include the following features:

- Persist across system reboots.
- The theoretical maximum number of snapshots is 2^{64} .
- Use no separate backing store. Snapshots consume disk space directly from the same storage pool as the file system from which they were created.
- Recursive snapshots are created quickly as one atomic operation. The snapshots are created together (all at once) or not created at all. The benefit of atomic snapshots operations is that the snapshot data is always taken at one consistent time, even across descendant file systems.

Snapshots of volumes cannot be accessed directly, but they can be cloned, backed up, rolled back to, and so on. For information about backing up a ZFS snapshot, see [“Saving and Restoring ZFS Data” on page 113](#).

Creating and Destroying ZFS Snapshots

Snapshots are created by using the `zfs snapshot` command, which takes as its only argument the name of the snapshot to create. The snapshot name is specified as follows:

```
filesystem@snapname
volume@snapname
```

The snapshot name must satisfy the naming conventions defined in [“ZFS Component Naming Requirements” on page 26](#).

In the following example, a snapshot of `tank/home/ahrens` that is named `friday` is created.

```
# zfs snapshot tank/home/ahrens@friday
```

You can create snapshots for all descendant file systems by using the `-r` option. For example:

```
# zfs snapshot -r tank/home@now
# zfs list -t snapshot
NAME                                USED  AVAIL  REFER  MOUNTPOINT
tank/home@now                       0     - 29.5K  -
tank/home/ahrens@now                 0     - 2.15M  -
tank/home/anne@now                   0     - 1.89M  -
tank/home/bob@now                    0     - 1.89M  -
tank/home/cindys@now                 0     - 2.15M  -
```

Snapshots have no modifiable properties. Nor can dataset properties be applied to a snapshot.

```
# zfs set compression=on tank/home/ahrens@tuesday
cannot set compression property for 'tank/home/ahrens@tuesday': snapshot
properties cannot be modified
```

Snapshots are destroyed by using the `zfs destroy` command. For example:

```
# zfs destroy tank/home/ahrens@friday
```

A dataset cannot be destroyed if snapshots of the dataset exist. For example:

```
# zfs destroy tank/home/ahrens
cannot destroy 'tank/home/ahrens': filesystem has children
use '-r' to destroy the following datasets:
tank/home/ahrens@tuesday
tank/home/ahrens@wednesday
tank/home/ahrens@thursday
```

In addition, if clones have been created from a snapshot, then they must be destroyed before the snapshot can be destroyed.

For more information about the `destroy` subcommand, see [“Destroying a ZFS File System” on page 79](#).

Renaming ZFS Snapshots

You can rename snapshots but they must be renamed within the pool and dataset from which they were created. For example:

```
# zfs rename tank/home/cindys@083006 tank/home/cindys@today
```

In addition, the following shortcut syntax provides equivalent snapshot renaming syntax as the example above.

```
# zfs rename tank/home/cindys@083006 today
```

The following snapshot rename operation is not supported because the target pool and file system name are different from the pool and file system where the snapshot was created.

```
# zfs rename tank/home/cindys@today pool/home/cindys@aturday
cannot rename to 'pool/home/cindys@today': snapshots must be part of same
dataset
```

Displaying and Accessing ZFS Snapshots

Snapshots of file systems are accessible in the `.zfs/snapshot` directory within the root of the containing file system. For example, if `tank/home/ahrens` is mounted on `/home/ahrens`, then the `tank/home/ahrens@thursday` snapshot data is accessible in the `/home/ahrens/.zfs/snapshot/thursday` directory.

```
# ls /tank/home/ahrens/.zfs/snapshot
tuesday wednesday thursday
```

You can list snapshots as follows:

```
# zfs list -t snapshot
NAME                                USED  AVAIL  REFER  MOUNTPOINT
pool/home/anne@monday              0     -    780K  -
pool/home/bob@monday               0     -    1.01M  -
tank/home/ahrens@tuesday           8.50K  -    780K  -
tank/home/ahrens@wednesday        8.50K  -    1.01M  -
tank/home/ahrens@thursday          0     -    1.77M  -
tank/home/cindys@today             8.50K  -    524K  -
```

You can list snapshots that were created for a particular file system as follows:

```
# zfs list -r -t snapshot -o name,creation tank/home
NAME                                CREATION
tank/home@now                        Wed Aug 30 10:53 2006
tank/home/ahrens@tuesday             Wed Aug 30 10:53 2006
tank/home/ahrens@wednesday          Wed Aug 30 10:54 2006
tank/home/ahrens@thursday           Wed Aug 30 10:53 2006
tank/home/cindys@now                 Wed Aug 30 10:57 2006
```

Snapshot Space Accounting

When a snapshot is created, its space is initially shared between the snapshot and the file system, and possibly with previous snapshots. As the file system changes, space that was previously shared becomes unique to the snapshot, and thus is counted in the snapshot's used property. Additionally, deleting snapshots can increase the amount of space unique to (and thus *used* by) other snapshots.

A snapshot's space referenced property is the same as the file system's was when the snapshot was created.

Rolling Back to a ZFS Snapshot

The `zfs rollback` command can be used to discard all changes made since a specific snapshot. The file system reverts to its state at the time the snapshot was taken. By default, the command cannot roll back to a snapshot other than the most recent snapshot.

To roll back to an earlier snapshot, all intermediate snapshots must be destroyed. You can destroy earlier snapshots by specifying the `-r` option.

If clones of any intermediate snapshots exist, the `-R` option must be specified to destroy the clones as well.

Note – The file system that you want to roll back must be unmounted and remounted, if it is currently mounted. If the file system cannot be unmounted, the rollback fails. The `-f` option forces the file system to be unmounted, if necessary.

In the following example, the `tank/home/ahrens` file system is rolled back to the `tuesday` snapshot:

```
# zfs rollback tank/home/ahrens@tuesday
cannot rollback to 'tank/home/ahrens@tuesday': more recent snapshots exist
use '-r' to force deletion of the following snapshots:
tank/home/ahrens@wednesday
tank/home/ahrens@thursday
# zfs rollback -r tank/home/ahrens@tuesday
```

In the above example, the wednesday and thursday snapshots are removed because you rolled back to the previous tuesday snapshot.

```
# zfs list -r -t snapshot -o name,creation tank/home/ahrens
NAME                                CREATION
tank/home/ahrens@tuesday            Wed Aug 30 10:53 2006
```

Overview of ZFS Clones

A *clone* is a writable volume or file system whose initial contents are the same as the dataset from which it was created. As with snapshots, creating a clone is nearly instantaneous, and initially consumes no additional disk space. In addition, you can snapshot a clone.

- [“Creating a ZFS Clone” on page 111](#)
- [“Destroying a ZFS Clone” on page 112](#)
- [“Replacing a ZFS File System With a ZFS Clone” on page 112](#)

Clones can only be created from a snapshot. When a snapshot is cloned, an implicit dependency is created between the clone and snapshot. Even though the clone is created somewhere else in the dataset hierarchy, the original snapshot cannot be destroyed as long as the clone exists. The `origin` property exposes this dependency, and the `zfs destroy` command lists any such dependencies, if they exist.

Clones do not inherit the properties of the dataset from which it was created. Rather, clones inherit their properties based on where the clones are created in the pool hierarchy. Use the `zfs get` and `zfs set` commands to view and change the properties of a cloned dataset. For more information about setting ZFS dataset properties, see [“Setting ZFS Properties” on page 93](#).

Because a clone initially shares all its disk space with the original snapshot, its used property is initially zero. As changes are made to the clone, it uses more space. The used property of the original snapshot does not consider the disk space consumed by the clone.

Creating a ZFS Clone

To create a clone, use the `zfs clone` command, specifying the snapshot from which to create the clone, and the name of the new file system or volume. The new file system or volume can be located anywhere in the ZFS hierarchy. The type of the new dataset (for example, file system or volume) is the same type as the snapshot from which the clone was created. You cannot create clone of a file system in a pool that is different from where the original file system snapshot resides.

In the following example, a new clone named `tank/home/ahrens/bug123` with the same initial contents as the snapshot `tank/ws/gate@yesterday` is created.

```
# zfs snapshot tank/ws/gate@yesterday
# zfs clone tank/ws/gate@yesterday tank/home/ahrens/bug123
```

In the following example, a cloned workspace is created from the projects/newproject@today snapshot for a temporary user as projects/teamA/tempuser. Then, properties are set on the cloned workspace.

```
# zfs snapshot projects/newproject@today
# zfs clone projects/newproject@today projects/teamA/tempuser
# zfs set sharenfs=on projects/teamA/tempuser
# zfs set quota=5G projects/teamA/tempuser
```

Destroying a ZFS Clone

ZFS clones are destroyed by using the `zfs destroy` command. For example:

```
# zfs destroy tank/home/ahrens/bug123
```

Clones must be destroyed before the parent snapshot can be destroyed.

Replacing a ZFS File System With a ZFS Clone

You can use the `zfs promote` command to replace an active ZFS file system with a clone of that file system. This feature facilitates the ability to clone and replace file systems so that the “origin” file system become the clone of the specified file system. In addition, this feature makes it possible to destroy the file system from which the clone was originally created. Without clone promotion, you cannot destroy a “origin” file system of active clones. For more information about destroying clones, see [“Destroying a ZFS Clone” on page 112](#).

In the following example, the `tank/test/productA` file system is cloned and then the clone file system, `tank/test/productAbeta` becomes the `tank/test/productA` file system.

```
# zfs create tank/test
# zfs create tank/test/productA
# zfs snapshot tank/test/productA@today
# zfs clone tank/test/productA@today tank/test/productAbeta
# zfs list -r tank/test
NAME                USED  AVAIL  REFER  MOUNTPOINT
tank/test            314K  8.24G  25.5K  /tank/test
tank/test/productA  288K  8.24G  288K   /tank/test/productA
tank/test/productA@today  0     -      288K   -
tank/test/productAbeta  0     8.24G  288K   /tank/test/productAbeta
# zfs promote tank/test/productAbeta
# zfs list -r tank/test
NAME                USED  AVAIL  REFER  MOUNTPOINT
```



```
tank/test          316K 8.24G 27.5K /tank/test
tank/test/productA      0 8.24G 288K /tank/test/productA
tank/test/productAbeta 288K 8.24G 288K /tank/test/productAbeta
tank/test/productAbeta@today  0 - 288K -
```

In the above `zfs -list` output, you can see that the space accounting of the original `productA` file system has been replaced with the `productAbeta` file system.

Complete the clone replacement process by renaming the file systems. For example:

```
# zfs rename tank/test/productA tank/test/productAlegacy
# zfs rename tank/test/productAbeta tank/test/productA
# zfs list -r tank/test
NAME                USED  AVAIL  REFER  MOUNTPOINT
tank/test            316K  8.24G  27.5K  /tank/test
tank/test/productA  288K  8.24G  288K  /tank/test/productA
tank/test/productA@today  0    -    288K  -
tank/test/productAlegacy  0  8.24G  288K  /tank/test/productAlegacy
```

Optionally, you can remove the legacy file system. For example:

```
# zfs destroy tank/test/productAlegacy
```

Saving and Restoring ZFS Data

The `zfs send` command creates a stream representation of a snapshot that is written to standard output. By default, a full stream is generated. You can redirect the output to a file or to a different system. The `zfs receive` command creates a snapshot whose contents are specified in the stream that is provided on standard input. If a full stream is received, a new file system is created as well. You can save ZFS snapshot data and restore ZFS snapshot data and file systems with these commands. See the examples in the next section.

- [“Saving ZFS Data With Other Backup Products” on page 114](#)
- [“Saving a ZFS Snapshot” on page 114](#)
- [“Restoring a ZFS Snapshot” on page 115](#)
- [“Remote Replication of ZFS Data” on page 116](#)

The following solutions for saving ZFS data are provided:

- Saving ZFS snapshots and rolling back snapshots, if necessary.
- Saving full and incremental copies of ZFS snapshots and restoring the snapshots and file systems, if necessary.
- Remotely replicating ZFS file systems by saving and restoring ZFS snapshots and file systems.
- Saving ZFS data with archive utilities such as `tar` and `cpio` or third-party backup products.

Consider the following when choosing a solution for saving ZFS data:

- File system snapshots and rolling back snapshots – Use the `zfs snapshot` and `zfs rollback` commands if you want to easily create a copy of a file system and revert back to a previous file system version, if necessary. For example, if you want to restore a file or files from a previous version of a file system, you could use this solution.

For more information about creating and rolling back to a snapshot, see [“Overview of ZFS Snapshots” on page 107](#).

- Saving snapshots – Use the `zfs send` and `zfs receive` commands to save and restore a ZFS snapshot. You can save incremental changes between snapshots, but you cannot restore files individually. You must restore the entire file system snapshot.
- Remote replication – Use the `zfs send` and `zfs receive` commands when you want to copy a file system from one system to another. This process is different from a traditional volume management product that might mirror devices across a WAN. No special configuration or hardware is required. The advantage of replicating a ZFS file system is that you can re-create a file system on a storage pool on another system, and specify different levels of configuration for the newly created pool, such as RAID-Z, but with identical file system data.

Saving ZFS Data With Other Backup Products

In addition to the `zfs send` and `zfs receive` commands, you can also use archive utilities, such as the `tar` and `cpio` commands, to save ZFS files. All of these utilities save and restore ZFS file attributes and ACLs. Check the appropriate options for both the `tar` and `cpio` commands.

For up-to-date information about issues with ZFS and third-party backup products, please see the Solaris Express release notes.

Saving a ZFS Snapshot

The most common use of the `zfs send` command is to save a copy of a snapshot and receive the snapshot on another system that is used to store backup data. For example:

```
host1# zfs send tank/dana@snap1 | ssh host2 zfs recv newtank/dana
```

When sending a full stream, the destination file system must not exist.

You can save incremental data by using the `zfs send -i` option. For example:

```
host1# zfs send -i tank/dana@snap1 tank/dana@snap2 | ssh host2 zfs recv newtank/dana
```

Note that the first argument is the earlier snapshot and the second argument is the later snapshot. In this case, the `newtank/dana` file system must exist for the incremental receive to be successful.

The incremental *snapshot1* source can be specified as the last component of the snapshot name. This shortcut means you only have to specify the name after the @ sign for *snapshot1*, which is assumed to be from the same file system as *snapshot2*. For example:

```
host1# zfs send -i snap1 tank/dana@snap2 > ssh host2 zfs recv newtank/dana
```

This syntax is equivalent to the above example of the incremental syntax.

The following message is displayed if you attempt to generate an incremental stream from a different file system *snapshot1*:

```
cannot send 'pool/fs@name': not an earlier snapshot from the same fs
```

If you need to store many copies, you might consider compressing a ZFS snapshot stream representation with the `gzip` command. For example:

```
# zfs send pool/fs@snap | gzip > backupfile.gz
```

Restoring a ZFS Snapshot

Keep the following key points in mind when you restore a file system snapshot:

- The snapshot and the file system are restored.
- The file system and all descendant file systems are unmounted.
- The file systems are inaccessible while they are being restored.
- The original file system to be restored must not exist while it is being restored.
- If a conflicting file system name exists, `zfs rename` can be used to rename the file system.

For example:

```
# zfs send tank/gozer@0830 > /bkups/gozer.083006
# zfs receive tank/gozer2@today < /bkups/gozer.083006
# zfs rename tank/gozer tank/gozer.old
# zfs rename tank/gozer2 tank/gozer
```

You can use `zfs recv` as an alias for the `zfs receive` command.

If you make a change to the file system and you want to do another incremental send of a snapshot, you must first rollback the receiving file system.

For example, if you make a change to the file system as follows:

```
host2# rm newtank/dana/file.1
```

And you do an incremental send of `tank/dana@snap3`, you must first rollback the receiving file system to receive the new incremental snapshot. You can eliminate the rollback step by using the `-F` option. For example:

```
host1# zfs send -i tank/dana@snap2 tank/dana@snap3 | ssh host2 zfs recv -F newtank/dana
```

When you receive an incremental snapshot, the destination file system must already exist.

If you make changes to the file system and you do not rollback the receiving file system to receive the new incremental snapshot or you do not use the `-F` option, you will see the following message:

```
host1# zfs send -i tank/dana@snap4 tank/dana@snap5 | ssh host2 zfs recv newtank/dana
cannot receive: destination has been modified since most recent snapshot
```

The following checks are performed before the `-F` option is successful:

- If the most recent snapshot doesn't match the incremental source, neither the rollback nor the receive is completed, and an error message is returned.
- If you accidentally provide the name of different file system that doesn't match the incremental source to the `zfs receive` command, neither the rollback nor the receive is completed, and the following error message is returned.

```
cannot send 'pool/fs@name': not an earlier snapshot from the same fs
```

Remote Replication of ZFS Data

You can use the `zfs send` and `zfs recv` commands to remotely copy a snapshot stream representation from one system to another system. For example:

```
# zfs send tank/cindy@today | ssh newsys zfs recv sandbox/restfs@today
```

This command saves the `tank/cindy@today` snapshot data and restores it into the `sandbox/restfs` file system and also creates a `restfs@today` snapshot on the `newsys` system. In this example, the user has been configured to use `ssh` on the remote system.

Using ACLs to Protect ZFS Files

This chapter provides information about using access control lists (ACLs) to protect your ZFS files by providing more granular permissions than the standard UNIX permissions.

The following sections are provided in this chapter:

- “New Solaris ACL Model” on page 117
- “Setting ACLs on ZFS Files” on page 123
- “Setting and Displaying ACLs on ZFS Files in Verbose Format” on page 125
- “Setting and Displaying ACLs on ZFS Files in Compact Format” on page 139

New Solaris ACL Model

Recent previous versions of Solaris supported an ACL implementation that was primarily based on the POSIX-draft ACL specification. The POSIX-draft based ACLs are used to protect UFS files and are translated by versions of NFS prior to NFSv4.

With the introduction of NFSv4, a new ACL model fully supports the interoperability that NFSv4 offers between UNIX and non-UNIX clients. The new ACL implementation, as defined in the NFSv4 specification, provides much richer semantics that are based on NT-style ACLs.

The main differences of the new ACL model are as follows:

- Based on the NFSv4 specification and similar to NT-style ACLs.
- Provide much more granular set of access privileges. For more information, see [Table 7–2](#).
- Set and displayed with the `chmod` and `ls` commands rather than the `setfacl` and `getfacl` commands.
- Provide richer inheritance semantics for designating how access privileges are applied from directory to subdirectories, and so on. For more information, see “[ACL Inheritance](#)” on [page 121](#).

Both ACL models provide more fine-grained access control than is available with the standard file permissions. Much like POSIX-draft ACLs, the new ACLs are composed of multiple Access Control Entries (ACEs).

POSIX-draft style ACLs use a single entry to define what permissions are allowed and what permissions are denied. The new ACL model has two types of ACEs that affect access checking: `ALLOW` and `DENY`. As such, you cannot infer from any single ACE that defines a set of permissions whether or not the permissions that weren't defined in that ACE are allowed or denied.

Translation between NFSv4-style ACLs and POSIX-draft ACLs is as follows:

- If you use any ACL-aware utility, such as the `cp`, `mv`, `tar`, `cpio`, or `rcp` commands, to transfer UFS files with ACLs to a ZFS file system, the POSIX-draft ACLs are translated into the equivalent NFSv4-style ACLs.
- Some NFSv4-style ACLs are translated to POSIX-draft ACLs. You see a message similar to the following if an NFSv4-style ACL isn't translated to a POSIX-draft ACL:

```
# cp -p filea /var/tmp
cp: failed to set acl entries on /var/tmp/filea
```

- If you create a UFS `tar` or `cpio` archive with the preserve ACL option (`tar -p` or `cpio -P`) on a system that runs a current Solaris release, you will lose the ACLs when the archive is extracted on a system that runs a previous Solaris release.

All of the files are extracted with the correct file modes, but the ACL entries are ignored.

- You can use the `ufs restore` command to restore data into a ZFS file system, but the ACLs will be lost.
- If you attempt to set an NFSv4-style ACL on a UFS file, you see a message similar to the following:

```
chmod: ERROR: ACL type's are different
```

- If you attempt to set a POSIX-style ACL on a ZFS file, you will see messages similar to the following:

```
# getfacl filea
File system doesn't support aclent_t style ACL's.
See acl(5) for more information on Solaris ACL support.
```

For information about other limitations with ACLs and backup products, see [“Saving ZFS Data With Other Backup Products” on page 114](#).

Syntax Descriptions for Setting ACLs

Two basic ACL formats are provided as follows:

Syntax for Setting Trivial ACLs

```

chmod [options] A[index]{+|=}owner@ |group@
|everyone@:access-permissions/...[:inheritance-flags]:deny | allow file

chmod [options] A-owner@, group@,
everyone@:access-permissions/...[:inheritance-flags]:deny | allow file ...

chmod [options] A[index]- file

```

Syntax for Setting Non-Trivial ACLs

```

chmod [options]
A[index]{+|=}user|group:name:access-permissions/...[:inheritance-flags]:deny | allow file

chmod [options] A-user|group:name:access-permissions/...[:inheritance-flags]:deny |
allow file ...

chmod [options] A[index]- file

```

owner@, group@, everyone@

Identifies the *ACL-entry-type* for trivial ACL syntax. For a description of *ACL-entry-types*, see [Table 7-1](#).

user or group:ACL-entry-ID=username or groupname

Identifies the *ACL-entry-type* for explicit ACL syntax. The user and group *ACL-entry-type* must also contain the *ACL-entry-ID*, *username* or *groupname*. For a description of *ACL-entry-types*, see [Table 7-1](#).

access-permissions/.../

Identifies the access permissions that are granted or denied. For a description of ACL access privileges, see [Table 7-2](#).

inheritance-flags

Identifies an optional list of ACL inheritance flags. For a description of the ACL inheritance flags, see [Table 7-3](#).

deny | allow

Identifies whether the access permissions are granted or denied.

In the following example, the *ACL-entry-ID* value is not relevant.

```
group@:write_data/append_data/execute:deny
```

The following example includes an *ACL-entry-ID* because a specific user (*ACL-entry-type*) is included in the ACL.

```
0:user:gozer:list_directory/read_data/execute:allow
```

When an ACL entry is displayed, it looks similar to the following:

```
2:group@:write_data/append_data/execute:deny
```

The **2** or the *index-ID* designation in this example identifies the ACL entry in the larger ACL, which might have multiple entries for owner, specific UIDs, group, and everyone. You can specify the *index-ID* with the `chmod` command to identify which part of the ACL you want to modify. For example, you can identify index ID 3 as `A3` to the `chmod` command, similar to the following:

```
chmod A3=user:venkman:read_acl:allow filename
```

ACL entry types, which are the ACL representations of owner, group, and other, are described in the following table.

TABLE 7-1 ACL Entry Types

ACL Entry Type	Description
owner@	Specifies the access granted to the owner of the object.
group@	Specifies the access granted to the owning group of the object.
everyone@	Specifies the access granted to any user or group that does not match any other ACL entry.
user	With a user name, specifies the access granted to an additional user of the object. Must include the <i>ACL-entry-ID</i> , which contains a <i>username</i> or <i>userID</i> . If the value is not a valid numeric UID or <i>username</i> , the ACL entry type is invalid.
group	With a group name, specifies the access granted to an additional group of the object. Must include the <i>ACL-entry-ID</i> , which contains a <i>groupname</i> or <i>groupID</i> . If the value is not a valid numeric GID or <i>groupname</i> , the ACL entry type is invalid.

ACL access privileges are described in the following table.

TABLE 7-2 ACL Access Privileges

Access Privilege	Compact Access Privilege	Description
add_file	w	Permission to add a new file to a directory.
add_subdirectory	p	On a directory, permission to create a subdirectory.
append_data	p	Placeholder. Not currently implemented.
delete	d	Permission to delete a file.
delete_child	D	Permission to delete a file or directory within a directory.
execute	x	Permission to execute a file or search the contents of a directory.
list_directory	r	Permission to list the contents of a directory.

TABLE 7-2 ACL Access Privileges (Continued)

Access Privilege	Compact Access Privilege	Description
read_acl	c	Permission to read the ACL (ls).
read_attributes	a	Permission to read basic attributes (non-ACLs) of a file. Think of basic attributes as the stat level attributes. Allowing this access mask bit means the entity can execute <code>ls(1)</code> and <code>stat(2)</code> .
read_data	r	Permission to read the contents of the file.
read_xattr	R	Permission to read the extended attributes of a file or perform a lookup in the file's extended attributes directory.
synchronize	s	Placeholder. Not currently implemented.
write_xattr	A	Permission to create extended attributes or write to the extended attributes directory. Granting this permission to a user means that the user can create an extended attribute directory for a file. The attribute file's permissions control the user's access to the attribute.
write_data	w	Permission to modify or replace the contents of a file.
write_attributes	W	Permission to change the times associated with a file or directory to an arbitrary value.
write_acl	C	Permission to write the ACL or the ability to modify the ACL by using the <code>chmod</code> command.
write_owner	o	Permission to change the file's owner or group. Or, the ability to execute the <code>chown</code> or <code>chgrp</code> commands on the file. Permission to take ownership of a file or permission to change the group ownership of the file to a group of which the user is a member. If you want to change the file or group ownership to an arbitrary user or group, then the <code>PRIV_FILE_CHOWN</code> privilege is required.

ACL Inheritance

The purpose of using ACL inheritance is so that a newly created file or directory can inherit the ACLs they are intended to inherit, but without disregarding the existing permission bits on the parent directory.

By default, ACLs are not propagated. If you set a non-trivial ACL on a directory, it is not inherited to any subsequent directory. You must specify the inheritance of an ACL on a file or directory.

The optional inheritance flags are described in the following table.

TABLE 7-3 ACL Inheritance Flags

Inheritance Flag	Compact Inheritance Flag	Description
<code>file_inherit</code>	<code>f</code>	Only inherit the ACL from the parent directory to the directory's files.
<code>dir_inherit</code>	<code>d</code>	Only inherit the ACL from the parent directory to the directory's subdirectories.
<code>inherit_only</code>	<code>i</code>	Inherit the ACL from the parent directory but applies only to newly created files or subdirectories and not the directory itself. This flag requires the <code>file_inherit</code> flag, the <code>dir_inherit</code> flag, or both, to indicate what to inherit.
<code>no_propagate</code>	<code>n</code>	Only inherit the ACL from the parent directory to the first-level contents of the directory, not the second-level or subsequent contents. This flag requires the <code>file_inherit</code> flag, the <code>dir_inherit</code> flag, or both, to indicate what to inherit.

In addition, you can set a default ACL inheritance policy on the file system that is more strict or less strict by using the `aclinherit` file system property. For more information, see the next section.

ACL Property Modes

The ZFS file system includes two property modes related to ACLs:

- `aclinherit` – This property determines the behavior of ACL inheritance. Values include the following:
 - `discard` – For new objects, no ACL entries are inherited when a file or directory is created. The ACL on the file or directory is equal to the permission mode of the file or directory.
 - `noallow` – For new objects, only inheritable ACL entries that have an access type of deny are inherited.
 - `secure` – For new objects, the `write_owner` and `write_acl` permissions are removed when an ACL entry is inherited.
 - `passthrough` – For new objects, the inheritable ACL entries are inherited with no changes made to them. This mode, in effect, disables secure mode.

The default mode for the `aclinherit` is `secure`.

- `aclmode` – This property modifies ACL behavior whenever a file or directory's mode is modified by the `chmod` command or when a file is initially created. Values include the following:

- `discard` – All ACL entries are removed except for the entries needed to define the mode of the file or directory.
- `groupmask` – User or group ACL permissions are reduced so that they are no greater than the group permission bits, unless it is a user entry that has the same UID as the owner of the file or directory. Then, the ACL permissions are reduced so that they are no greater than owner permission bits.
- `passthrough` – For new objects, the inheritable ACL entries are inherited with no changes made to the them.

The default mode for the `aclmode` property is `groupmask`.

Setting ACLs on ZFS Files

As implemented with ZFS, ACLs are composed of an array of ACL entries. ZFS provides a *pure* ACL model, where all files have an ACL. Typically, the ACL is *trivial* in that it only represents the traditional UNIX `owner/group/other` entries.

ZFS files still have permission bits and a mode, but these values are more of a cache of what the ACL represents. As such, if you change the permissions of the file, the file's ACL is updated accordingly. In addition, if you remove a non-trivial ACL that granted a user access to a file or directory, that user could still have access to the file or directory because of the file or directory's permission bits that grant access to group or everyone. All access control decisions are governed by the permissions represented in a file or directory's ACL.

The primary rules of ACL access on a ZFS file are as follows:

- ZFS processes ACL entries in the order they are listed in the ACL, from the top down.
- Only ACL entries that have a “who” that matches the requester of the access are processed.
- Once an allow permission has been granted, it cannot be denied by a subsequent ACL deny entry in the same ACL permission set.
- The owner of the file is granted the `write_acl` permission unconditionally, even if the permission is explicitly denied. Otherwise, any permission left unspecified is denied.

In the cases of deny permissions or when an access permission is missing, the privilege subsystem determines what access request is granted for the owner of the file or for superuser. This mechanism prevents owners of files from getting locked out of their files and enables superuser to modify files for recovery purposes.

If you set a non-trivial ACL on a directory, the ACL is not automatically inherited by the directory's children. If you set a non-trivial ACL and you want it inherited to the directory's children, you have to use the ACL inheritance flags. For more information, see [Table 7-3](#) and “[Setting ACL Inheritance on ZFS Files in Verbose Format](#)” on page 131.

When you create a new file and depending on the `umask` value, a default trivial ACL, similar to the following, is applied:

```
$ ls -v file.1
-r--r--r-- 1 root    root      206663 May  4 11:52 file.1
 0:owner@:write_data/append_data/execute:deny
 1:owner@:read_data/write_xattr/write_attributes/write_acl/write_owner
   :allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

Note that each user category (owner@, group@, everyone@) in this example has two ACL entries. One entry for deny permissions, and one entry is for allow permissions.

A description of this file ACL is as follows:

- 0:owner@ The owner is denied execute permissions to the file (execute:deny).
- 1:owner@ The owner can read and modify the contents of the file (read_data/write_data/append_data). The owner can also modify the file's attributes such as timestamps, extended attributes, and ACLs (write_xattr/write_attributes/write_acl). In addition, the owner can modify the ownership of the file (write_owner:allow)
- 2:group@ The group is denied modify and execute permissions to the file (write_data/append_data/execute:deny).
- 3:group@ The group is granted read permissions to the file (read_data:allow).
- 4:everyone@ Everyone who is not user or group is denied permission to execute or modify the contents of the file and to modify any attributes of the file (write_data/append_data/write_xattr/execute/write_attributes/write_acl/write_owner:deny).
- 5:everyone@ Everyone who is not user or group is granted read permissions to the file, and the file's attributes (read_data/read_xattr/read_attributes/read_acl/synchronize:allow). The synchronize access permission is not currently implemented.

When a new directory is created and depending on the umask value, a default directory ACL is similar to the following:

```
$ ls -dv dir.1
drwxr-xr-x 2 root    root      2 Feb 23 10:37 dir.1
 0:owner@::deny
 1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
```

```

2:group@:add_file/write_data/add_subdirectory/append_data:deny
3:group@:list_directory/read_data/execute:allow
4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
5:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

A description of this directory ACL is as follows:

- 0:owner@ The owner deny list is empty for the directory (: : deny).
- 1:owner@ The owner can read and modify the directory contents (list_directory/read_data/add_file/write_data/add_subdirectory/append_data), search the contents (execute), and modify the file's attributes such as timestamps, extended attributes, and ACLs (write_xattr/write_attributes/write_acl). In addition, the owner can modify the ownership of the directory (write_owner:allow).
- 2:group@ The group cannot add to or modify the directory contents (add_file/write_data/add_subdirectory/append_data : deny).
- 3:group@ The group can list and read the directory contents. In addition, the group has execute permission to search the directory contents (list_directory/read_data/execute:allow).
- 4:everyone@ Everyone who is not user or group is denied permission to add to or modify the contents of the directory (add_file/write_data/add_subdirectory/append_data). In addition, the permission to modify any attributes of the directory is denied. (write_xattr/write_attributes/write_acl/write_owner:deny).
- 5:everyone@ Everyone who is not user or group is granted read and execute permissions to the directory contents and the directory's attributes (list_directory/read_data/read_xattr/execute/read_attributes/read_acl/synchronize:allow). The synchronize access permission is not currently implemented.

Setting and Displaying ACLs on ZFS Files in Verbose Format

You can use the `chmod` command to modify ACLs on ZFS files. The following `chmod` syntax for modifying ACLs uses *acl-specification* to identify the format of the ACL. For a description of *acl-specification*, see “[Syntax Descriptions for Setting ACLs](#)” on page 118.

- Adding ACL entries
 - Adding an ACL entry for a user

```
% chmod A+acl-specification filename
```

- Adding an ACL entry by *index-ID*

```
% chmod Aindex-ID+acl-specification filename
```

This syntax inserts the new ACL entry at the specified *index-ID* location.

- Replacing an ACL entry

```
% chmod Aindex-ID=acl-specification filename
```

```
% chmod A=acl-specification filename
```

- Removing ACL entries

- Removing an ACL entry by *index-ID*

```
% chmod Aindex-ID- filename
```

- Removing an ACL entry by user

```
% chmod A-acl-specification filename
```

- Removing all non-trivial ACEs from a file

```
% chmod A- filename
```

Verbose ACL information is displayed by using the `ls -v` command. For example:

```
# ls -v file.1
-rw-r--r--  1 root   root      206663 Feb 16 11:00 file.1
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

For information about using the compact ACL format, see [“Setting and Displaying ACLs on ZFS Files in Compact Format” on page 139](#).

EXAMPLE 7-1 Modifying Trivial ACLs on ZFS Files

This section provides examples of setting and displaying trivial ACLs.

In the following example, a trivial ACL exists on `file.1`:

EXAMPLE 7-1 Modifying Trivial ACLs on ZFS Files (Continued)

```
# ls -v file.1
-rw-r--r--  1 root    root      206663 Feb 16 11:00 file.1
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

In the following example, `write_data` permissions are granted for `group@`.

```
# chmod A2=group@:append_data/execute:deny file.1
# chmod A3=group@:read_data/write_data:allow file.1
# ls -v file.1
-rw-rw-r--  1 root    root      206663 May  3 16:36 file.1
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:append_data/execute:deny
 3:group@:read_data/write_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

In the following example, permissions on `file.1` are set back to 644.

```
# chmod 644 file.1
# ls -v file.1
-rw-r--r--  1 root    root      206663 May  3 16:36 file.1
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

EXAMPLE 7-2 Setting Non-Trivial ACLs on ZFS Files

This section provides examples of setting and displaying non-trivial ACLs.

In the following example, `read_data/execute` permissions are added for the user `gozer` on the `test.dir` directory.

```
# chmod A+user:gozer:read_data/execute:allow test.dir
# ls -dv test.dir
drwxr-xr-x+ 2 root    root          2 Feb 16 11:12 test.dir
 0:user:gozer:list_directory/read_data/execute:allow
 1:owner@::deny
 2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
 3:group@:add_file/write_data/add_subdirectory/append_data:deny
 4:group@:list_directory/read_data/execute:allow
 5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
   /write_attributes/write_acl/write_owner:deny
 6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
   /read_acl/synchronize:allow
```

In the following example, `read_data/execute` permissions are removed for user `gozer`.

```
# chmod A0- test.dir
# ls -dv test.dir
drwxr-xr-x 2 root    root          2 Feb 16 11:12 test.dir
 0:owner@::deny
 1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
 2:group@:add_file/write_data/add_subdirectory/append_data:deny
 3:group@:list_directory/read_data/execute:allow
 4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
   /write_attributes/write_acl/write_owner:deny
 5:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
   /read_acl/synchronize:allow
```

EXAMPLE 7-3 ACL Interaction With Permissions on ZFS Files

These ACL examples illustrate the interaction between setting ACLs and then changing the file or directory's permission bits.

In the following example, a trivial ACL exists on `file.2`:

EXAMPLE 7-3 ACL Interaction With Permissions on ZFS Files (Continued)

```
# ls -v file.2
-rw-r--r--  1 root    root      2703 Feb 16 11:16 file.2
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 5:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow
```

In the following example, ACL allow permissions are removed from everyone@.

```
# chmod A5- file.2
# ls -v file.2
-rw-r-----  1 root    root      2703 Feb 16 11:16 file.2
 0:owner@:execute:deny
 1:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 2:group@:write_data/append_data/execute:deny
 3:group@:read_data:allow
 4:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
```

In this output, the file's permission bits are reset from 655 to 650. Read permissions for everyone@ have been effectively removed from the file's permissions bits when the ACL allow permissions are removed for everyone@.

In the following example, the existing ACL is replaced with read_data/write_data permissions for everyone@.

```
# chmod A=everyone@:read_data/write_data:allow file.3
# ls -v file.3
-rw-rw-rw-+  1 root    root      1532 Feb 16 11:18 file.3
 0:everyone@:read_data/write_data:allow
```

In this output, the chmod syntax effectively replaces the existing ACL with read_data/write_data:allow permissions to read/write permissions for owner, group, and everyone@. In this model, everyone@ specifies access to any user or group. Since no owner@ or group@ ACL entry exists to override the permissions for owner and group, the permission bits are set to 666.

In the following example, the existing ACL is replaced with read permissions for user gozer.

EXAMPLE 7-3 ACL Interaction With Permissions on ZFS Files (Continued)

```
# chmod A=user:gozer:read_data:allow file.3
# ls -v file.3
-----+ 1 root    root        1532 Feb 16 11:18 file.3
      0:user:gozer:read_data:allow
```

In this output, the file permissions are computed to be 000 because no ACL entries exist for owner@, group@, or everyone@, which represent the traditional permission components of a file. The owner of the file can resolve this problem by resetting the permissions (and the ACL) as follows:

```
# chmod 655 file.3
# ls -v file.3
-rw-r-xr-x+ 1 root    root            0 Mar  8 13:24 file.3
      0:user:gozer::deny
      1:user:gozer:read_data:allow
      2:owner@:execute:deny
      3:owner@:read_data/write_data/append_data/write_xattr/write_attributes
        /write_acl/write_owner:allow
      4:group@:write_data/append_data:deny
      5:group@:read_data/execute:allow
      6:everyone@:write_data/append_data/write_xattr/write_attributes
        /write_acl/write_owner:deny
      7:everyone@:read_data/read_xattr/execute/read_attributes/read_acl
        /synchronize:allow
```

EXAMPLE 7-4 Restoring Trivial ACLs on ZFS Files

You can use the `chmod` command to remove all non-trivial ACLs on a file or directory.

In the following example, 2 non-trivial ACEs exist on `test5.dir`.

```
# ls -dv test5.dir
drwxr-xr-x+ 2 root    root            2 Feb 16 11:23 test5.dir
      0:user:gozer:read_data:file_inherit:deny
      1:user:lp:read_data:file_inherit:deny
      2:owner@::deny
      3:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
        /append_data/write_xattr/execute/write_attributes/write_acl
        /write_owner:allow
      4:group@:add_file/write_data/add_subdirectory/append_data:deny
      5:group@:list_directory/read_data/execute:allow
      6:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
        /write_attributes/write_acl/write_owner:deny
```

EXAMPLE 7-4 Restoring Trivial ACLs on ZFS Files (Continued)

```
7:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
/read_acl/synchronize:allow
```

In the following example, the non-trivial ACLs for users `gozer` and `lp` are removed. The remaining ACL contains the six default values for `owner@`, `group@`, and `everyone@`.

```
# chmod A- test5.dir
# ls -dv test5.dir
drwxr-xr-x  2 root    root          2 Feb 16 11:23 test5.dir
 0:owner@::deny
 1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
 2:group@:add_file/write_data/add_subdirectory/append_data:deny
 3:group@:list_directory/read_data/execute:allow
 4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
 5:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow
```

Setting ACL Inheritance on ZFS Files in Verbose Format

You can determine how ACLs are inherited or not inherited on files and directories. By default, ACLs are not propagated. If you set a non-trivial ACL on a directory, the ACL is not inherited by any subsequent directory. You must specify the inheritance of an ACL on a file or directory.

In addition, two ACL properties are provided that can be set globally on file systems: `aclinherit` and `aclmode`. By default, `aclinherit` is set to `secure` and `aclmode` is set to `groupmask`.

For more information, see [“ACL Inheritance” on page 121](#).

EXAMPLE 7-5 Default ACL Inheritance

By default, ACLs are not propagated through a directory structure.

In the following example, a non-trivial ACE of `read_data/write_data/execute` is applied for user `gozer` on `test.dir`.

```
# chmod A+user:gozer:read_data/write_data/execute:allow test.dir
# ls -dv test.dir
drwxr-xr-x+ 2 root    root          2 Feb 17 14:45 test.dir
 0:user:gozer:list_directory/read_data/add_file/write_data/execute:allow
```

EXAMPLE 7-5 Default ACL Inheritance (Continued)

```

1:owner@::deny
2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
3:group@:add_file/write_data/add_subdirectory/append_data:deny
4:group@:list_directory/read_data/execute:allow
5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

If a `test.dir` subdirectory is created, the ACE for user `gozer` is not propagated. User `gozer` would only have access to `sub.dir` if the permissions on `sub.dir` granted him access as the file owner, group member, or `everyone@`.

```

# mkdir test.dir/sub.dir
# ls -dv test.dir/sub.dir
drwxr-xr-x  2 root   root           2 Feb 17 14:46 test.dir/sub.dir
0:owner@::deny
1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
2:group@:add_file/write_data/add_subdirectory/append_data:deny
3:group@:list_directory/read_data/execute:allow
4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
5:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

EXAMPLE 7-6 Granting ACL Inheritance on Files and Directories

This series of examples identify the file and directory ACEs that are applied when the `file_inherit` flag is set.

In the following example, `read_data/write_data` permissions are added for files in the `test.dir` directory for user `gozer` so that he has read access on any newly created files.

```

# chmod A+user:gozer:read_data/write_data:file_inherit:allow test2.dir
# ls -dv test2.dir
drwxr-xr-x+  2 root   root           2 Feb 17 14:47 test2.dir
0:user:gozer:read_data/write_data:file_inherit:allow
1:owner@::deny
2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl

```

EXAMPLE 7-6 Granting ACL Inheritance on Files and Directories (Continued)

```

/write_owner:allow
3:group@:add_file/write_data/add_subdirectory/append_data:deny
4:group@:list_directory/read_data/execute:allow
5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
/write_attributes/write_acl/write_owner:deny
6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
/read_acl/synchronize:allow

```

In the following example, user gozer's permissions are applied on the newly created `test2.dir/file.2` file. The ACL inheritance granted, `read_data:file_inherit:allow`, means user gozer can read the contents of any newly created file.

```

# touch test2.dir/file.2
# ls -lv test2.dir/file.2
-rw-r--r--+ 1 root    root          0 Feb 17 14:49 test2.dir/file.2
 0:user:gozer:write_data:deny
 1:user:gozer:read_data/write_data:allow
 2:owner@:execute:deny
 3:owner@:read_data/write_data/append_data/write_xattr/write_attributes+
/write_acl/write_owner:allow
 4:group@:write_data/append_data/execute:deny
 5:group@:read_data:allow
 6:everyone@:write_data/append_data/write_xattr/execute/write_attributes
/write_acl/write_owner:deny
 7:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
:allow

```

Because the `aclmode` for this file is set to the default mode, `groupmask`, user gozer does not have `write_data` permission on `file.2` because the group permission of the file does not allow it.

Note the `inherit_only` permission, which is applied when the `file_inherit` or `dir_inherit` flags are set, is used to propagate the ACL through the directory structure. As such, user gozer is only granted or denied permission from `everyone@` permissions unless he is the owner of the file or a member of the owning group of the file. For example:

```

# mkdir test2.dir/subdir.2
# ls -dv test2.dir/subdir.2
drwxr-xr-x+ 2 root    root          2 Feb 17 14:50 test2.dir/subdir.2
 0:user:gozer:list_directory/read_data/add_file/write_data:file_inherit
/inherit_only:allow
 1:owner@::deny
 2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
/append_data/write_xattr/execute/write_attributes/write_acl
/write_owner:allow
 3:group@:add_file/write_data/add_subdirectory/append_data:deny

```

EXAMPLE 7-6 Granting ACL Inheritance on Files and Directories *(Continued)*

```

4:group@:list_directory/read_data/execute:allow
5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

The following series of examples identify the file and directory ACLs that are applied when both the `file_inherit` and `dir_inherit` flags are set.

In the following example, user `gozer` is granted read, write, and execute permissions that are inherited for newly created files and directories.

```

# chmod A+user:gozer:read_data/write_data/execute:file_inherit/dir_inherit:allow test3.dir
# ls -dv test3.dir
drwxr-xr-x+ 2 root    root          2 Feb 17 14:51 test3.dir
 0:user:gozer:list_directory/read_data/add_file/write_data/execute
  :file_inherit/dir_inherit:allow
 1:owner@::deny
 2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
 3:group@:add_file/write_data/add_subdirectory/append_data:deny
 4:group@:list_directory/read_data/execute:allow
 5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
 6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

# touch test3.dir/file.3
# ls -v test3.dir/file.3
-rw-r--r--+ 1 root    root          0 Feb 17 14:53 test3.dir/file.3
 0:user:gozer:write_data/execute:deny
 1:user:gozer:read_data/write_data/execute:allow
 2:owner@:execute:deny
 3:owner@:read_data/write_data/append_data/write_xattr/write_attributes
  /write_acl/write_owner:allow
 4:group@:write_data/append_data/execute:deny
 5:group@:read_data:allow
 6:everyone@:write_data/append_data/write_xattr/execute/write_attributes
  /write_acl/write_owner:deny
 7:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
  :allow

# mkdir test3.dir/subdir.1
# ls -dv test3.dir/subdir.1

```

EXAMPLE 7-6 Granting ACL Inheritance on Files and Directories (Continued)

```

drwxr-xr-x+ 2 root    root          2 May  4 15:00 test3.dir/subdir.1
 0:user:gozer:list_directory/read_data/add_file/write_data/execute
   :file_inherit/dir_inherit/inherit_only:allow
 1:user:gozer:add_file/write_data:deny
 2:user:gozer:list_directory/read_data/add_file/write_data/execute:allow
 3:owner@::deny
 4:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
 5:group@:add_file/write_data/add_subdirectory/append_data:deny
 6:group@:list_directory/read_data/execute:allow
 7:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
   /write_attributes/write_acl/write_owner:deny
 8:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
   /read_acl/synchronize:allow

```

In these examples, because the permission bits of the parent directory for `group@` and `everyone@` deny write and execute permissions, user `gozer` is denied write and execute permissions. The default `aclmode` property is `secure`, which means that `write_data` and `execute` permissions are not inherited.

In the following example, user `gozer` is granted read, write, and execute permissions that are inherited for newly created files, but are not propagated to subsequent contents of the directory.

```

# chmod A+user:gozer:read_data/write_data/execute:file_inherit/no_propagate:allow test4.dir
# ls -dv test4.dir
drwxr-xr-x+ 2 root    root          2 Feb 17 14:54 test4.dir
 0:user:gozer:list_directory/read_data/add_file/write_data/execute
   :file_inherit/no_propagate:allow
 1:owner@::deny
 2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
 3:group@:add_file/write_data/add_subdirectory/append_data:deny
 4:group@:list_directory/read_data/execute:allow
 5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
   /write_attributes/write_acl/write_owner:deny
 6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
   /read_acl/synchronize:allow

```

As the following example illustrates, when a new subdirectory is created, user `gozer`'s `read_data/write_data/execute` permission for files are not propagated to the new `sub4.dir` directory.

EXAMPLE 7-6 Granting ACL Inheritance on Files and Directories (Continued)

```

# mkdir test4.dir/sub4.dir
# ls -dv test4.dir/sub4.dir
drwxr-xr-x  2 root   root           2 Feb 17 14:57 test4.dir/sub4.dir
 0:owner@:deny
 1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
   /append_data/write_xattr/execute/write_attributes/write_acl
   /write_owner:allow
 2:group@:add_file/write_data/add_subdirectory/append_data:deny
 3:group@:list_directory/read_data/execute:allow
 4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
   /write_attributes/write_acl/write_owner:deny
 5:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
   /read_acl/synchronize:allow

```

As the following example illustrates, gozer's read_data/write_data/execute permission for files is propagated to the newly created file.

```

# touch test4.dir/file.4
# ls -v test4.dir/file.4
-rw-r--r--+ 1 root   root           0 May  4 15:02 test4.dir/file.4
 0:user:gozer:write_data/execute:deny
 1:user:gozer:read_data/write_data/execute:allow
 2:owner@:execute:deny
 3:owner@:read_data/write_data/append_data/write_xattr/write_attributes
   /write_acl/write_owner:allow
 4:group@:write_data/append_data/execute:deny
 5:group@:read_data:allow
 6:everyone@:write_data/append_data/write_xattr/execute/write_attributes
   /write_acl/write_owner:deny
 7:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
   :allow

```

EXAMPLE 7-7 ACL Inheritance With ACL Mode Set to Passthrough

If the aclmode property on the tank/cindy file system is set to passthrough, then user gozer would inherit the ACL applied on test4.dir for the newly created file.4 as follows:

```

# zfs set aclmode=passthrough tank/cindy
# touch test4.dir/file.4
# ls -v test4.dir/file.4
-rw-r--r--+ 1 root   root           0 Feb 17 15:15 test4.dir/file.4
 0:user:gozer:read_data/write_data/execute:allow
 1:owner@:execute:deny
 2:owner@:read_data/write_data/append_data/write_xattr/write_attributes

```


EXAMPLE 7-7 ACL Inheritance With ACL Mode Set to Passthrough (Continued)

```

/write_acl/write_owner:allow
3:group@:write_data/append_data/execute:deny
4:group@:read_data:allow
5:everyone@:write_data/append_data/write_xattr/execute/write_attributes
/write_acl/write_owner:deny
6:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
:allow

```

This output illustrates that the `read_data/write_data/execute:allow:file_inherit/dir_inherit` ACL that was set on the parent directory, `test4.dir`, is passed through to user `gozer`.

EXAMPLE 7-8 ACL Inheritance With ACL Mode Set to Discard

If the `aclmode` property on a file system is set to `discard`, then ACLs can potentially be discarded when the permission bits on a directory change. For example:

```

# zfs set aclmode=discard tank/cindy
# chmod A+user:gozer:read_data/write_data/execute:dir_inherit:allow test5.dir
# ls -dv test5.dir
drwxr-xr-x  2 root   root       2 Feb 16 11:23 test5.dir
 0:user:gozer:list_directory/read_data/add_file/write_data/execute
  :dir_inherit:allow
 1:owner@::deny
 2:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
 3:group@:add_file/write_data/add_subdirectory/append_data:deny
 4:group@:list_directory/read_data/execute:allow
 5:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
 6:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

If, at a later time, you decide to tighten the permission bits on a directory, the non-trivial ACL is discarded. For example:

```

# chmod 744 test5.dir
# ls -dv test5.dir
drwxr--r--  2 root   root       2 Feb 16 11:23 test5.dir
 0:owner@::deny
 1:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow

```

EXAMPLE 7-8 ACL Inheritance With ACL Mode Set to Discard (Continued)

```

2:group@:add_file/write_data/add_subdirectory/append_data/execute:deny
3:group@:list_directory/read_data:allow
4:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /execute/write_attributes/write_acl/write_owner:deny
5:everyone@:list_directory/read_data/read_xattr/read_attributes/read_acl
  /synchronize:allow

```

EXAMPLE 7-9 ACL Inheritance With ACL Inherit Mode Set to Noallow

In the following example, two non-trivial ACLs with file inheritance are set. One ACL allows `read_data` permission, and one ACL denies `read_data` permission. This example also illustrates how you can specify two ACEs in the same `chmod` command.

```

# zfs set aclinherit=nonallow tank/cindy
# chmod A+user:gozer:read_data:file_inherit:deny,user:lp:read_data:file_inherit:allow test6.dir
# ls -dv test6.dir
drwxr-xr-x+ 2 root      root      2 May  4 14:23 test6.dir
 0:user:gozer:read_data:file_inherit:deny
 1:user:lp:read_data:file_inherit:allow
 2:owner@::deny
 3:owner@:list_directory/read_data/add_file/write_data/add_subdirectory
  /append_data/write_xattr/execute/write_attributes/write_acl
  /write_owner:allow
 4:group@:add_file/write_data/add_subdirectory/append_data:deny
 5:group@:list_directory/read_data/execute:allow
 6:everyone@:add_file/write_data/add_subdirectory/append_data/write_xattr
  /write_attributes/write_acl/write_owner:deny
 7:everyone@:list_directory/read_data/read_xattr/execute/read_attributes
  /read_acl/synchronize:allow

```

As the following example shows, when a new file is created, the ACL that allows `read_data` permission is discarded.

```

# touch test6.dir/file.6
# ls -v test6.dir/file.6
-rw-r--r--+ 1 root      root      0 May  4 13:44 test6.dir/file.6
 0:user:gozer:read_data:deny
 1:owner@:execute:deny
 2:owner@:read_data/write_data/append_data/write_xattr/write_attributes
  /write_acl/write_owner:allow
 3:group@:write_data/append_data/execute:deny
 4:group@:read_data:allow
 5:everyone@:write_data/append_data/write_xattr/execute/write_attributes
  /write_acl/write_owner:deny

```

EXAMPLE 7-9 ACL Inheritance With ACL Inherit Mode Set to Noallow (Continued)

```
6:everyone@:read_data/read_xattr/read_attributes/read_acl/synchronize
:allow
```

Setting and Displaying ACLs on ZFS Files in Compact Format

You can set and display permissions on ZFS files in a compact format that uses 14 unique letters to represent the permissions. The letters that represent the compact permissions are listed in [Table 7-2](#) and [Table 7-3](#).

You can display compact ACL listings for files and directories by using the `ls -V` command. For example:

```
# ls -V file.1
-rw-r--r--  1 root    root      206663 Feb 16 11:00 file.1
  owner@:--x-----:-----:deny
  owner@:rw-p---A-W-Co-:-----:allow
  group@:-wxp-----:-----:deny
  group@:r-----:-----:allow
 everyone@:-wxp---A-W-Co-:-----:deny
 everyone@:r-----a-R-c--s:-----:allow
```

The compact ACL output is described as follows:

- owner@ The owner is denied execute permissions to the file (x=execute).
- owner@ The owner can read and modify the contents of the file (rw=read_data/write_data), (p=append_data). The owner can also modify the file's attributes such as timestamps, extended attributes, and ACLs (A=write_xattr,W=write_attributes,C=write_acl). In addition, the owner can modify the ownership of the file (O=write_owner).
- group@ The group is denied modify and execute permissions to the file (rw=read_data/write_data,p=append_data, and x=execute).
- group@ The group is granted read permissions to the file (r=read_data).
- everyone@ Everyone who is not user or group is denied permission to execute or modify the contents of the file, and to modify any attributes of the file (w=write_data, x=execute,p=append_data,A=write_xattr,W=write_attributes,C=write_acl, and o=write_owner).
- everyone@ Everyone who is not user or group is granted read permissions to the file and the file's attributes (r=read_data,a=append_data,R=read_xattr,c=read_acl, and s=synchronize). The synchronize access permission is not currently

implemented.

Compact ACL format provides the following advantages over verbose ACL format:

- Permissions can be specified as positional arguments to the `chmod` command.
- The hyphen (-) characters, which identify no permissions, can be removed and only the required letters need to be specified.
- Both permissions and inheritance flags are set in the same fashion.

For information about using the verbose ACL format, see [“Setting and Displaying ACLs on ZFS Files in Verbose Format” on page 125](#).

EXAMPLE 7-10 Setting and Displaying ACLs in Compact Format

In the following example, a trivial ACL exists on `file.1`:

```
# ls -V file.1
-rw-r-xr-x  1 root    root      206663 Feb 16 11:00 file.1
  owner@: --x-----:-----:deny
  owner@: rw-p---A-W-Co-:-----:allow
  group@: -w-p-----:-----:deny
  group@: r-x-----:-----:allow
  everyone@: -w-p---A-W-Co-:-----:deny
  everyone@: r-x---a-R-c--s:-----:allow
```

In this example, `read_data/execute` permissions are added for the user `gozer` on `file.1`.

```
# chmod A+user:gozer:rx:allow file.1
# ls -V file.1
-rw-r-xr-x+  1 root    root      206663 Feb 16 11:00 file.1
  user:gozer:r-x-----:-----:allow
  owner@: --x-----:-----:deny
  owner@: rw-p---A-W-Co-:-----:allow
  group@: -w-p-----:-----:deny
  group@: r-x-----:-----:allow
  everyone@: -w-p---A-W-Co-:-----:deny
  everyone@: r-x---a-R-c--s:-----:allow
```

Another way to add the same permissions for user `gozer` is to insert a new ACL at a specific position, 4, for example. As such, the existing ACLs at positions 4–6 are pushed down. For example:

```
# chmod A4+user:gozer:rx:allow file.1
# ls -V file.1
-rw-r-xr-x+  1 root    root      206663 Feb 16 11:00 file.1
  owner@: --x-----:-----:deny
  owner@: rw-p---A-W-Co-:-----:allow
```

EXAMPLE 7-10 Setting and Displaying ACLs in Compact Format (Continued)

```

group@: -w-p-----:-----:deny
group@: r-x-----:-----:allow
user:gozer:r-x-----:-----:allow
everyone@: -w-p---A-W-Co-:-----:deny
everyone@: r-x---a-R-c--s:-----:allow

```

In the following example, user `gozer` is granted read, write, and execute permissions that are inherited for newly created files and directories by using the compact ACL format.

```

# chmod A+user:gozer:rw:fd:allow dir.2
# ls -dv dir.2
drwxr-xr-x+ 2 root    root          2 Aug 28 13:21 dir.2
  user:gozer:rw-----:fd----:allow
  owner@:-----:-----:deny
  owner@: rwxp---A-W-Co-:-----:allow
  group@: -w-p-----:-----:deny
  group@: r-x-----:-----:allow
  everyone@: -w-p---A-W-Co-:-----:deny
  everyone@: r-x---a-R-c--s:-----:allow

```

You can also cut and paste permissions and inheritance flags from the `ls -V` output into the compact `chmod` format. For example, to duplicate the permissions and inheritance flags on `dir.1` for user `gozer` to user `cindys`, copy and paste the permission and inheritance flags (`rw-----:f-----:allow`) into your `chmod` command. For example:

```

# chmod A+user:cindys:rw-----:fd----:allow dir.2
# ls -dv dir.2
drwxr-xr-x+ 2 root    root          2 Aug 28 14:12 dir.2
  user:cindys:rw-----:fd----:allow
  user:gozer:rw-----:fd----:allow
  owner@:-----:-----:deny
  owner@: rwxp---A-W-Co-:-----:allow
  group@: -w-p-----:-----:deny
  group@: r-x-----:-----:allow
  everyone@: -w-p---A-W-Co-:-----:deny
  everyone@: r-x---a-R-c--s:-----:allow

```


ZFS Advanced Topics

This chapter describes ZFS volumes, using ZFS on a Solaris system with zones installed, ZFS alternate root pools, and ZFS rights profiles.

The following sections are provided in this chapter:

- “ZFS Volumes” on page 143
- “Using ZFS on a Solaris System With Zones Installed” on page 145
- “Using ZFS Alternate Root Pools” on page 151
- “ZFS Rights Profiles” on page 152

ZFS Volumes

A ZFS *emulated* volume is a dataset that represents a block device and can be used like any block device. ZFS volumes are identified as devices in the `/dev/zvol/{disk,rdsk}/path` directory.

In the following example, 5-Gbyte ZFS volume, `tank/vol`, is created:

```
# zfs create -V 5gb tank/vol
```

When you create a volume, a reservation is automatically set to the initial size of the volume. The reservation size continues to equal the size of the volume so that unexpected behavior doesn't occur. For example, if the size of the volume shrinks, data corruption might occur. You must be careful when changing the size of the volume.

In addition, if you create a snapshot of a volume that changes in size, you might introduce file system inconsistencies if you attempt to rollback the snapshot or create a clone from the snapshot.

For information about file system properties that can be applied to volumes, see [Table 5–1](#).

If you are using a Solaris system with zones installed, you cannot create or clone a ZFS volume in a non-global zone. Any attempt to create or clone a volume from within a non-global zone will fail. For information about using ZFS volumes in a global zone, see [“Adding ZFS Volumes to a Non-Global Zone”](#) on page 148.

Using a ZFS Volume as a Swap or Dump Device

To set up a swap area, create a ZFS volume of a specific size and then enable swap on that device. Do not swap to a file on a ZFS file system. A ZFS swap file configuration is not supported.

In the following example, the 5-Gbyte tank/vol volume is added as a swap device.

```
# swap -a /dev/zvol/dsk/tank/vol
# swap -l
swapfile          dev  swaplo blocks  free
/dev/dsk/c0t0d0s1 32,33  16 1048688 1048688
/dev/zvol/dsk/tank/vol 254,1  16 10485744 10485744
```

Using a ZFS volume as a dump device is not supported. Use the `dumpadm` command to set up a dump device.

Using a ZFS Volume as a Solaris iSCSI Target

Solaris iSCSI targets and initiators are supported in the Solaris Express Community release.

In addition, you can easily create a ZFS volume as a iSCSI target by setting the `shareiscsi` property on the volume. For example:

```
# zfs create -V 2g tank/volumes/v2
# zfs set shareiscsi=on tank/volumes/v2
# iscsitadm list target
Target: tank/volumes/v2
    iSCSI Name: iqn.1986-03.com.sun:02:984fe301-c412-ccc1-cc80-cf9a72aa062a
    Connections: 0
```

After the iSCSI target is created, set up the iSCSI initiator. For more information about Solaris iSCSI targets and initiators, see Chapter 14, “Configuring Solaris iSCSI Targets and Initiators (Tasks),” in *System Administration Guide: Devices and File Systems*.

Note – Solaris iSCSI targets can also be created and managed with `iscsitadm` command. If you set the `shareiscsi` property on a ZFS volume, do not use the `iscsitadm` command to also create the same target device. Otherwise, you will end up with duplicate target information for the same device.

A ZFS volume as an iSCSI target is managed just like other ZFS dataset. However, the rename, export, and import operations work a little differently for iSCSI targets.

- When you rename a ZFS volume, the iSCSI target name remains the same. For example:

```
# zfs rename tank/volumes/v2 tank/volumes/v1
# iscsitadm list target
Target: tank/volumes/v1
    iSCSI Name: iqn.1986-03.com.sun:02:984fe301-c412-ccc1-cc80-cf9a72aa062a
    Connections: 0
```

- Exporting a pool that contains a shared ZFS volume causes the target to be removed. Importing a pool that contains a shared ZFS volume causes the target to be shared. For example:

```
# zpool export tank
# iscsitadm list target
# zpool import tank
# iscsitadm list target
Target: tank/volumes/v1
    iSCSI Name: iqn.1986-03.com.sun:02:984fe301-c412-ccc1-cc80-cf9a72aa062a
    Connections: 0
```

All iSCSI target configuration information is stored with the dataset. Like an NFS shared file system, an iSCSI target that is imported on a different system is shared appropriately.

Using ZFS on a Solaris System With Zones Installed

The following sections describe how to use ZFS on a system with Solaris zones.

- “Adding ZFS File Systems to a Non-Global Zone” on page 146
- “Delegating Datasets to a Non-Global Zone” on page 147
- “Adding ZFS Volumes to a Non-Global Zone” on page 148
- “Using ZFS Storage Pools Within a Zone” on page 148
- “Mangling ZFS Properties Within a Zone” on page 148
- “Understanding the zoned Property” on page 149

Keep the following points in mind when associating ZFS datasets with zones:

- You can add a ZFS file system or a ZFS clone to a non-global with or without delegating administrative control.

- You can add a ZFS volume as a device to non-global zones
- You cannot associate ZFS snapshots with zones at this time

In the sections below, a ZFS dataset refers to a file system or clone.

Adding a dataset allows the non-global zone to share space with the global zone, though the zone administrator cannot control properties or create new file systems in the underlying file system hierarchy. This is identical to adding any other type of file system to a zone, and should be used when the primary purpose is solely to share common space.

ZFS also allows datasets to be delegated to a non-global zone, giving complete control over the dataset and all its children to the zone administrator. The zone administrator can create and destroy file systems or clones within that dataset, and modify properties of the datasets. The zone administrator cannot affect datasets that have not been added to the zone, and cannot exceed any top-level quotas set on the exported dataset.

Consider the following interactions when working with ZFS on a system with Solaris zones installed:

- A ZFS file system that is added to a non-global zone must have its `mountpoint` property set to `legacy`.
- When a source `zonepath` and the target `zonepath` both reside on ZFS and are in the same pool, `zoneadm clone` will now automatically use ZFS `clone` to clone a zone. The `zoneadm clone` command will take a ZFS snapshot of the source `zonepath` and set up the target `zonepath`. Do not use the ZFS snapshot features to clone a zone. For more information, see Part II, “Zones,” in *System Administration Guide: Solaris Containers-Resource Management and Solaris Zones*.

Adding ZFS File Systems to a Non-Global Zone

You can add a ZFS file system as a generic file system when the goal is solely to share space with the global zone. A ZFS file system that is added to a non-global zone must have its `mountpoint` property set to `legacy`.

You can add a ZFS file system to a non-global zone by using the `zonecfg` command's `add fs` subcommand. For example:

In the following example, a ZFS file system is added to a non-global zone by a global administrator in the global zone.

```
# zonecfg -z zion
zion: No such zone configured
Use 'create' to begin configuring a new zone.
zonecfg:zion> create
zonecfg:zion> add fs
```

```

zonecfg:zion:fs> set type=zfs
zonecfg:zion:fs> set special=tank/zone/zion
zonecfg:zion:fs> set dir=/export/shared
zonecfg:zion:fs> end

```

This syntax adds the ZFS file system, `tank/zone/zion`, to the zone `zion`, mounted at `/export/shared`. The mountpoint property of the file system must be set to `legacy`, and the file system cannot already be mounted in another location. The zone administrator can create and destroy files within the file system. The file system cannot be remounted in a different location, nor can the zone administrator change properties on the file system such as `atime`, `readonly`, `compression`, and so on. The global zone administrator is responsible for setting and controlling properties of the file system.

For more information about the `zonecfg` command and about configuring resource types with `zonecfg`, see Part II, “Zones,” in *System Administration Guide: Solaris Containers-Resource Management and Solaris Zones*.

Delegating Datasets to a Non-Global Zone

If the primary goal is to delegate the administration of storage to a zone, then ZFS supports adding datasets to a non-global zone through use of the `zonecfg` command's `add dataset` subcommand.

In the following example, a ZFS file system is delegated to a non-global zone by a global administrator in the global zone.

```

# zonecfg -z zion
zion: No such zone configured
Use 'create' to begin configuring a new zone.
zonecfg:zion> create
zonecfg:zion> add dataset
zonecfg:zion:dataset> set name=tank/zone/zion
zonecfg:zion:dataset> end

```

Unlike adding a file system, this syntax causes the ZFS file system `tank/zone/zion` to be visible within the zone `zion`. The zone administrator can set file system properties, as well as create children. In addition, the zone administrator can take snapshots, create clones, and otherwise control the entire file system hierarchy.

For more information about what actions are allowed within zones, see [“Manging ZFS Properties Within a Zone” on page 148](#).

Adding ZFS Volumes to a Non-Global Zone

Emulated volumes cannot be added to a non-global zone by using the `zonecfg` command's `add dataset` subcommand. If an attempt to add an emulated volume is detected, the zone cannot boot. However, volumes can be added to a zone by using the `zonecfg` command's `add device` subcommand.

In the following example, a ZFS emulated volume is added to a non-global zone by a global administrator in the global zone:

```
# zonecfg -z zion
zion: No such zone configured
Use 'create' to begin configuring a new zone.
zonecfg:zion> create
zonecfg:zion> add device
zonecfg:zion:device> set match=/dev/zvol/dsk/tank/vol
zonecfg:zion:device> end
```

This syntax exports the `tank/vol` emulated volume to the zone. Note that adding a raw volume to a zone has implicit security risks, even if the volume doesn't correspond to a physical device. In particular, the zone administrator could create malformed file systems that would panic the system when a mount is attempted. For more information about adding devices to zones and the related security risks, see [“Understanding the zoned Property” on page 149](#).

For more information about adding devices to zones, see Part II, “Zones,” in *System Administration Guide: Solaris Containers-Resource Management and Solaris Zones*.

Using ZFS Storage Pools Within a Zone

ZFS storage pools cannot be created or modified within a zone. The delegated administration model centralizes control of physical storage devices within the global zone and control of virtual storage to non-global zones. While a pool-level dataset can be added to a zone, any command that modifies the physical characteristics of the pool, such as creating, adding, or removing devices, is not allowed from within a zone. Even if physical devices are added to a zone by using the `zonecfg` command's `add device` subcommand, or if files are used, the `zpool` command does not allow the creation of any new pools within the zone.

Manging ZFS Properties Within a Zone

Once a dataset is added to a zone, the zone administrator can control specific dataset properties. When a dataset is added to a zone, all its ancestors are visible as read-only datasets, while the dataset itself is writable as are all its children. For example, consider the following configuration:

```
global# zfs list -Ho name
tank
tank/home
tank/data
tank/data/matrix
tank/data/zion
tank/data/zion/home
```

If `tank/data/zion` is added to a zone, each dataset would have the following properties.

Dataset	Visible	Writable	Immutable Properties
tank	Yes	No	-
tank/home	No	-	-
tank/data	Yes	No	-
tank/data/matrix	No	-	-
tank/data/zion	Yes	Yes	sharefs, zoned, quota, reservation
tank/data/zion/home	Yes	Yes	sharefs, zoned

Note that every parent of `tank/zone/zion` is visible read-only, all children are writable, and datasets that are not part of the parent hierarchy are not visible at all. The zone administrator cannot change the `sharefs` property, because non-global zones cannot act as NFS servers. Neither can the zone administrator change the `zoned` property, because doing so would expose a security risk as described in the next section.

Any other property can be changed, except for the added dataset itself, where the `quota` and `reservation` properties cannot be changed. This behavior allows the global zone administrator to control the space consumption of all datasets used by the non-global zone.

In addition, the `sharefs` and `mountpoint` properties cannot be changed by the global zone administrator once a dataset has been added to a non-global zone.

Understanding the zoned Property

When a dataset is added to a non-global zone, the dataset must be specially marked so that certain properties are not interpreted within the context of the global zone. Once a dataset has been added to a non-global zone under the control of a zone administrator, its contents can no longer be trusted. As with any file system, there might be `setuid` binaries, symbolic links, or otherwise questionable contents that might adversely affect the security of the global zone. In addition, the `mountpoint` property cannot be interpreted in the context of the global zone.

Otherwise, the zone administrator could affect the global zone's namespace. To address the latter, ZFS uses the `zoned` property to indicate that a dataset has been delegated to a non-global zone at one point in time.

The `zoned` property is a boolean value that is automatically turned on when a zone containing a ZFS dataset is first booted. A zone administrator will not need to manually turn on this property. If the `zoned` property is set, the dataset cannot be mounted or shared in the global zone, and is ignored when the `zfs share -a` command or the `zfs mount -a` command is executed. In the following example, `tank/zone/zion` has been added to a zone, while `tank/zone/global` has not:

```
# zfs list -o name,zoned,mountpoint -r tank/zone
NAME                                ZONED  MOUNTPOINT
tank/zone/global                    off    /tank/zone/global
tank/zone/zion                      on     /tank/zone/zion
# zfs mount
tank/zone/global                    /tank/zone/global
tank/zone/zion                      /export/zone/zion/root/tank/zone/zion
```

Note the difference between the `mountpoint` property and the directory where the `tank/zone/zion` dataset is currently mounted. The `mountpoint` property reflects the property as stored on disk, not where the dataset is currently mounted on the system.

When a dataset is removed from a zone or a zone is destroyed, the `zoned` property is **not** automatically cleared. This behavior is due to the inherent security risks associated with these tasks. Because an untrusted user has had complete access to the dataset and its children, the `mountpoint` property might be set to bad values, or `setuid` binaries might exist on the file systems.

To prevent accidental security risks, the `zoned` property must be manually cleared by the global administrator if you want to reuse the dataset in any way. Before setting the `zoned` property to `off`, make sure that the `mountpoint` property for the dataset and all its children are set to reasonable values and that no `setuid` binaries exist, or turn off the `setuid` property.

Once you have verified that no security vulnerabilities are left, the `zoned` property can be turned off by using the `zfs set` or `zfs inherit` commands. If the `zoned` property is turned off while a dataset is in use within a zone, the system might behave in unpredictable ways. Only change the property if you are sure the dataset is no longer in use by a non-global zone.

Using ZFS Alternate Root Pools

When a pool is created, the pool is intrinsically tied to the host system. The host system maintains knowledge about the pool so that it can detect when the pool is otherwise unavailable. While useful for normal operation, this knowledge can prove a hindrance when booting from alternate media, or creating a pool on removable media. To solve this problem, ZFS provides an *alternate root* pool feature. An alternate root pool does not persist across system reboots, and all mount points are modified to be relative to the root of the pool.

Creating ZFS Alternate Root Pools

The most common use for creating an alternate root pool is for use with removable media. In these circumstances, users typically want a single file system, and they want it to be mounted wherever they choose on the target system. When an alternate root pool is created by using the `-R` option, the mount point of the root file system is automatically set to `/`, which is the equivalent of the alternate root itself.

In the following example, a pool called `morpheus` is created with `/mnt` as the alternate root path:

```
# zpool create -R /mnt morpheus c0t0d0
# zfs list morpheus
```

NAME	USED	AVAIL	REFER	MOUNTPOINT
morpheus	32.5K	33.5G	8K	/mnt/

Note the single file system, `morpheus`, whose mount point is the alternate root of the pool, `/mnt`. The mount point that is stored on disk is `/` and the full path to `/mnt` is interpreted only in the context of the alternate root pool. This file system can then be exported and imported under an arbitrary alternate root pool on a different system.

Importing Alternate Root Pools

Pools can also be imported using an alternate root. This feature allows for recovery situations, where the mount points should not be interpreted in context of the current root, but under some temporary directory where repairs can be performed. This feature also can be used when mounting removable media as described above.

In the following example, a pool called `morpheus` is imported with `/mnt` as the alternate root path. This example assumes that `morpheus` was previously exported.

```
# zpool import -R /mnt morpheus
# zpool list morpheus
```

NAME	SIZE	USED	AVAIL	CAP	HEALTH	ALROOT
morpheus	33.8G	68.0K	33.7G	0%	ONLINE	/mnt

```
# zfs list morpheus
```

NAME	USED	AVAIL	REFER	MOUNTPOINT
morpheus	32.5K	33.5G	8K	/mnt/morpheus

ZFS Rights Profiles

If you want to perform ZFS management tasks without using the superuser (root) account, you can assume a role with either of the following profiles to perform ZFS administration tasks:

- ZFS Storage Management – Provides the ability to create, destroy, and manipulate devices within a ZFS storage pool
- ZFS File system Management – Provides the ability to create, destroy, and modify ZFS file systems

For more information about creating or assigning roles, see *System Administration Guide: Security Services*.

ZFS Troubleshooting and Data Recovery

This chapter describes how to identify and recover from ZFS failure modes. Information for preventing failures is provided as well.

The following sections are provided in this chapter:

- “ZFS Failure Modes” on page 153
- “Checking ZFS Data Integrity” on page 155
- “Identifying Problems in ZFS” on page 157
- “Repairing a Damaged ZFS Configuration” on page 162
- “Repairing a Missing Device” on page 162
- “Repairing a Damaged Device” on page 164
- “Repairing Damaged Data” on page 169
- “Repairing an Unbootable System” on page 173

ZFS Failure Modes

As a combined file system and volume manager, ZFS can exhibit many different failure modes. This chapter begins by outlining the various failure modes, then discusses how to identify them on a running system. This chapter concludes by discussing how to repair the problems. ZFS can encounter three basic types of errors:

- “Missing Devices in a ZFS Storage Pool” on page 154
- “Damaged Devices in a ZFS Storage Pool” on page 154
- “Corrupted ZFS Data” on page 154

Note that a single pool can experience all three errors, so a complete repair procedure involves finding and correcting one error, proceeding to the next error, and so on.

Missing Devices in a ZFS Storage Pool

If a device is completely removed from the system, ZFS detects that the device cannot be opened and places it in the `FAULTED` state. Depending on the data replication level of the pool, this might or might not result in the entire pool becoming unavailable. If one disk in a mirrored or RAID-Z device is removed, the pool continues to be accessible. If all components of a mirror are removed, if more than one device in a RAID-Z device is removed, or if a single-disk, top-level device is removed, the pool becomes `FAULTED`. No data is accessible until the device is reattached.

Damaged Devices in a ZFS Storage Pool

The term “damaged” covers a wide variety of possible errors. Examples include the following errors:

- Transient I/O errors due to a bad disk or controller
- On-disk data corruption due to cosmic rays
- Driver bugs resulting in data being transferred to or from the wrong location
- Simply another user overwriting portions of the physical device by accident

In some cases, these errors are transient, such as a random I/O error while the controller is having problems. In other cases, the damage is permanent, such as on-disk corruption. Even still, whether the damage is permanent does not necessarily indicate that the error is likely to occur again. For example, if an administrator accidentally overwrites part of a disk, no type of hardware failure has occurred, and the device need not be replaced. Identifying exactly what went wrong with a device is not an easy task and is covered in more detail in a later section.

Corrupted ZFS Data

Data corruption occurs when one or more device errors (indicating missing or damaged devices) affects a top-level virtual device. For example, one half of a mirror can experience thousands of device errors without ever causing data corruption. If an error is encountered on the other side of the mirror in the exact same location, corrupted data will be the result.

Data corruption is always permanent and requires special consideration during repair. Even if the underlying devices are repaired or replaced, the original data is lost forever. Most often this scenario requires restoring data from backups. Data errors are recorded as they are encountered, and can be controlled through routine disk scrubbing as explained in the following section. When a corrupted block is removed, the next scrubbing pass recognizes that the corruption is no longer present and removes any trace of the error from the system.

Checking ZFS Data Integrity

No `fsck` utility equivalent exists for ZFS. This utility has traditionally served two purposes, data repair and data validation.

Data Repair

With traditional file systems, the way in which data is written is inherently vulnerable to unexpected failure causing data inconsistencies. Because a traditional file system is not transactional, unreferenced blocks, bad link counts, or other inconsistent data structures are possible. The addition of journaling does solve some of these problems, but can introduce additional problems when the log cannot be rolled back. With ZFS, none of these problems exist. The only way for inconsistent data to exist on disk is through hardware failure (in which case the pool should have been redundant) or a bug in the ZFS software exists.

Given that the `fsck` utility is designed to repair known pathologies specific to individual file systems, writing such a utility for a file system with no known pathologies is impossible. Future experience might prove that certain data corruption problems are common enough and simple enough such that a repair utility can be developed, but these problems can always be avoided by using redundant pools.

If your pool is not redundant, the chance that data corruption can render some or all of your data inaccessible is always present.

Data Validation

In addition to data repair, the `fsck` utility validates that the data on disk has no problems. Traditionally, this task is done by unmounting the file system and running the `fsck` utility, possibly taking the system to single-user mode in the process. This scenario results in downtime that is proportional to the size of the file system being checked. Instead of requiring an explicit utility to perform the necessary checking, ZFS provides a mechanism to perform routine checking of all data. This functionality, known as *scrubbing*, is commonly used in memory and other systems as a method of detecting and preventing errors before they result in hardware or software failure.

Controlling ZFS Data Scrubbing

Whenever ZFS encounters an error, either through scrubbing or when accessing a file on demand, the error is logged internally so that you can get a quick overview of all known errors within the pool.

Explicit ZFS Data Scrubbing

The simplest way to check your data integrity is to initiate an explicit scrubbing of all data within the pool. This operation traverses all the data in the pool once and verifies that all blocks can be read. Scrubbing proceeds as fast as the devices allow, though the priority of any I/O remains below that of normal operations. This operation might negatively impact performance, though the file system should remain usable and nearly as responsive while the scrubbing occurs. To initiate an explicit scrub, use the `zpool scrub` command. For example:

```
# zpool scrub tank
```

The status of the current scrub can be displayed in the `zpool status` output. For example:

```
# zpool status -v tank
pool: tank
state: ONLINE
scrub: scrub completed with 0 errors on Wed Aug 30 14:02:24 2006
config:
```

NAME	STATE	READ	WRITE	CKSUM
tank	ONLINE	0	0	0
mirror	ONLINE	0	0	0
c1t0d0	ONLINE	0	0	0
c1t1d0	ONLINE	0	0	0

```
errors: No known data errors
```

Note that only one active scrubbing operation per pool can occur at one time.

You can stop a scrub that is in progress by using the `-s` option. For example:

```
# zpool scrub -s tank
```

In most cases, a scrub operation to ensure data integrity should continue to completion. Stop a scrub at your own discretion if system performance is impacted by a scrub operation.

Performing routine scrubbing also guarantees continuous I/O to all disks on the system. Routine scrubbing has the side effect of preventing power management from placing idle disks in low-power mode. If the system is generally performing I/O all the time, or if power consumption is not a concern, then this issue can safely be ignored.

For more information about interpreting `zpool status` output, see [“Querying ZFS Storage Pool Status” on page 62](#).

ZFS Data Scrubbing and Resilvering

When a device is replaced, a resilvering operation is initiated to move data from the good copies to the new device. This action is a form of disk scrubbing. Therefore, only one such action can

happen at a given time in the pool. If a scrubbing operation is in progress, a resilvering operation suspends the current scrubbing, and restarts it after the resilvering is complete.

For more information about resilvering, see [“Viewing Resilvering Status”](#) on page 168.

Identifying Problems in ZFS

The following sections describe how to identify problems in your ZFS file systems or storage pools.

- [“Determining if Problems Exist in a ZFS Storage Pool”](#) on page 158
- [“Reviewing zpool status Output”](#) on page 158
- [“System Reporting of ZFS Error Messages”](#) on page 161

You can use the following features to identify problems with your ZFS configuration:

- Detailed ZFS storage pool information with the `zpool status` command
- Pool and device failures are reported with ZFS/FMA diagnostic messages
- Previous ZFS commands that modified pool state information can be displayed with the `zpool history` command

Most ZFS troubleshooting is centered around the `zpool status` command. This command analyzes the various failures in the system and identifies the most severe problem, presenting you with a suggested action and a link to a knowledge article for more information. Note that the command only identifies a single problem with the pool, though multiple problems can exist. For example, data corruption errors always imply that one of the devices has failed. Replacing the failed device does not fix the data corruption problems.

In addition, a ZFS diagnostic engine is provided to diagnose and report pool failures and device failures. Checksum, I/O, device, and pool errors associated with pool or device failures are also reported. ZFS failures as reported by `fmd` are displayed on the console as well as the system messages file. In most cases, the `fmd` message directs you to the `zpool status` command for further recovery instructions.

The basic recovery process is as follows:

- If appropriate, use the `zpool history` command to identify the previous ZFS commands that led up to the error scenario. For example:

```
# zpool history
History for 'tank':
2006-10-23.11:19:06 zpool create tank mirror c1t0d0 c1t1d0
2006-10-23.11:19:31 zfs create tank/erick
2006-10-23.11:19:54 zfs set checksum=off tank/erick
```

Notice in the above output that checksums are disabled for the `tank/erick` file system. This configuration is not recommended.

- Identify the errors through the `fmd` messages that are displayed on the system console or in the `/var/adm/messages` files.
- Find further repair instructions in the `zpool status -x` command.
- Repair the failures, such as:
 - Replace the faulted or missing device and bring it online.
 - Restore the faulted configuration or corrupted data from a backup.
 - Verify the recovery by using the `zpool status -x` command.
 - Back up your restored configuration, if applicable.

This chapter describes how to interpret `zpool status` output in order to diagnose the type of failure and directs you to one of the following sections on how to repair the problem. While most of the work is performed automatically by the command, it is important to understand exactly what problems are being identified in order to diagnose the type of failure.

Determining if Problems Exist in a ZFS Storage Pool

The easiest way to determine if any known problems exist on the system is to use the `zpool status -x` command. This command describes only pools exhibiting problems. If no bad pools exist on the system, then the command displays a simple message, as follows:

```
# zpool status -x
all pools are healthy
```

Without the `-x` flag, the command displays the complete status for all pools (or the requested pool, if specified on the command line), even if the pools are otherwise healthy.

For more information about command-line options to the `zpool status` command, see [“Querying ZFS Storage Pool Status” on page 62](#).

Reviewing `zpool status` Output

The complete `zpool status` output looks similar to the following:

```
# zpool status tank
pool: tank
state: DEGRADED
status: One or more devices has been taken offline by the administrator.
       Sufficient replicas exist for the pool to continue functioning in a
       degraded state.
action: Online the device using 'zpool online' or replace the device with
       'zpool replace'.
scrub: none requested
config:
```

NAME	STATE	READ	WRITE	CKSUM
tank	DEGRADED	0	0	0
mirror	DEGRADED	0	0	0
c1t0d0	ONLINE	0	0	0
c1t1d0	OFFLINE	0	0	0

errors: No known data errors

This output is divided into several sections:

Overall Pool Status Information

This header section in the `zpool status` output contains the following fields, some of which are only displayed for pools exhibiting problems:

<code>pool</code>	The name of the pool.
<code>state</code>	The current health of the pool. This information refers only to the ability of the pool to provide the necessary replication level. Pools that are <code>ONLINE</code> might still have failing devices or data corruption.
<code>status</code>	A description of what is wrong with the pool. This field is omitted if no problems are found.
<code>action</code>	A recommended action for repairing the errors. This field is an abbreviated form directing the user to one of the following sections. This field is omitted if no problems are found.
<code>see</code>	A reference to a knowledge article containing detailed repair information. Online articles are updated more often than this guide can be updated, and should always be referenced for the most up-to-date repair procedures. This field is omitted if no problems are found.
<code>scrub</code>	Identifies the current status of a scrub operation, which might include the date and time that the last scrub was completed, a scrub in progress, or if no scrubbing was requested.
<code>errors</code>	Identifies known data errors or the absence of known data errors.

Configuration Information

The `config` field in the `zpool status` output describes the configuration layout of the devices comprising the pool, as well as their state and any errors generated from the devices. The state can be one of the following: `ONLINE`, `FAULTED`, `DEGRADED`, `UNAVAILABLE`, or `OFFLINE`. If the state is anything but `ONLINE`, the fault tolerance of the pool has been compromised.

The second section of the configuration output displays error statistics. These errors are divided into three categories:

- READ – I/O error occurred while issuing a read request.
- WRITE – I/O error occurred while issuing a write request.
- CKSUM – Checksum error. The device returned corrupted data as the result of a read request.

These errors can be used to determine if the damage is permanent. A small number of I/O errors might indicate a temporary outage, while a large number might indicate a permanent problem with the device. These errors do not necessarily correspond to data corruption as interpreted by applications. If the device is in a redundant configuration, the disk devices might show uncorrectable errors, while no errors appear at the mirror or RAID-Z device level. If this scenario is the case, then ZFS successfully retrieved the good data and attempted to heal the damaged data from existing replicas.

For more information about interpreting these errors to determine device failure, see [“Determining the Type of Device Failure” on page 164](#).

Finally, additional auxiliary information is displayed in the last column of the `zpool status` output. This information expands on the `state` field, aiding in diagnosis of failure modes. If a device is `FAULTED`, this field indicates whether the device is inaccessible or whether the data on the device is corrupted. If the device is undergoing resilvering, this field displays the current progress.

For more information about monitoring resilvering progress, see [“Viewing Resilvering Status” on page 168](#).

Scrubbing Status

The third section of the `zpool status` output describes the current status of any explicit scrubs. This information is distinct from whether any errors are detected on the system, though this information can be used to determine the accuracy of the data corruption error reporting. If the last scrub ended recently, most likely, any known data corruption has been discovered.

For more information about data scrubbing and how to interpret this information, see [“Checking ZFS Data Integrity” on page 155](#).

Data Corruption Errors

The `zpool status` command also shows whether any known errors are associated with the pool. These errors might have been found during disk scrubbing or during normal operation. ZFS maintains a persistent log of all data errors associated with the pool. This log is rotated whenever a complete scrub of the system finishes.

Data corruption errors are always fatal. Their presence indicates that at least one application experienced an I/O error due to corrupt data within the pool. Device errors within a redundant pool do not result in data corruption and are not recorded as part of this log. By default, only the

number of errors found is displayed. A complete list of errors and their specifics can be found by using the `zpool status -v` option. For example:

```
# zpool status -v
pool: tank
state: DEGRADED
status: One or more devices has experienced an error resulting in data
corruption. Applications may be affected.
action: Restore the file in question if possible. Otherwise restore the
entire pool from backup.
see: http://www.sun.com/msg/ZFS-8000-8A
scrub: resilver completed with 1 errors on Fri Mar 17 15:42:18 2006
config:
```

NAME	STATE	READ	WRITE	CKSUM	
tank	DEGRADED	0	0	1	
mirror	DEGRADED	0	0	1	
c1t0d0	ONLINE	0	0	2	
c1t1d0	UNAVAIL	0	0	0	corrupted data

errors: The following persistent errors have been detected:

DATASET	OBJECT	RANGE
5	0	lvl=4294967295 blkid=0

A similar message is also displayed by `cmd` on the system console and the `/var/adm/messages` file. These messages can also be tracked by using the `cmdump` command.

For more information about interpreting data corruption errors, see [“Identifying the Type of Data Corruption” on page 170](#).

System Reporting of ZFS Error Messages

In addition to persistently keeping track of errors within the pool, ZFS also displays syslog messages when events of interest occur. The following scenarios generate events to notify the administrator:

- **Device state transition** – If a device becomes `FAULTED`, ZFS logs a message indicating that the fault tolerance of the pool might be compromised. A similar message is sent if the device is later brought online, restoring the pool to health.
- **Data corruption** – If any data corruption is detected, ZFS logs a message describing when and where the corruption was detected. This message is only logged the first time it is detected. Subsequent accesses do not generate a message.

- **Pool failures and device failures** – If a pool failure or device failure occurs, the fault manager daemon reports these errors through syslog messages as well as the `fmddump` command.

If ZFS detects a device error and automatically recovers from it, no notification occurs. Such errors do not constitute a failure in the pool redundancy or data integrity. Moreover, such errors are typically the result of a driver problem accompanied by its own set of error messages.

Repairing a Damaged ZFS Configuration

ZFS maintains a cache of active pools and their configuration on the root file system. If this file is corrupted or somehow becomes out of sync with what is stored on disk, the pool can no longer be opened. ZFS tries to avoid this situation, though arbitrary corruption is always possible given the qualities of the underlying file system and storage. This situation typically results in a pool disappearing from the system when it should otherwise be available. This situation can also manifest itself as a partial configuration that is missing an unknown number of top-level virtual devices. In either case, the configuration can be recovered by exporting the pool (if it is visible at all), and re-importing it.

For more information about importing and exporting pools, see [“Migrating ZFS Storage Pools” on page 68](#).

Repairing a Missing Device

If a device cannot be opened, it displays as `UNAVAILABLE` in the `zpool status` output. This status means that ZFS was unable to open the device when the pool was first accessed, or the device has since become unavailable. If the device causes a top-level virtual device to be unavailable, then nothing in the pool can be accessed. Otherwise, the fault tolerance of the pool might be compromised. In either case, the device simply needs to be reattached to the system to restore normal operation.

For example, you might see a message similar to the following from `fmdd` after a device failure:

```
SUNW-MSG-ID: ZFS-8000-D3, TYPE: Fault, VER: 1, SEVERITY: Major
EVENT-TIME: Thu Aug 31 11:40:59 MDT 2006
PLATFORM: SUNW,Sun-Blade-1000, CSN: -, HOSTNAME: tank
SOURCE: zfs-diagnosis, REV: 1.0
EVENT-ID: e11d8245-d76a-e152-80c6-e63763ed7e4e
DESC: A ZFS device failed. Refer to http://sun.com/msg/ZFS-8000-D3 for more information.
AUTO-RESPONSE: No automated response will occur.
IMPACT: Fault tolerance of the pool may be compromised.
REC-ACTION: Run 'zpool status -x' and replace the bad device.
```

The next step is to use the `zpool status -x` command to view more detailed information about the device problem and the resolution. For example:

```
# zpool status -x
pool: tank
state: DEGRADED
status: One or more devices could not be opened. Sufficient replicas exist for
the pool to continue functioning in a degraded state.
action: Attach the missing device and online it using 'zpool online'.
see: http://www.sun.com/msg/ZFS-8000-D3
scrub: resilver completed with 0 errors on Thu Aug 31 11:45:59 MDT 2006
config:

NAME          STATE      READ WRITE CKSUM
tank          DEGRADED   0     0     0
  mirror      DEGRADED   0     0     0
    c0t1d0    UNAVAIL    0     0     0  cannot open
    c1t1d0    ONLINE    0     0     0
```

You can see from this output that the missing device `c0t1d0` is not functioning. If you determine that the drive is faulty, replace the device.

Then, use the `zpool online` command to online the replaced device. For example:

```
# zpool online tank c0t1d0
```

Confirm that the pool with the replaced device is healthy.

```
# zpool status -x tank
pool 'tank' is healthy
```

Physically Reattaching the Device

Exactly how a missing device is reattached depends on the device in question. If the device is a network-attached drive, connectivity should be restored. If the device is a USB or other removable media, it should be reattached to the system. If the device is a local disk, a controller might have failed such that the device is no longer visible to the system. In this case, the controller should be replaced at which point the disks will again be available. Other pathologies can exist and depend on the type of hardware and its configuration. If a drive fails and it is no longer visible to the system (an unlikely event), the device should be treated as a damaged device. Follow the procedures outlined in [“Repairing a Damaged Device” on page 164](#).

Notifying ZFS of Device Availability

Once a device is reattached to the system, ZFS might or might not automatically detect its availability. If the pool was previously faulted, or the system was rebooted as part of the attach procedure, then ZFS automatically rescans all devices when it tries to open the pool. If the pool was degraded and the device was replaced while the system was up, you must notify ZFS that the device is now available and ready to be reopened by using the `zpool online` command. For example:

```
# zpool online tank c0t1d0
```

For more information about bringing devices online, see [“Bringing a Device Online” on page 56](#).

Repairing a Damaged Device

This section describes how to determine device failure types, clear transient errors, and replace a device.

Determining the Type of Device Failure

The term *damaged device* is rather vague, and can describe a number of possible situations:

- **Bit rot** – Over time, random events, such as magnetic influences and cosmic rays, can cause bits stored on disk to flip in unpredictable events. These events are relatively rare but common enough to cause potential data corruption in large or long-running systems. These errors are typically transient.
- **Misdirected reads or writes** – Firmware bugs or hardware faults can cause reads or writes of entire blocks to reference the incorrect location on disk. These errors are typically transient, though a large number might indicate a faulty drive.
- **Administrator error** – Administrators can unknowingly overwrite portions of the disk with bad data (such as copying `/dev/zero` over portions of the disk) that cause permanent corruption on disk. These errors are always transient.
- **Temporary outage** – A disk might become unavailable for a period time, causing I/Os to fail. This situation is typically associated with network-attached devices, though local disks can experience temporary outages as well. These errors might or might not be transient.
- **Bad or flaky hardware** – This situation is a catch-all for the various problems that bad hardware exhibits. This could be consistent I/O errors, faulty transports causing random corruption, or any number of failures. These errors are typically permanent.

- **Offline device** – If a device is offline, it is assumed that the administrator placed the device in this state because it is presumed faulty. The administrator who placed the device in this state can determine if this assumption is accurate.

Determining exactly what is wrong can be a difficult process. The first step is to examine the error counts in the `zpool status` output as follows:

```
# zpool status -v pool
```

The errors are divided into I/O errors and checksum errors, both of which might indicate the possible failure type. Typical operation predicts a very small number of errors (just a few over long periods of time). If you are seeing large numbers of errors, then this situation probably indicates impending or complete device failure. However, the pathology for administrator error can result in large error counts. The other source of information is the system log. If the log shows a large number of SCSI or fibre channel driver messages, then this situation probably indicates serious hardware problems. If no syslog messages are generated, then the damage is likely transient.

The goal is to answer the following question:

Is another error likely to occur on this device?

Errors that happen only once are considered *transient*, and do not indicate potential failure. Errors that are persistent or severe enough to indicate potential hardware failure are considered “fatal.” The act of determining the type of error is beyond the scope of any automated software currently available with ZFS, and so much must be done manually by you, the administrator. Once the determination is made, the appropriate action can be taken. Either clear the transient errors or replace the device due to fatal errors. These repair procedures are described in the next sections.

Even if the device errors are considered transient, it still may have caused uncorrectable data errors within the pool. These errors require special repair procedures, even if the underlying device is deemed healthy or otherwise repaired. For more information on repairing data errors, see “[Repairing Damaged Data](#)” on page 169.

Clearing Transient Errors

If the device errors are deemed transient, in that they are unlikely to effect the future health of the device, then the device errors can be safely cleared to indicate that no fatal error occurred. To clear error counters for RAID-Z or mirrored devices, use the `zpool clear` command. For example:

```
# zpool clear tank c1t0d0
```

This syntax clears any errors associated with the device and clears any data error counts associated with the device.

To clear all errors associated with the virtual devices in the pool, and clear any data error counts associated with the pool, use the following syntax:

```
# zpool clear tank
```

For more information about clearing pool errors, see [“Clearing Storage Pool Devices” on page 57](#).

Replacing a Device in a ZFS Storage Pool

If device damage is permanent or future permanent damage is likely, the device must be replaced. Whether the device can be replaced depends on the configuration.

- [“Determining if a Device Can Be Replaced” on page 166](#)
- [“Devices That Cannot be Replaced” on page 167](#)
- [“Replacing a Device in a ZFS Storage Pool” on page 167](#)
- [“Viewing Resilvering Status” on page 168](#)

Determining if a Device Can Be Replaced

For a device to be replaced, the pool must be in the `ONLINE` state. The device must be part of a redundant configuration, or it must be healthy (in the `ONLINE` state). If the disk is part of a redundant configuration, sufficient replicas from which to retrieve good data must exist. If two disks in a four-way mirror are faulted, then either disk can be replaced because healthy replicas are available. However, if two disks in a four-way RAID-Z device are faulted, then neither disk can be replaced because not enough replicas from which to retrieve data exist. If the device is damaged but otherwise online, it can be replaced as long as the pool is not in the `FAULTED` state. However, any bad data on the device is copied to the new device unless there are sufficient replicas with good data.

In the following configuration, the disk `c1t1d0` can be replaced, and any data in the pool is copied from the good replica, `c1t0d0`.

```
mirror          DEGRADED
  c1t0d0         ONLINE
  c1t1d0         FAULTED
```

The disk `c1t0d0` can also be replaced, though no self-healing of data can take place because no good replica is available.

In the following configuration, neither of the faulted disks can be replaced. The `ONLINE` disks cannot be replaced either, because the pool itself is faulted.

```
raidz          FAULTED
  c1t0d0        ONLINE
  c2t0d0        FAULTED
  c3t0d0        FAULTED
  c3t0d0        ONLINE
```

In the following configuration, either top-level disk can be replaced, though any bad data present on the disk is copied to the new disk.

```
c1t0d0        ONLINE
c1t1d0        ONLINE
```

If either disk were faulted, then no replacement could be performed because the pool itself would be faulted.

Devices That Cannot be Replaced

If the loss of a device causes the pool to become faulted, or the device contains too many data errors in a non-redundant configuration, then the device cannot safely be replaced. Without sufficient redundancy, no good data with which to heal the damaged device exists. In this case, the only option is to destroy the pool and re-create the configuration, restoring your data in the process.

For more information about restoring an entire pool, see [“Repairing ZFS Storage Pool-Wide Damage”](#) on page 172.

Replacing a Device in a ZFS Storage Pool

Once you have determined that a device can be replaced, use the `zpool replace` command to replace the device. If you are replacing the damaged device with another different device, use the following command:

```
# zpool replace tank c1t0d0 c2t0d0
```

This command begins migrating data to the new device from the damaged device, or other devices in the pool if it is in a redundant configuration. When the command is finished, it detaches the damaged device from the configuration, at which point the device can be removed from the system. If you have already removed the device and replaced it with a new device in the same location, use the single device form of the command. For example:

```
# zpool replace tank c1t0d0
```

This command takes an unformatted disk, formats it appropriately, and then begins resilvering data from the rest of the configuration.

For more information about the `zpool replace` command, see [“Replacing Devices in a Storage Pool” on page 58](#).

Viewing Resilvering Status

The process of replacing a drive can take an extended period of time, depending on the size of the drive and the amount of data in the pool. The process of moving data from one device to another device is known as *resilvering*, and can be monitored by using the `zpool status` command.

Traditional file systems resilver data at the block level. Because ZFS eliminates the artificial layering of the volume manager, it can perform resilvering in a much more powerful and controlled manner. The two main advantages of this feature are as follows:

- ZFS only resilvers the minimum amount of necessary data. In the case of a short outage (as opposed to a complete device replacement), the entire disk can be resilvered in a matter of minutes or seconds, rather than resilvering the entire disk, or complicating matters with “dirty region” logging that some volume managers support. When an entire disk is replaced, the resilvering process takes time proportional to the amount of data used on disk. Replacing a 500-Gbyte disk can take seconds if only a few gigabytes of used space is in the pool.
- Resilvering is interruptible and safe. If the system loses power or is rebooted, the resilvering process resumes exactly where it left off, without any need for manual intervention.

To view the resilvering process, use the `zpool status` command. For example:

```
# zpool status tank
pool: tank
state: DEGRADED
reason: One or more devices is being resilvered.
action: Wait for the resilvering process to complete.
see: http://www.sun.com/msg/ZFS-XXXX-08
scrub: none requested
config:
  NAME                STATE      READ WRITE CKSUM
  tank                DEGRADED   0     0     0
    mirror            DEGRADED   0     0     0
      replacing       DEGRADED   0     0     0 52% resilvered
        c1t0d0        ONLINE    0     0     0
        c2t0d0        ONLINE    0     0     0
        c1t1d0        ONLINE    0     0     0
```

In this example, the disk `c1t0d0` is being replaced by `c2t0d0`. This event is observed in the status output by presence of the *replacing* virtual device in the configuration. This device is not real,

nor is it possible for you to create a pool by using this virtual device type. The purpose of this device is solely to display the resilvering process, and to identify exactly which device is being replaced.

Note that any pool currently undergoing resilvering is placed in the DEGRADED state, because the pool cannot provide the desired level of redundancy until the resilvering process is complete. Resilvering proceeds as fast as possible, though the I/O is always scheduled with a lower priority than user-requested I/O, to minimize impact on the system. Once the resilvering is complete, the configuration reverts to the new, complete, configuration. For example:

```
# zpool status tank
pool: tank
state: ONLINE
scrub: scrub completed with 0 errors on Thu Aug 31 11:20:18 2006
config:

    NAME        STATE      READ WRITE CKSUM
    tank         ONLINE    0     0     0
      mirror    ONLINE    0     0     0
        c2t0d0  ONLINE    0     0     0
        c1t1d0  ONLINE    0     0     0

errors: No known data errors
```

The pool is once again ONLINE, and the original bad disk (c1t0d0) has been removed from the configuration.

Repairing Damaged Data

The following sections describe how to identify the type of data corruption and how to repair the data, if possible.

- [“Identifying the Type of Data Corruption” on page 170](#)
- [“Repairing a Corrupted File or Directory” on page 171](#)
- [“Repairing ZFS Storage Pool-Wide Damage” on page 172](#)

ZFS uses checksumming, redundancy, and self-healing data to minimize the chances of data corruption. Nonetheless, data corruption can occur if the pool isn't redundant, if corruption occurred while the pool was degraded, or an unlikely series of events conspired to corrupt multiple copies of a piece of data. Regardless of the source, the result is the same: The data is corrupted and therefore no longer accessible. The action taken depends on the type of data being corrupted, and its relative value. Two basic types of data can be corrupted:

- Pool metadata – ZFS requires a certain amount of data to be parsed to open a pool and access datasets. If this data is corrupted, the entire pool or complete portions of the dataset hierarchy will become unavailable.
- Object data – In this case, the corruption is within a specific file or directory. This problem might result in a portion of the file or directory being inaccessible, or this problem might cause the object to be broken altogether.

Data is verified during normal operation as well as through scrubbing. For more information about how to verify the integrity of pool data, see [“Checking ZFS Data Integrity” on page 155](#).

Identifying the Type of Data Corruption

By default, the `zpool status` command shows only that corruption has occurred, but not where this corruption occurred. For example:

```
# zpool status
  pool: monkey
state: ONLINE
status: One or more devices has experienced an error resulting in data
       corruption. Applications may be affected.
action: Restore the file in question if possible.  Otherwise restore the
       entire pool from backup.
       see: http://www.sun.com/msg/ZFS-8000-8A
scrub: none requested
config:
```

NAME	STATE	READ	WRITE	CKSUM
monkey	ONLINE	0	0	0
c1t1d0s6	ONLINE	0	0	0
c1t1d0s7	ONLINE	0	0	0

```
errors: 8 data errors, use '-v' for a list
```

Each error indicates only that an error occurred at the given point in time. Each error is not necessarily still present on the system. Under normal circumstances, this situation is true. Certain temporary outages might result in data corruption that is automatically repaired once the outage ends. A complete scrub of the pool is guaranteed to examine every active block in the pool, so the error log is reset whenever a scrub finishes. If you determine that the errors are no longer present, and you don't want to wait for a scrub to complete, reset all errors in the pool by using the `zpool online` command.

If the data corruption is in pool-wide metadata, the output is slightly different. For example:

```
# zpool status -v morpheus
pool: morpheus
id: 1422736890544688191
state: FAULTED
status: The pool metadata is corrupted.
action: The pool cannot be imported due to damaged devices or data.
see: http://www.sun.com/msg/ZFS-8000-72
config:

    morpheus    FAULTED    corrupted data
    c1t10d0     ONLINE
```

In the case of pool-wide corruption, the pool is placed into the FAULTED state, because the pool cannot possibly provide the needed redundancy level.

Repairing a Corrupted File or Directory

If a file or directory is corrupted, the system might still be able to function depending on the type of corruption. Any damage is effectively unrecoverable. No good copies of the data exist anywhere on the system. If the data is valuable, you have no choice but to restore the affected data from backup. Even so, you might be able to recover from this corruption without restoring the entire pool.

If the damage is within a file data block, then the file can safely be removed, thereby clearing the error from the system. Use the `zpool status -v` command to display a list of filenames with persistent errors. For example:

```
# zpool status -v
pool: monkey
state: ONLINE
status: One or more devices has experienced an error resulting in data
       corruption. Applications may be affected.
action: Restore the file in question if possible. Otherwise restore the
       entire pool from backup.
see: http://www.sun.com/msg/ZFS-8000-8A
scrub: none requested
config:

    NAME        STATE    READ WRITE CKSUM
    monkey      ONLINE    0     0     0
    c1t1d0s6    ONLINE    0     0     0
    c1t1d0s7    ONLINE    0     0     0
```

errors: Permanent errors have been detected in the following files:

```
/monkey/a.txt  
/monkey/bananas/b.txt  
/monkey/sub/dir/d.txt  
/monkey/ghost/e.txt  
/monkey/ghost/boo/f.txt
```

The preceding output is described as follows:

- If the full path to the file is found and the dataset is mounted, the full path to the file is displayed. For example:

```
/monkey/a.txt
```

- If the full path to the file is found, but the dataset is not mounted, then the dataset name with no preceding slash (/), followed by the path within the dataset to the file, is displayed. For example:

```
monkey/ghost:/e.txt
```

- If the object number to a file path cannot be successfully translated, either due to an error or because the object doesn't have a real file path associated with it, as is the case for a `dnode_t`, then the dataset name followed by the object's number is displayed. For example:

```
monkey/dnode:<0x0>
```

- If an object in the meta-object set (MOS) is corrupted, then a special tag of `<metadata>`, followed by the object number, is displayed.

If the corruption is within a directory or a file's metadata, the only choice is to move the file elsewhere. You can safely move any file or directory to a less convenient location, allowing the original object to be restored in place.

Repairing ZFS Storage Pool-Wide Damage

If the damage is in pool metadata that damage prevents the pool from being opened, then you must restore the pool and all its data from backup. The mechanism you use varies widely by the pool configuration and backup strategy. First, save the configuration as displayed by `zpool status` so that you can recreate it once the pool is destroyed. Then, use `zpool destroy -f` to destroy the pool. Also, keep a file describing the layout of the datasets and the various locally set properties somewhere safe, as this information will become inaccessible if the pool is ever rendered inaccessible. With the pool configuration and dataset layout, you can reconstruct your complete configuration after destroying the pool. The data can then be populated by using whatever backup or restoration strategy you use.

Repairing an Unbootable System

ZFS is designed to be robust and stable despite errors. Even so, software bugs or certain unexpected pathologies might cause the system to panic when a pool is accessed. As part of the boot process, each pool must be opened, which means that such failures will cause a system to enter into a panic-reboot loop. In order to recover from this situation, ZFS must be informed not to look for any pools on startup.

ZFS maintains an internal cache of available pools and their configurations in `/etc/zfs/zpool.cache`. The location and contents of this file are private and are subject to change. If the system becomes unbootable, boot to the `none` milestone by using the `-m milestone=none` boot option. Once the system is up, remount your root file system as writable and then remove `/etc/zfs/zpool.cache`. These actions cause ZFS to forget that any pools exist on the system, preventing it from trying to access the bad pool causing the problem. You can then proceed to a normal system state by issuing the `svcadm milestone all` command. You can use a similar process when booting from an alternate root to perform repairs.

Once the system is up, you can attempt to import the pool by using the `zpool import` command. However, doing so will likely cause the same error that occurred during boot, because the command uses the same mechanism to access pools. If more than one pool is on the system and you want to import a specific pool without accessing any other pools, you must re-initialize the devices in the damaged pool, at which point you can safely import the good pool.

Index

A

accessing

- ZFS snapshot
(example of), 109

ACL model, Solaris, differences between ZFS and traditional file systems, 39

ACL property mode

- `aclinherit`, 81
- `aclmode`, 82

`aclinherit` property mode, 122

`aclmode` property mode, 122

ACLs

- access privileges, 120
- ACL inheritance, 121
- ACL inheritance flags, 121
- ACL on ZFS directory
 - detailed description, 125
- ACL on ZFS file
 - detailed description, 124
- ACL property modes, 122
- `aclinherit` property mode, 122
- `aclmode` property mode, 122
- description, 117
- differences from POSIX-draft ACLs, 118
- entry types, 120
- format description, 118
- modifying trivial ACL on ZFS file (verbose mode)
(example of), 126
- restoring trivial ACL on ZFS file (verbose mode)
(example of), 130
- setting ACL inheritance on ZFS file (verbose mode)
(example of), 131

ACLs (Continued)

- setting ACLs on ZFS file (compact mode)
(example of), 140
- description, 139
- setting ACLs on ZFS file (verbose mode)
description, 125
- setting on ZFS files
description, 123

adding

- devices to ZFS storage pool (`zpool add`)
(example of), 52
- ZFS file system to a non-global zone
(example of), 146
- ZFS volume to a non-global zone
(example of), 148

alternate root pools

- creating
(example of), 151
- description, 151
- importing
(example of), 151

`atime` property, description, 82

attaching

- devices to ZFS storage pool (`zpool attach`)
(example of), 53

`available` property, description, 82

C

- `canmount` property, detailed description, 88
- checking, ZFS data integrity, 155

- checksum, definition, 25
- checksum property, description, 82
- checksummed data, description, 24
- clearing
 - a device in a ZFS storage pool (`zpool clear`)
 - description, 57
 - device errors (`zpool clear`)
 - (example of), 165
- clearing a device
 - ZFS storage pool
 - (example of), 57
- clone, definition, 25
- clones
 - creating
 - (example of), 111
 - destroying
 - (example of), 112
 - features, 111
- components of, ZFS storage pool, 41
- components of ZFS, naming requirements, 26
- compression property, description, 82
- `compressratio` property, description, 83
- controlling, data validation (scrubbing), 155
- creating
 - a basic ZFS file system (`zpool create`)
 - (example of), 30
 - a ZFS storage pool (`zpool create`)
 - (example of), 30
 - alternate root pools
 - (example of), 151
 - double-parity RAID-Z storage pool (`zpool create`)
 - (example of), 47
 - emulated volume
 - (example of), 143
 - emulated volume as swap device
 - (example of), 144
 - mirrored ZFS storage pool (`zpool create`)
 - (example of), 47
 - single-parity RAID-Z storage pool (`zpool create`)
 - (example of), 47
 - ZFS clone
 - (example of), 111
 - ZFS file system, 33
 - (example of), 78

- creating, ZFS file system (*Continued*)
 - description, 78
 - ZFS file system hierarchy, 32
 - ZFS snapshot
 - (example of), 108
 - ZFS storage pool
 - description, 46
 - ZFS storage pool (`zpool create`)
 - (example of), 46
- creation property, description, 83

D

- data
 - corrupted, 154
 - corruption identified (`zpool status -v`)
 - (example of), 161
 - repair, 155
 - resilvering
 - description, 157
 - scrubbing
 - (example of), 156
 - validation (scrubbing), 155
- dataset
 - definition, 25
 - description, 77
- dataset types, description, 91
- delegating
 - dataset to a non-global zone
 - (example of), 147
- destroying
 - ZFS clone
 - (example of), 112
 - ZFS file system
 - (example of), 79
 - ZFS file system with dependents
 - (example of), 79
 - ZFS snapshot
 - (example of), 109
 - ZFS storage pool
 - description, 46
 - ZFS storage pool (`zpool destroy`)
 - (example of), 50

- detaching
 - devices to ZFS storage pool (`zpool detach`)
 - (example of), 55
- detecting
 - in-use devices
 - (example of), 48
 - mismatched replication levels
 - (example of), 49
- determining
 - if a device can be replaced
 - description, 166
 - type of device failure
 - description, 164
- devices property, description, 83
- differences between ZFS and traditional file systems
 - file system granularity, 37
 - mounting ZFS file systems, 39
 - new Solaris ACL Model, 39
 - out of space behavior, 38
 - traditional volume management, 39
 - ZFS space accounting, 38
- disks, as components of ZFS storage pools, 42
- displaying
 - detailed ZFS storage pool health status
 - (example of), 67
 - health status of storage pools
 - description of, 66
 - syslog reporting of ZFS error messages
 - description, 161
 - ZFS storage pool health status
 - (example of), 66
 - ZFS storage pool I/O statistics
 - description, 64
 - ZFS storage pool vdev I/O statistics
 - (example of), 65
 - ZFS storage pool-wide I/O statistics
 - (example of), 64
- dry run
 - ZFS storage pool creation (`zpool create -n`)
 - (example of), 50
- dynamic striping
 - description, 45
 - storage pool feature, 45

E

- EFI label
 - description, 42
 - interaction with ZFS, 42
- emulated volume
 - as swap device, 144
 - description, 143
- exec property, description, 83
- exporting
 - ZFS storage pool
 - (example of), 69

F

- failure modes, 153
 - corrupted data, 154
 - damaged devices, 154
 - missing (faulted) devices, 154
- file system, definition, 25
- file system granularity, differences between ZFS and traditional file systems, 37
- file system hierarchy, creating, 32
- files, as components of ZFS storage pools, 43

H

- hardware and software requirements, 29
- hot spares
 - creating
 - (example of), 58
 - description of
 - (example of), 58

I

- identifying
 - storage requirements, 31
 - type of data corruption (`zpool status -v`)
 - (example of), 170
 - ZFS storage pool for import (`zpool import -a`)
 - (example of), 70

importing

- alternate root pools
 - (example of), 151
- ZFS storage pool
 - (example of), 73
- ZFS storage pool from alternate directories (`zpool import -d`)
 - (example of), 72

in-use devices

- detecting
 - (example of), 48

inheriting

- ZFS properties (`zfs inherit`)
 - description, 93

L

listing

- descendants of ZFS file systems
 - (example of), 91
- types of ZFS file systems
 - (example of), 92
- ZFS file systems
 - (example of), 90
- ZFS file systems (`zfs list`)
 - (example of), 35
- ZFS file systems without header information
 - (example of), 92
- ZFS pool information, 32
- ZFS properties (`zfs list`)
 - (example of), 94
- ZFS properties by source value
 - (example of), 96
- ZFS properties for scripting
 - (example of), 96
- ZFS storage pools
 - (example of), 63
 - description, 62

M

- migrating ZFS storage pools, description, 68
- mirror, definition, 25

mirrored configuration

- conceptual view, 44
- description, 44
- redundancy feature, 44

mirrored storage pool (`zpool create`), (example of), 47

mismatched replication levels

- detecting
 - (example of), 49

modifying

- trivial ACL on ZFS file (verbose mode)
 - (example of), 126

mount points

- automatic, 98
- legacy, 97
- managing ZFS
 - description, 97

mounted property, description, 83

mounting

- ZFS file systems
 - (example of), 100

mounting ZFS file systems, differences between ZFS and traditional file systems, 39

mountpoint

- default for ZFS file system, 78
- default for ZFS storage pools, 50

mountpoint property, description, 83

N

naming requirements, ZFS components, 26

NFSv4 ACLs

- ACL inheritance, 121
- ACL inheritance flags, 121
- ACL property modes, 122
- differences from POSIX-draft ACLs, 118
- format description, 118
- model
 - description, 117

notifying

- ZFS of reattached device (`zpool online`)
 - (example of), 164

O

- offlining a device (zpool offline)
 - ZFS storage pool
 - (example of), 56
- onlining a device
 - ZFS storage pool (zpool online)
 - (example of), 57
- onlining and offlining devices
 - ZFS storage pool
 - description, 55
- origin property, description, 83
- out of space behavior, differences between ZFS and traditional file systems, 38

P

- pool, definition, 26
- pooled storage, description, 23
- POSIX-draft ACLs, description, 118
- properties of ZFS
 - description, 81
 - description of heritable properties, 81

Q

- quota property, description, 84
- quotas and reservations, description, 103

R

- RAID-Z, definition, 26
- RAID-Z configuration
 - (example of), 47
 - conceptual view, 44
 - double-parity, description, 44
 - redundancy feature, 44
 - single-parity, description, 44
- read-only properties of ZFS
 - available, 82
 - compression, 83
 - creation, 83
 - description, 86
- read-only properties of ZFS (*Continued*)
 - mounted, 83
 - origin, 83
 - referenced, 84
 - type, 85
 - used, 85
- read-only property, description, 84
- recordsize property
 - description, 84
 - detailed description, 88
- recovering
 - destroyed ZFS storage pool
 - (example of), 74
- referenced property, description, 84
- renaming
 - ZFS file system
 - (example of), 80
 - ZFS snapshot
 - (example of), 109
- repairing
 - a damaged ZFS configuration
 - description, 162
 - an unbootable system
 - description, 173
 - pool-wide damage
 - description, 172
 - repairing a corrupted file or directory
 - description, 171
- replacing
 - a device (zpool replace)
 - (example of), 58, 167, 168
 - a missing device
 - (example of), 162
- replication features of ZFS, mirrored or RAID-Z, 44
- reservation property, description, 84
- resilvering, definition, 26
- resilvering and data scrubbing, description, 157
- restoring
 - trivial ACL on ZFS file (verbose mode)
 - (example of), 130
 - ZFS file system data (zfs receive)
 - (example of), 115

- rights profiles
 - for management of ZFS file systems and storage pools
 - description, 152
- rolling back
 - ZFS snapshot
 - (example of), 110

S

- saving
 - ZFS file system data (`zfs send`)
 - (example of), 114
- saving and restoring
 - ZFS file system data
 - description, 113
- scripting
 - ZFS storage pool output
 - (example of), 63
- scrubbing
 - (example of), 156
 - data validation, 155
- self-healing data, description, 45
- settable properties of ZFS
 - `aclinherit`, 81
 - `aclmode`, 82
 - `atime`, 82
 - `canmount`
 - detailed description, 88
 - `checksum`, 82
 - `compression`, 82
 - description, 87
 - devices, 83
 - `exec`, 83
 - mountpoint, 83
 - quota, 84
 - read-only, 84
 - `recordsize`, 84
 - detailed description, 88
 - reservation, 84
 - `setuid`, 85
 - `sharenfs`, 85
 - `snapdir`, 85

- settable properties of ZFS (*Continued*)
 - `used`
 - detailed description, 86
 - `volblocksize`, 85
 - `volsize`, 85
 - detailed description, 89
 - `xattr`, 85
 - `zoned`, 85
- setting
 - ACL inheritance on ZFS file (verbose mode)
 - (example of), 131
 - ACLs on ZFS file (compact mode)
 - (example of), 140
 - description, 139
 - ACLs on ZFS file (verbose mode)
 - (description, 125
 - ACLs on ZFS files
 - description, 123
 - compression property
 - (example of), 34
 - legacy mount points
 - (example of), 99
 - mountpoint property, 34
 - quota property (example of), 34
 - `sharenfs` property
 - (example of), 34
 - ZFS `atime` property
 - (example of), 93
 - ZFS file system quota (`zfs set quota`)
 - example of, 103
 - ZFS file system reservation
 - (example of), 104
 - ZFS mount points (`zfs set mountpoint`)
 - (example of), 98
 - ZFS quota
 - (example of), 93
- `setuid` property, description, 85
- `sharenfs` property
 - description, 85, 102
- sharing
 - ZFS file systems
 - description, 102
 - example of, 102
- simplified administration, description, 25

- snapdir property, description, 85
 - snapshot
 - accessing
 - (example of), 109
 - creating
 - (example of), 108
 - definition, 26
 - destroying
 - (example of), 109
 - features, 107
 - renaming
 - (example of), 109
 - rolling back
 - (example of), 110
 - space accounting, 110
 - Solaris ACLs
 - ACL inheritance, 121
 - ACL inheritance flags, 121
 - ACL property modes, 122
 - differences from POSIX-draft ACLs, 118
 - format description, 118
 - new model
 - description, 117
 - storage requirements, identifying, 31
- T**
- terminology
 - checksum, 25
 - clone, 25
 - dataset, 25
 - file system, 25
 - mirror, 25
 - pool, 26
 - RAID-Z, 26
 - resilvering, 26
 - snapshot, 26
 - virtual device, 26
 - volume, 26
 - traditional volume management, differences between
 - ZFS and traditional file systems, 39
 - transactional semantics, description, 23
 - troubleshooting
 - clear device errors (zpool clear)
 - (example of), 165
 - damaged devices, 154
 - data corruption identified (zpool status -v)
 - (example of), 161
 - determining if a device can be replaced
 - description, 166
 - determining if problems exist (zpool status -x), 158
 - determining type of data corruption (zpool status -v)
 - (example of), 170
 - determining type of device failure
 - description, 164
 - identifying problems, 157
 - missing (faulted) devices, 154
 - notifying ZFS of reattached device (zpool online)
 - (example of), 164
 - overall pool status information
 - description, 159
 - repairing a corrupted file or directory
 - description, 171
 - repairing a damaged ZFS configuration, 162
 - repairing an unbootable system
 - description, 173
 - repairing pool-wide damage
 - description, 172
 - replacing a device (zpool replace)
 - (example of), 167, 168
 - replacing a missing device
 - (example of), 162
 - syslog reporting of ZFS error messages, 161
 - ZFS failure modes, 153
 - type property, description, 85
- U**
- unmounting
 - ZFS file systems
 - (example of), 101
 - unsharing
 - ZFS file systems
 - example of, 102

upgrading

- ZFS storage pool
 - description, 75

used property

- description, 85
- detailed description, 86

user properties of ZFS

- (example of), 89
- detailed description, 89

V

virtual device, definition, 26

virtual devices, as components of ZFS storage pools, 43

volblocksize property, description, 85

volsize property

- description, 85
- detailed description, 89

volume, definition, 26

W

whole disks, as components of ZFS storage pools, 42

X

xattr property, description, 85

Z

zfs create

- (example of), 33, 78
- description, 78

zfs destroy, (example of), 79

zfs destroy -r, (example of), 79

ZFS file system, description, 77

ZFS file systems

- ACL on ZFS directory
 - detailed description, 125
- ACL on ZFS file
 - detailed description, 124

ZFS file systems (*Continued*)

adding ZFS file system to a non-global zone
(example of), 146

adding ZFS volume to a non-global zone
(example of), 148

checksum

definition, 25

checksummed data
description, 24

clone

creating, 111

destroying, 112

replacing a file system with (example of), 112

clones

definition, 25

description, 111

component naming requirements, 26

creating

(example of), 78

creating an emulated volume

(example of), 143

creating an emulated volume as swap device

(example of), 144

dataset

definition, 25

dataset types

description, 91

default mountpoint

(example of), 78

delegating dataset to a non-global zone

(example of), 147

description, 22

destroying

(example of), 79

destroying with dependents

(example of), 79

file system

definition, 25

inheriting property of (`zfs inherit`)

(example of), 93

listing

(example of), 90

listing descendants

(example of), 91

ZFS file systems (*Continued*)

- listing properties by source value
 - (example of), 96
- listing properties for scripting
 - (example of), 96
- listing properties of (`zfs list`)
 - (example of), 94
- listing types of
 - (example of), 92
- listing without header information
 - (example of), 92
- managing automatic mount points, 98
- managing legacy mount points
 - description, 97
- managing mount points
 - description, 97
- modifying trivial ACL on ZFS file (verbose mode)
 - (example of), 126
- mounting
 - (example of), 100
- pooled storage
 - description, 23
- property management within a zone
 - description, 148
- renaming
 - (example of), 80
- restoring data streams (`zfs receive`)
 - (example of), 115
- restoring trivial ACL on ZFS file (verbose mode)
 - (example of), 130
- rights profiles, 152
- saving and restoring
 - description, 113
- saving data streams (`zfs send`)
 - (example of), 114
- setting a reservation
 - (example of), 104
- setting ACL inheritance on ZFS file (verbose mode)
 - (example of), 131
- setting ACLs on ZFS file (compact mode)
 - (example of), 140
 - description, 139
- setting ACLs on ZFS file (verbose mode)
 - description, 125

ZFS file systems (*Continued*)

- setting ACLs on ZFS files
 - description, 123
- setting a time property
 - (example of), 93
- setting legacy mount point
 - (example of), 99
- setting mount point (`zfs set mountpoint`)
 - (example of), 98
- setting quota property
 - (example of), 93
- sharing
 - description, 102
 - example of, 102
- simplified administration
 - description, 25
- snapshot
 - accessing, 109
 - creating, 108
 - definition, 26
 - description, 107
 - destroying, 109
 - renaming, 109
 - rolling back, 110
- snapshot space accounting, 110
- transactional semantics
 - description, 23
- unmounting
 - (example of), 101
- unsharing
 - example of, 102
- using on a Solaris system with zones installed
 - description, 146
- volume
 - definition, 26
- ZFS file systems (`zfs set quota`)
 - setting a quota
 - example of, 103
- `zfs get`, (example of), 94
- `zfs get -H -o`, (example of), 96
- `zfs get -s`, (example of), 96
- `zfs inherit`, (example of), 93
- `zfs list`
 - (example of), 35, 90

- zfs list -H, (example of), 92
- zfs list -r, (example of), 91
- zfs list -t, (example of), 92
- zfs mount, (example of), 100
- zfs promote, clone promotion (example of), 112
- ZFS properties
 - aclinherit, 81
 - aclmode, 82
 - atime, 82
 - available, 82
 - canmount
 - detailed description, 88
 - checksum, 82
 - compression, 82
 - compressratio, 83
 - creation, 83
 - description, 81
 - devices, 83
 - exec, 83
 - inheritable, description of, 81
 - management within a zone
 - description, 148
 - mounted, 83
 - mountpoint, 83
 - origin, 83
 - quota, 84
 - read-only, 84
 - read-only, 86
 - recordsize, 84
 - detailed description, 88
 - referenced, 84
 - reservation, 84
 - settable, 87
 - setuid, 85
 - sharenfs, 85
 - snapsdir, 85
 - type, 85
 - used, 85
 - detailed description, 86
 - user properties
 - detailed description, 89
 - volblocksize, 85
 - volsize, 85
 - detailed description, 89
- ZFS properties (*Continued*)
 - xattr, 85
 - zoned, 85
 - zoned property
 - detailed description, 150
 - zfs receive, (example of), 115
 - zfs rename, (example of), 80
 - zfs send, (example of), 114
 - zfs set atime, (example of), 93
 - zfs set compression, (example of), 34
 - zfs set mountpoint
 - (example of), 34, 98
 - zfs set mountpoint=legacy, (example of), 99
 - zfs set quota
 - (example of), 34
 - zfs set quota, (example of), 93
 - zfs set quota
 - example of, 103
 - zfs set reservation, (example of), 104
 - zfs set sharenfs, (example of), 34
 - zfs set sharenfs=on, example of, 102
- ZFS space accounting, differences between ZFS and traditional file systems, 38
- ZFS storage pools
 - adding devices to (zpool add)
 - (example of), 52
 - alternate root pools, 151
 - attaching devices to (zpool attach)
 - (example of), 53
 - clearing a device
 - (example of), 57
 - clearing device errors (zpool clear)
 - (example of), 165
 - components, 41
 - corrupted data
 - description, 154
 - creating (zpool create)
 - (example of), 46
 - creating a RAID-Z configuration (zpool create)
 - (example of), 47
 - creating mirrored configuration (zpool create)
 - (example of), 47
 - damaged devices
 - description, 154

ZFS storage pools (*Continued*)

- data corruption identified (`zpool status -v`)
 - (example of), 161
- data repair
 - description, 155
- data scrubbing
 - (example of), 156
 - description, 155
- data scrubbing and resilvering
 - description, 157
- data validation
 - description, 155
- default mountpoint, 50
- destroying (`zpool destroy`)
 - (example of), 50
- detaching devices from (`zpool detach`)
 - (example of), 55
- determining if a device can be replaced
 - description, 166
- determining if problems exist (`zpool status -x`)
 - description, 158
- determining type of device failure
 - description, 164
- displaying detailed health status
 - (example of), 67
- displaying health status, 66
 - (example of), 66
- doing a dry run (`zpool create -n`)
 - (example of), 50
- dynamic striping, 45
- exporting
 - (example of), 69
- failure modes, 153
- identifying for import (`zpool import -a`)
 - (example of), 70
- identifying problems
 - description, 157
- identifying type of data corruption (`zpool status -v`)
 - (example of), 170
- importing
 - (example of), 73
- importing from alternate directories (`zpool import -d`)

ZFS storage pools, importing from alternate directories (`zpool import -d`) (*Continued*)

- (example of), 72
- listing
 - (example of), 63
- migrating
 - description, 68
- mirror
 - definition, 25
- mirrored configuration, description of, 44
- missing (faulted) devices
 - description, 154
- notifying ZFS of reattached device (`zpool online`)
 - (example of), 164
- offlining a device (`zpool offline`)
 - (example of), 56
- onlining and offlining devices
 - description, 55
- overall pool status information for troubleshooting
 - description, 159
- pool
 - definition, 26
- pool-wide I/O statistics
 - (example of), 64
- RAID-Z
 - definition, 26
- RAID-Z configuration, description of, 44
- recovering a destroyed pool
 - (example of), 74
- repairing a corrupted file or directory
 - description, 171
- repairing a damaged ZFS configuration, 162
- repairing an unbootable system
 - description, 173
- repairing pool-wide damage
 - description, 172
- replacing a device (`zpool replace`)
 - (example of), 58, 167
- replacing a missing device
 - (example of), 162
- resilvering
 - definition, 26
- rights profiles, 152

ZFS storage pools (*Continued*)

- scripting storage pool output
 - (example of), 63
- system error messages
 - description, 161
- upgrading
 - description, 75
- using files, 43
- using whole disks, 42
- vdev I/O statistics
 - (example of), 65
- viewing resilvering process
 - (example of), 168
- virtual device
 - definition, 26
- virtual devices, 43
- ZFS storage pools (zpool online)
 - onlining a device
 - (example of), 57
- zfs unmount, (example of), 101
- zoned property
 - description, 85
 - detailed description, 150
- zones
 - adding ZFS file system to a non-global zone
 - (example of), 146
 - adding ZFS volume to a non-global zone
 - (example of), 148
 - delegating dataset to a non-global zone
 - (example of), 147
 - using with ZFS file systems
 - description, 146
 - ZFS property management within a zone
 - description, 148
 - zoned property
 - detailed description, 150
- zpool add, (example of), 52
- zpool attach, (example of), 53
- zpool clear
 - (example of), 57
 - description, 57
- zpool create
 - (example of), 30, 32

zpool create (*Continued*)

- basic pool
 - (example of), 46
- mirrored storage pool
 - (example of), 47
- RAID-Z storage pool
 - (example of), 47
- zpool create -n
 - dry run
 - (example of), 50
- zpool destroy, (example of), 50
- zpool detach, (example of), 55
- zpool export, (example of), 69
- zpool import -a, (example of), 70
- zpool import -D, (example of), 74
- zpool import -d, (example of), 72
- zpool import *name*, (example of), 73
- zpool iostat, pool-wide (example of), 64
- zpool iostat -v, vdev (example of), 65
- zpool list
 - (example of), 32, 63
 - description, 62
- zpool list -Ho name, (example of), 63
- zpool offline, (example of), 56
- zpool online, (example of), 57
- zpool replace, (example of), 58
- zpool status -v, (example of), 67
- zpool status -x, (example of), 66
- zpool upgrade, 75